

QuTiP: Quantum Toolbox in Python

Release 5.0.0a1

P.D. Nation, J.R. Johansson, A.J.G. Pitchford, C. Granade, A.L. C.

Feb 07, 2023

Contents

1	Frontmatter	3
1.1	About This Documentation	3
1.2	Citing This Project	4
1.3	Funding	4
1.4	About QuTiP	5
1.5	QuTiP Plugins	6
1.6	Libraries Using QuTiP	6
1.7	Contributing to QuTiP	6
2	Installation	7
2.1	Quick Start	7
2.2	General Requirements	7
2.3	Installing with conda	8
2.3.1	Adding the conda-forge channel	8
2.3.2	New conda environments	8
2.4	Installing from Source	9
2.4.1	PEP 517 Source Builds	9
2.4.2	Direct Setuptools Source Builds	9
2.5	Installation on Windows	10
2.6	Verifying the Installation	10
2.7	Checking Version Information	11
3	Users Guide	13
3.1	Guide Overview	13
3.1.1	Organization	13
3.2	Basic Operations on Quantum Objects	14
3.2.1	First things first	14
3.2.2	The quantum object class	15
3.2.3	Functions operating on Qobj class	20
3.3	Manipulating States and Operators	23
3.3.1	Introduction	23
3.3.2	State Vectors (kets or bras)	23
3.3.3	Density matrices	27
3.3.4	Qubit (two-level) systems	29
3.3.5	Expectation values	31
3.3.6	Superoperators and Vectorized Operators	33
3.3.7	Choi, Kraus, Stinespring and χ Representations	36
3.3.8	Properties of Quantum Maps	42
3.4	Using Tensor Products and Partial Traces	43
3.4.1	Tensor products	43
3.4.2	Example: Constructing composite Hamiltonians	45
3.4.3	Partial trace	48
3.4.4	Superoperators and Tensor Manipulations	49
3.5	Time Evolution and Quantum System Dynamics	50
3.5.1	Introduction	50
3.5.2	Dynamics Simulation Results	50
3.5.3	Lindblad Master Equation Solver	52


3.5.4	Monte Carlo Solver	60
3.5.5	Krylov Solver	67
3.5.6	Stochastic Solver - Photocurrent	69
3.5.7	Stochastic Solver	70
3.5.8	Solving Problems with Time-dependent Hamiltonians	73
3.5.9	Bloch-Redfield master equation	80
3.5.10	Floquet Formalism	87
3.5.11	Permutational Invariance	96
3.5.12	Setting Options for the Dynamics Solvers	97
3.6	Hierarchical Equations of Motion	98
3.6.1	Introduction	98
3.6.2	Describing the system and bath	99
3.6.3	System and bath dynamics	100
3.6.4	Steady-state	102
3.6.5	Matsubara Terminator	102
3.6.6	Matsubara expansion coefficients	102
3.6.7	Multiple baths	104
3.6.8	Fermionic Environments	105
3.6.9	Previous implementations	115
3.6.10	References	115
3.7	Solving for Steady-State Solutions	116
3.7.1	Introduction	116
3.7.2	Steady State solvers in QuTiP	116
3.7.3	Using the Steadystate Solver	117
3.7.4	Additional Solver Arguments	118
3.7.5	Example: Harmonic Oscillator in Thermal Bath	118
3.8	Two-time correlation functions	120
3.8.1	Steadystate correlation function	120
3.8.2	Emission spectrum	122
3.8.3	Non-steadystate correlation function	124
3.9	Quantum Optimal Control	128
3.9.1	Introduction	128
3.9.2	Closed Quantum Systems	128
3.9.3	The GRAPE algorithm	129
3.9.4	The CRAB Algorithm	130
3.9.5	Optimal Quantum Control in QuTiP	131
3.9.6	Using the pulseoptim functions	132
3.10	Plotting on the Bloch Sphere	132
3.10.1	Introduction	132
3.10.2	The Bloch and Bloch3d Classes	133
3.10.3	Configuring the Bloch sphere	147
3.10.4	Animating with the Bloch sphere	149
3.11	Visualization of quantum states and processes	151
3.11.1	Fock-basis probability distribution	151
3.11.2	Quasi-probability distributions	152
3.11.3	Visualizing operators	155
3.11.4	Quantum process tomography	157
3.12	Parallel computation	159
3.12.1	Parallel map and parallel for-loop	159
3.12.2	IPython-based parallel_map	161
3.13	Saving QuTiP Objects and Data Sets	161
3.13.1	Storing and loading QuTiP objects	161
3.13.2	Storing and loading datasets	162
3.14	Generating Random Quantum States & Operators	164
3.14.1	Random objects with a given eigen spectrum	166
3.14.2	Composite random objects	166
3.14.3	Controlling the random number generator	167
3.14.4	Internal matrix format	167

3.15	Modifying Internal QuTiP Settings	167
3.15.1	User Accessible Parameters	167
3.15.2	Example: Changing Settings	167
3.16	Measurement of Quantum Objects	168
3.16.1	Introduction	168
3.16.2	Performing a basic measurement (Observable)	168
3.16.3	Performing a basic measurement (Projective)	169
3.16.4	Obtaining measurement statistics(Observable)	170
3.16.5	Obtaining measurement statistics(Projective)	171
4	Gallery	173
5	API documentation	175
5.1	Classes	175
5.1.1	Qobj	175
5.1.2	QobjEvo	184
5.1.3	Bloch sphere	188
5.1.4	Distributions	193
5.1.5	Solver	194
5.1.6	Non-Markovian HEOM Solver	196
5.1.7	Integrator	206
5.1.8	Non-Markovian Memory Cascade and Transfer Tensor Solvers	209
5.1.9	Solver Options and Results	211
5.1.10	Permutational Invariance	212
5.1.11	Distribution functions	216
5.1.12	Optimal control	217
5.2	Functions	238
5.2.1	Manipulation and Creation of States and Operators	238
5.2.2	Functions acting on states and operators	270
5.2.3	Measurement	279
5.2.4	Dynamics and Time-Evolution	282
5.2.5	Visualization	313
5.2.6	Non-Markovian Solvers	324
5.2.7	Optimal control	325
5.2.8	Utility Functions	339
6	Change Log	343
6.1	Version 5.0.0a1 (February 7, 2023)	343
6.1.1	Contributors	343
6.1.2	Qobj changes	344
6.1.3	QobjEvo changes	345
6.1.4	Solver changes	345
6.1.5	QuTiP core	347
6.1.6	QuTiP settings	348
6.1.7	Package reorganization	348
6.1.8	Miscellaneous	348
6.1.9	Feature removals	349
6.2	Version 4.7.1 (December 11, 2022)	349
6.2.1	Features	349
6.2.2	Bug Fixes	349
6.2.3	Documentation	350
6.2.4	Miscellaneous	350
6.3	Version 4.7.0 (April 13, 2022)	350
6.3.1	Improvements	350
6.3.2	Bug Fixes	351
6.3.3	Documentation Improvements	352
6.3.4	Developer Changes	352
6.4	Version 4.6.3 (February 9, 2022)	353
6.4.1	Improvements	353

6.4.2	Bug Fixes	353
6.4.3	Documentation Improvements	354
6.4.4	Developer Changes	354
6.5	Version 4.6.2 (June 2, 2021)	355
6.5.1	Improvements	355
6.5.2	Bug Fixes	355
6.5.3	Developer Changes	355
6.6	Version 4.6.1 (May 4, 2021)	356
6.6.1	Improvements	356
6.6.2	Bug Fixes	356
6.6.3	Developer Changes	356
6.7	Version 4.6.0 (April 11, 2021)	356
6.7.1	Improvements	356
6.7.2	Bug Fixes	357
6.7.3	Deprecations	357
6.7.4	Developer Changes	358
6.8	Version 4.5.3 (February 19, 2021)	358
6.8.1	Improvements	358
6.9	Version 4.5.2 (July 14, 2020)	358
6.9.1	Improvements	358
6.9.2	Bug Fixes	359
6.9.3	Developer Changes	359
6.10	Version 4.5.1 (May 15, 2020)	359
6.10.1	Improvements	359
6.10.2	Bug Fixes	359
6.10.3	Deprecations	359
6.10.4	Developer Changes	359
6.11	Version 4.5.0 (January 31, 2020)	360
6.11.1	Improvements	360
6.11.2	Bug Fixes	360
6.12	Version 4.4.1 (August 29, 2019)	361
6.12.1	Improvements	361
6.12.2	Bug Fixes	361
6.13	Version 4.4.0 (July 03, 2019)	361
6.13.1	Improvements	361
6.13.2	Bug Fixes	362
6.14	Version 4.3.0 (July 14, 2018)	362
6.14.1	Improvements	362
6.14.2	Bug Fixes	362
6.15	Version 4.2.0 (July 28, 2017)	363
6.15.1	Improvements	363
6.15.2	Bug Fixes	363
6.16	Version 4.1.0 (March 10, 2017)	363
6.16.1	Improvements	363
6.16.2	Bug Fixes	364
6.17	Version 4.0.2 (January 5, 2017)	364
6.17.1	Bug Fixes	364
6.18	Version 4.0.0 (December 22, 2016)	364
6.18.1	Improvements	364
6.18.2	Bug Fixes	364
6.19	Version 3.2.0 (Never officially released)	364
6.19.1	New Features	364
6.19.2	Improvements	365
6.19.3	Bug Fixes	366
6.20	Version 3.1.0 (January 1, 2015)	367
6.20.1	New Features	367
6.20.2	Bug Fixes	367
6.21	Version 3.0.1 (Aug 5, 2014)	368

6.21.1	Bug Fixes	368
6.22	Version 3.0.0 (July 17, 2014)	368
6.22.1	New Features	368
6.22.2	Improvements	369
6.23	Version 2.2.0 (March 01, 2013)	369
6.23.1	New Features	369
6.23.2	Bug Fixes	370
6.24	Version 2.1.0 (October 05, 2012)	370
6.24.1	New Features	370
6.24.2	Bug Fixes	370
6.25	Version 2.0.0 (June 01, 2012)	371
6.25.1	New Features	371
6.26	Version 1.1.4 (May 28, 2012)	372
6.26.1	Bug Fixes	372
6.27	Version 1.1.3 (November 21, 2011)	372
6.27.1	New Functions	372
6.27.2	Bug Fixes	372
6.28	Version 1.1.2 (October 27, 2011)	372
6.28.1	Bug Fixes	372
6.29	Version 1.1.1 (October 25, 2011)	372
6.29.1	New Functions	372
6.29.2	Bug Fixes	373
6.30	Version 1.1.0 (October 04, 2011)	373
6.30.1	New Functions	373
6.30.2	Bug Fixes	373
6.31	Version 1.0.0 (July 29, 2011)	373
7	Developers	375
7.1	Lead Developers	376
7.2	Past Lead Developers	376
7.3	Contributors	376
8	Development Documentation	379
8.1	Contributing to QuTiP Development	379
8.1.1	Quick Start	379
8.1.2	Core Library: qutip/qutip	380
8.1.3	Documentation: qutip/qutip (doc directory)	382
8.2	QuTiP Development Roadmap	383
8.2.1	Preamble	383
8.2.2	Library package structure	384
8.2.3	Development Projects	386
8.2.4	Completed Development Projects	388
8.2.5	QuTiP major release roadmap	390
8.3	Ideas for future QuTiP development	390
8.3.1	QuTiP Interactive	390
8.3.2	Pulse level description of quantum circuits	391
8.3.3	Quantum Error Mitigation	393
8.3.4	GPU implementation of the Hierarchical Equations of Motion	394
8.3.5	Google Summer of Code	395
8.3.6	Completed Projects	395
8.4	Working with the QuTiP Documentation	397
8.4.1	Directives	397
8.5	Release and Distribution	400
8.5.1	Preamble	400
8.5.2	Setting Up The Release Branch	400
8.5.3	Build Release Distribution and Deploy	403
8.5.4	Getting the Built Documentation	405
8.5.5	Making a Release on GitHub	405

8.5.6	Website	405
8.5.7	Conda Forge	406
9	Bibliography	409
10	Copyright and Licensing	411
10.1	License Terms for Documentation Text	411
10.2	License Terms for Source Code of QuTiP and Code Samples	415
11	Indices and tables	417
	Bibliography	419
	Python Module Index	421
	Index	423



Chapter 1

Frontmatter

1.1 About This Documentation

This document contains a user guide and automatically generated API documentation for QuTiP. A PDF version of this text is available at the [documentation page](#).

For more information see the [QuTiP project web page](#).

Author J.R. Johansson

Author P.D. Nation

Author Alexander Pitchford

Author Arne Grimsmo

Author Chris Grenade

Author Nathan Shammah

Author Shahnawaz Ahmed

Author Neill Lambert

Author Eric Giguere

Author Boxi Li

Author Jake Lishman

Author Simon Cross

release 5.0.0a1

copyright The text of this documentation is licensed under the Creative Commons Attribution 3.0 Unported License. All contained code samples, and the source code of QuTiP, are licensed under the 3-clause BSD licence. Full details of the copyright notices can be found on the [Copyright and Licensing](#) page of this documentation.

1.2 Citing This Project

If you find this project useful, then please cite:

J. R. Johansson, P.D. Nation, and F. Nori, “QuTiP 2: A Python framework for the dynamics of open quantum systems”, *Comp. Phys. Comm.* **184**, 1234 (2013).

or

J. R. Johansson, P.D. Nation, and F. Nori, “QuTiP: An open-source Python framework for the dynamics of open quantum systems”, *Comp. Phys. Comm.* **183**, 1760 (2012).

which may also be downloaded from <https://arxiv.org/abs/1211.6518> or <https://arxiv.org/abs/1110.0573>, respectively.

1.3 Funding

QuTiP is developed under the auspice of the non-profit organizations:



QuTiP was partially supported by



日本学術振興会
Japan Society for the Promotion of Science



고려대학교
KOREA UNIVERSITY



1.4 About QuTiP

Every quantum system encountered in the real world is an open quantum system. For although much care is taken experimentally to eliminate the unwanted influence of external interactions, there remains, if ever so slight, a coupling between the system of interest and the external world. In addition, any measurement performed on the system necessarily involves coupling to the measuring device, therefore introducing an additional source of external influence. Consequently, developing the necessary tools, both theoretical and numerical, to account for the interactions between a system and its environment is an essential step in understanding the dynamics of practical quantum systems.

In general, for all but the most basic of Hamiltonians, an analytical description of the system dynamics is not possible, and one must resort to numerical simulations of the equations of motion. In absence of a quantum computer, these simulations must be carried out using classical computing techniques, where the exponentially increasing dimensionality of the underlying Hilbert space severely limits the size of system that can be efficiently simulated. However, in many fields such as quantum optics, trapped ions, superconducting circuit devices, and most recently nanomechanical systems, it is possible to design systems using a small number of effective oscillator and spin components, excited by a limited number of quanta, that are amenable to classical simulation in a truncated Hilbert space.

The Quantum Toolbox in Python, or QuTiP, is an open-source framework written in the Python programming language, designed for simulating the open quantum dynamics of systems such as those listed above. This framework distinguishes itself from other available software solutions in providing the following advantages:

- QuTiP relies entirely on open-source software. You are free to modify and use it as you wish with no licensing fees or limitations.
- QuTiP is based on the Python scripting language, providing easy to read, fast code generation without the need to compile after modification.
- The numerics underlying QuTiP are time-tested algorithms that run at C-code speeds, thanks to the [Numpy](#), [Scipy](#), and [Cython](#) libraries, and are based on many of the same algorithms used in propriety software.
- QuTiP allows for solving the dynamics of Hamiltonians with (almost) arbitrary time-dependence, including collapse operators.
- Time-dependent problems can be automatically compiled into C++-code at run-time for increased performance.
- Takes advantage of the multiple processing cores found in essentially all modern computers.
- QuTiP was designed from the start to require a minimal learning curve for those users who have experience using the popular quantum optics toolbox by Sze M. Tan.
- Includes the ability to create high-quality plots, and animations, using the excellent [Matplotlib](#) package.

For detailed information about new features of each release of QuTiP, see the [Change Log](#).

1.5 QuTiP Plugins

Several libraries depend on QuTiP heavily making QuTiP a super-library

Matsubara [Matsubara](#) is a plugin to study the ultrastrong coupling regime with structured baths

QNET [QNET](#) is a computer algebra package for quantum mechanics and photonic quantum networks

1.6 Libraries Using QuTiP

Several libraries rely on QuTiP for quantum physics or quantum information processing. Some of them are:

Krotov [Krotov](#) focuses on the python implementation of Krotov's method for quantum optimal control

pyEPR [pyEPR](#) interfaces classical distributed microwave analysis with that of quantum structures and hamiltonians by providing easy to use analysis function and automation for the design of quantum chips

scQubits [scQubits](#) is a Python library which provides a convenient way to simulate superconducting qubits by providing an interface to QuTiP

SimulaQron [SimulaQron](#) is a distributed simulation of the end nodes in a quantum internet with the specific goal to explore application development

QInfer [QInfer](#) is a library for working with sequential Monte Carlo methods for parameter estimation in quantum information

QPtomographer [QPtomographer](#) derive quantum error bars for quantum processes in terms of the diamond norm to a reference quantum channel

QuNetSim [QuNetSim](#) is a quantum networking simulation framework to develop and test protocols for quantum networks

qupulse [qupulse](#) is a toolkit to facilitate experiments involving pulse driven state manipulation of physical qubits

Pulser [Pulser](#) is a framework for composing, simulating and executing pulse sequences for neutral-atom quantum devices.

1.7 Contributing to QuTiP

We welcome anyone who is interested in helping us make QuTiP the best package for simulating quantum systems. There are *detailed instructions on how to contribute code and documentation* in the developers' section of this guide. You can also help out our users by answering questions in the [QuTiP discussion mailing list](#), or by raising issues in the [main GitHub repository](#) if you find any bugs. Anyone who contributes code will be duly recognized. Even small contributions are noted. See [Contributors](#) for a list of people who have helped in one way or another.

Chapter 2

Installation

2.1 Quick Start

From QuTiP version 4.6 onwards, you should be able to get a working version of QuTiP with the standard

```
pip install qutip
```

It is not recommended to install any packages directly into the system Python environment; consider using `pip` or `conda` virtual environments to keep your operating system space clean, and to have more control over Python and other package versions.

You do not need to worry about the details on the rest of this page unless this command did not work, but do also read the next section for the list of optional dependencies. The rest of this page covers *installation directly from conda*, *installation from source*, and *additional considerations when working on Windows*.

2.2 General Requirements

QuTiP depends on several open-source libraries for scientific computing in the Python programming language. The following packages are currently required:

Package	Version	Details
Python	3.6+	
NumPy	1.16+	
SciPy	1.0+	Lower versions may have missing features.

In addition, there are several optional packages that provide additional functionality:

Package	Version	Details
matplotlib	1.2.1+	Needed for all visualisation tasks.
cython	0.29.20+	Needed for compiling some time-dependent Hamiltonians.
cvxpy	1.0+	Needed to calculate diamond norms.
C++ Compiler	GCC 4.7+, MS VS 2015	Needed for compiling Cython files, made when using string-format time-dependence.
pytest, pytest-rerunfailures	5.3+	For running the test suite.
LaTeX	TeXLive 2009+	Needed if using LaTeX in matplotlib figures, or for nice circuit drawings in IPython.

In addition, there are several additional packages that are not dependencies, but may give you a better programming experience. [IPython](#) provides an improved text-based Python interpreter that is far more full-featured than the

default interpreter, and runs in a terminal. If you prefer a more graphical set-up, [Jupyter](#) provides a notebook-style interface to mix code and mathematical notes together. Alternatively, [Spyder](#) is a free integrated development environment for Python, with several nice features for debugging code. QuTiP will detect if it is being used within one of these richer environments, and various outputs will have enhanced formatting.

2.3 Installing with conda

QuTiP is designed to work best when using the [Anaconda](#) or [Intel](#) Python distributions that support the conda package management system. It is still possible to use `pip` to install QuTiP while using conda, but uniformly using conda will make complete dependency management easier.

If you already have your conda environment set up, and have the `conda-forge` channel available, then you can install QuTiP using:

```
conda install qutip
```

This will install the minimum set of dependences, but none of the optional packages.

2.3.1 Adding the conda-forge channel

To install QuTiP from conda, you will need to add the conda-forge channel. The following command adds this channel with lowest priority, so conda will still try and install all other packages normally:

```
conda config --append channels conda-forge
```

If you want to change the order of your channels later, you can edit your `.condarc` (user home folder) file manually, but it is recommended to keep `defaults` as the highest priority.

2.3.2 New conda environments

The default Anaconda environment has all the Python packages needed for running QuTiP installed already, so you will only need to add the `conda-forge` channel and then install the package. If you have only installed Miniconda, or you want a completely clean virtual environment to install QuTiP in, the conda package manager provides a convenient way to do this.

To create a conda environment for QuTiP called `qutip-env`:

```
conda create -n qutip-env python qutip
```

This will automatically install all the necessary packages, and none of the optional packages. You activate the new environment by running

```
conda activate qutip-env
```

You can also install any more optional packages you want with `conda install`, for example `matplotlib`, `ipython` or `jupyter`.

2.4 Installing from Source

Official releases of QuTiP are available from the download section on [the project's web pages](#), and the latest source code is available in [our GitHub repository](#). In general we recommend users to use the latest stable release of QuTiP, but if you are interested in helping us out with development or wish to submit bug fixes, then use the latest development version from the GitHub repository.

You can install from source by using the *Python-recommended PEP 517 procedure*, or if you want more control or to have a development version, you can use the *low-level build procedure with setuptools*.

2.4.1 PEP 517 Source Builds

The easiest way to build QuTiP from source is to use a PEP-517-compatible builder such as the `build` package available on `pip`. These will automatically install all build dependencies for you, and the `pip` installation step afterwards will install the minimum runtime dependencies. You can do this by doing (for example)

```
pip install build
python -m build <path to qutip>
pip install <path to qutip>/dist/qutip-<version>.whl
```

The first command installs the reference PEP-517 build tool, the second effects the build and the third uses `pip` to install the built package. You will need to replace `<path to qutip>` with the actual path to the QuTiP source code. The string `<version>` will depend on the version of QuTiP, the version of Python and your operating system. It will look something like `4.6.0-cp39-cp39-manylinux1_x86_64`, but there should only be one `.whl` file in the `dist/` directory, which will be the correct one.

2.4.2 Direct Setuptools Source Builds

This is the method to have the greatest amount of control over the installation, but it the most error-prone and not recommended unless you know what you are doing. You first need to have all the runtime dependencies installed. The most up-to-date requirements will be listed in `pyproject.toml` file, in the `build-system.requires` key. As of the 4.6.0 release, the build requirements can be installed with

```
pip install setuptools wheel packaging 'cython>=0.29.20' 'numpy>=1.16.6,<1.20'
↪ 'scipy>=1.0'
```

or similar with `conda` if you prefer. You will also need to have a functional C++ compiler installed on your system. This is likely already done for you if you are on Linux or macOS, but see the [section on Windows installations](#) if that is your operating system.

To install QuTiP from the source code run:

```
python setup.py install
```

To install OpenMP support, if available, run:

```
python setup.py install --with-openmp
```

This will attempt to load up OpenMP libraries during the compilation process, which depends on you having suitable C++ compiler and library support. If you are on Linux this is probably already done, but the compiler macOS ships with does not have OpenMP support. You will likely need to refer to external operating-system-specific guides for more detail here, as it may be very non-trivial to correctly configure.

If you wish to contribute to the QuTiP project, then you will want to create your own fork of [the QuTiP git repository](#), clone this to a local folder, and install it into your Python environment using:

```
python setup.py develop
```

When you do `import qutip` in this environment, you will then load the code from your local fork, enabling you to edit the Python files and have the changes immediately available when you restart your Python interpreter, without needing to rebuild the package. Note that if you change any Cython files, you will need to rerun the build command.

You should not need to use `sudo` (or other superuser privileges) to install into a personal virtual environment; if it feels like you need it, there is a good chance that you are installing into the system Python environment instead.

2.5 Installation on Windows

As with other operating systems, the easiest method is to use `pip install qutip`, or use the `conda` procedure described above. If you want to build from source or use runtime compilation with Cython, you will need to have a working C++ compiler.

You can [download the Visual Studio IDE from Microsoft](#), which has a free Community edition containing a sufficient C++ compiler. This is the recommended compiler toolchain on Windows. When installing, be sure to select the following components:

- Windows “X” SDK (where “X” stands for your version: 7/8/8.1/10)
- Visual Studio C++ build tools

You can then follow the [installation from source](#) section as normal.

Important: In order to prevent issues with the `PATH` environment variable not containing the compiler and associated libraries, it is recommended to use the developer command prompt in the Visual Studio installation folder instead of the built-in command prompt.

The Community edition of Visual Studio takes around 10GB of disk space. If this is prohibitive for you, it is also possible to install [only the build tools and necessary SDKs](#) instead, which should save about 2GB of space.

2.6 Verifying the Installation

QuTiP includes a collection of built-in test scripts to verify that an installation was successful. To run the suite of tests scripts you must also have the `pytest` testing library. After installing QuTiP, leave the installation directory, run Python (or IPython), and call:

```
import qutip.testing
qutip.testing.run()
```

This will take between 10 and 30 minutes, depending on your computer. At the end, the testing report should report a success; it is normal for some tests to be skipped, and for some to be marked “xfail” in yellow. Skips may be tests that do not run on your operating system, or tests of optional components that you have not installed the dependencies for. If any failures or errors occur, please check that you have installed all of the required modules. See the next section on how to check the installed versions of the QuTiP dependencies. If these tests still fail, then head on over to the [QuTiP Discussion Board](#) or the [GitHub issues page](#) and post a message detailing your particular issue.

2.7 Checking Version Information

QuTiP includes an “about” function for viewing information about QuTiP and the important dependencies installed on your system. To view this information:

```
import qutip
qutip.about()
```


Chapter 3

Users Guide

3.1 Guide Overview

The goal of this guide is to introduce you to the basic structures and functions that make up QuTiP. This guide is divided up into several sections, each highlighting a specific set of functionalities. In combination with the examples that can be found on the project web page <https://qutip.org/tutorials.html>, this guide should provide a more or less complete overview of QuTip. We also provide the API documentation in *API documentation*.

3.1.1 Organization

QuTiP is designed to be a general framework for solving quantum mechanics problems such as systems composed of few-level quantum systems and harmonic oscillators. To this end, QuTiP is built from a large (and ever growing) library of functions and classes; from `qutip.states.basis` to `qutip.wigner`. The general organization of QuTiP, highlighting the important API available to the user, is shown in the figure below.




Fig. 1: Tree-diagram of the 468 user accessible functions and classes in QuTiP 4.6. A vector image of the code tree is in `qutip_tree.pdf`.

3.2 Basic Operations on Quantum Objects

3.2.1 First things first

Warning: Do not run QuTiP from the installation directory.

To load the qutip modules, first call the import statement:

```
from qutip import *
```

This will load all of the user available functions. Often, we also need to import the NumPy and Matplotlib libraries with:

```
import numpy as np
import matplotlib.pyplot as plt
```

In the rest of the documentation, functions are written using `qutip.module.function()` notation which links to the corresponding function in the QuTiP API: [Functions](#). However, in calling `import *`, we have already loaded all of the QuTiP modules. Therefore, we will only need the function name and not the complete path when calling the function from the interpreter prompt, Python script, or Jupyter notebook.

3.2.2 The quantum object class

Introduction

The key difference between classical and quantum mechanics is the use of operators instead of numbers as variables. Moreover, we need to specify state vectors and their properties. Therefore, in computing the dynamics of quantum systems, we need a data structure that encapsulates the properties of a quantum operator and ket/bra vectors. The quantum object class, `qutip.Qobj`, accomplishes this using matrix representation.

To begin, let us create a blank `Qobj`:

```
print(Qobj())
```

Output:

```
Quantum object: dims = [[1], [1]], shape = (1, 1), type = bra
Qobj data =
[[0.]]
```

where we see the blank `Qobj` object with dimensions, shape, and data. Here the data corresponds to a 1x1-dimensional matrix consisting of a single zero entry.

Hint: By convention, the names of Python classes, such as `Qobj()`, are capitalized whereas the names of functions are not.

We can create a `Qobj` with a user defined data set by passing a list or array of data into the `Qobj`:

```
print(Qobj([[1], [2], [3], [4], [5]]))
```

Output:

```
Quantum object: dims = [[5], [1]], shape = (5, 1), type = ket
Qobj data =
[[1.]
 [2.]
 [3.]
 [4.]
 [5.]]
```

```
x = np.array([[1, 2, 3, 4, 5]])
print(Qobj(x))
```

Output:

```
Quantum object: dims = [[1], [5]], shape = (1, 5), type = bra
Qobj data =
[[1. 2. 3. 4. 5.]]
```

```
r = np.random.rand(4, 4)
print(Qobj(r))
```

Output:

```
Quantum object: dims = [[4], [4]], shape = (4, 4), type = oper, isherm = False
Qobj data =
[[0.37454012 0.95071431 0.73199394 0.59865848]
 [0.15601864 0.15599452 0.05808361 0.86617615]
 [0.60111501 0.70807258 0.02058449 0.96990985]
 [0.83244264 0.21233911 0.18182497 0.18340451]]
```

Notice how both the dims and shape change according to the input data. Although dims and shape appear to be the same, dims keep track of the shapes for individual components of a multipartite system, while shape does not. We refer the reader to the section [tensor products and partial traces](#) for more information.

Note: If you are running QuTiP from a python script you must use the `print` function to view the Qobj attributes.

States and operators

Manually specifying the data for each quantum object is inefficient. Even more so when most objects correspond to commonly used types such as the ladder operators of a harmonic oscillator, the Pauli spin operators for a two-level system, or state vectors such as Fock states. Therefore, QuTiP includes predefined objects for a variety of states and operators:

States	Command (# means optional)	Inputs
Fock state ket vector	<code>basis(N, #m)</code> / <code>fock(N, #m)</code>	N = number of levels in Hilbert space, m = level containing excitation (0 if no m given)
Empty ket vector	<code>zero_ket(N)</code>	N = number of levels in Hilbert space,
Fock density matrix (outer product of basis)	<code>fock_dm(N, #p)</code>	same as <code>basis(N,m) / fock(N,m)</code>
Coherent state	<code>coherent(N, alpha)</code>	alpha = complex number (eigenvalue) for requested coherent state
Coherent density matrix (outer product)	<code>coherent_dm(N, alpha)</code>	same as <code>coherent(N,alpha)</code>
Thermal density matrix (for n particles)	<code>thermal_dm(N, n)</code>	n = particle number expectation value
Maximally mixed density matrix	<code>maximally_mixed(N)</code>	N = number of levels in Hilbert space

Operators	Command (# means optional)	Inputs
Charge operator	<code>charge(N, M=-N)</code>	Diagonal operator with entries from $M..0..N$.
Commutator	<code>commutator(A, B, kind)</code>	Kind = 'normal' or 'anti'.
Diagonals operator	<code>qdiags(N)</code>	Quantum object created from arrays of diagonals at given offsets.
Displacement operator (Single-mode)	<code>displace(N, alpha)</code>	N=number of levels in Hilbert space, alpha = complex displacement amplitude.
Higher spin operators	<code>jmat(j, #s)</code>	j = integer or half-integer representing spin, s = 'x', 'y', 'z', '+', or '-'
Identity	<code>qeye(N)</code>	N = number of levels in Hilbert space.
Lowering (destruction) operator	<code>destroy(N)</code>	same as above
Momentum operator	<code>momentum(N)</code>	same as above
Number operator	<code>num(N)</code>	same as above
Phase operator (Single-mode)	<code>phase(N, phi0)</code>	Single-mode Pegg-Barnett phase operator with ref phase phi0.
Position operator	<code>position(N)</code>	same as above
Raising (creation) operator	<code>create(N)</code>	same as above
Squeezing operator (Single-mode)	<code>squeeze(N, sp)</code>	N=number of levels in Hilbert space, sp = squeezing parameter.
Squeezing operator (Generalized)	<code>squeezing(q1, q2, sp)</code>	q1,q2 = Quantum operators (Qobj) sp = squeezing parameter.
Sigma-X	<code>sigmax()</code>	
Sigma-Y	<code>sigmay()</code>	
Sigma-Z	<code>sigmaz()</code>	
Sigma plus	<code>sigmap()</code>	
Sigma minus	<code>sigmam()</code>	
Tunneling operator	<code>tunneling(N, m)</code>	Tunneling operator with elements of the form $ N \rangle \langle N+m + N+m \rangle \langle N $.

As an example, we give the output for a few of these functions:

```
>>> basis(5,3)
Quantum object: dims = [[5], [1]], shape = (5, 1), type = ket
Qobj data =
[[0.]
 [0.]
 [0.]
 [1.]
 [0.]]

>>> coherent(5,0.5-0.5j)
Quantum object: dims = [[5], [1]], shape = (5, 1), type = ket
Qobj data =
[[ 0.7788017 +0.j          ]
 [ 0.38939142-0.38939142j]
 [ 0.          -0.27545895j]
 [-0.07898617-0.07898617j]
 [-0.04314271+0.j          ]]

>>> destroy(4)
Quantum object: dims = [[4], [4]], shape = (4, 4), type = oper, isherm = False
Qobj data =
[[0.          1.          0.          0.          ]
 [0.          0.          1.41421356 0.          ]]
```

(continues on next page)

(continued from previous page)

```
[0.          0.          0.          1.73205081]
[0.          0.          0.          0.          ]]

>>> sigmaz()
Quantum object: dims = [[2], [2]], shape = (2, 2), type = oper, isherm = True
Qobj data =
[[ 1.  0.]
 [ 0. -1.]]

>>> jmat(5/2.0, '+')
Quantum object: dims = [[6], [6]], shape = (6, 6), type = oper, isherm = False
Qobj data =
[[0.          2.23606798 0.          0.          0.          0.          ]
 [0.          0.          2.82842712 0.          0.          0.          ]
 [0.          0.          0.          3.          0.          0.          ]
 [0.          0.          0.          0.          2.82842712 0.          ]
 [0.          0.          0.          0.          0.          2.23606798]
 [0.          0.          0.          0.          0.          0.          ]]
```

Qobj attributes

We have seen that a quantum object has several internal attributes, such as data, dims, and shape. These can be accessed in the following way:

```
>>> q = destroy(4)

>>> q.dims
[[4], [4]]

>>> q.shape
(4, 4)
```

In general, the attributes (properties) of a `Qobj` object (or any Python object) can be retrieved using the *Q.attribute* notation. In addition to the those shown with the `print` function, an instance of the `Qobj` class also has the following attributes:

Property	At-tribute	Description
Data	<code>Q.data</code>	Matrix representing state or operator
Dimen-sions	<code>Q.dims</code>	List keeping track of shapes for individual components of a multipartite system (for tensor products and partial traces).
Shape	<code>Q.shape</code>	Dimensions of underlying data matrix.
is Hermi-tian?	<code>Q.isherm</code>	Is the operator Hermitian or not?
Type	<code>Q.type</code>	Is object of type 'ket', 'bra', 'oper', or 'super'?




Fig. 2: The `Qobj` Class viewed as a container for the properties needed to characterize a quantum operator or state vector.

For the destruction operator above:

```
>>> q.type
'oper'

>>> q.isherm
False

>>> q.data
<4x4 sparse matrix of type '<class 'numpy.complex128'>'
      with 3 stored elements in Compressed Sparse Row format>
```

The data attribute returns a message stating that the data is a sparse matrix. All `Qobj` instances store their data as a sparse matrix to save memory. To access the underlying dense matrix one needs to use the `qutip.Qobj.full` function as described below.

Qobj Math

The rules for mathematical operations on `Qobj` instances are similar to standard matrix arithmetic:

```
>>> q = destroy(4)

>>> x = sigmax()

>>> q + 5
Quantum object: dims = [[4], [4]], shape = (4, 4), type = oper, isherm = False
Qobj data =
[[5.         1.         0.         0.         ]
 [0.         5.         1.41421356 0.         ]
 [0.         0.         5.         1.73205081]
 [0.         0.         0.         5.         ]]

>>> x * x
Quantum object: dims = [[2], [2]], shape = (2, 2), type = oper, isherm = True
Qobj data =
[[1. 0.]
 [0. 1.]]

>>> q ** 3
Quantum object: dims = [[4], [4]], shape = (4, 4), type = oper, isherm = False
Qobj data =
```

(continues on next page)

(continued from previous page)

```
[ [0.      0.      0.      2.44948974]
  [0.      0.      0.      0.      ]
  [0.      0.      0.      0.      ]
  [0.      0.      0.      0.      ]]

>>> x / np.sqrt(2)
Quantum object: dims = [[2], [2]], shape = (2, 2), type = oper, isherm = True
Qobj data =
[[0.      0.70710678]
 [0.70710678 0.      ]]
```

Of course, like matrices, multiplying two objects of incompatible shape throws an error:

```
>>> print(q * x)
-----
TypeError                                Traceback (most recent call last)
<ipython-input-33-0b599f41213e> in <module>
----> 1 print(q * x)

~/Documents/qutip_dev/qutip/qutip/qobj.py in __mul__(self, other)
    553
    554         else:
--> 555             raise TypeError("Incompatible Qobj shapes")
    556
    557         elif isinstance(other, np.ndarray):

TypeError: Incompatible Qobj shapes
```

In addition, the logic operators “is equal” `==` and “is not equal” `!=` are also supported.

3.2.3 Functions operating on Qobj class

Like attributes, the quantum object class has defined functions (methods) that operate on `Qobj` class instances. For a general quantum object `Q`:

Function	Command	Description
Check Hermiticity	<code>Q.check_herm()</code>	Check if quantum object is Hermitian
Conjugate	<code>Q.conj()</code>	Conjugate of quantum object.
Cosine	<code>Q.cosm()</code>	Cosine of quantum object.
Dagger (adjoint)	<code>Q.dag()</code>	Returns adjoint (dagger) of object.
Diagonal	<code>Q.diag()</code>	Returns the diagonal elements.
Diamond Norm	<code>Q.dnorm()</code>	Returns the diamond norm.
Eigenenergies	<code>Q.eigenenergies()</code>	Eigenenergies (values) of operator.
Eigenstates	<code>Q.eigenstates()</code>	Returns eigenvalues and eigenvectors.
Exponential	<code>Q.expm()</code>	Matrix exponential of operator.
Full	<code>Q.full()</code>	Returns full (not sparse) array of Q's data.
Groundstate	<code>Q.groundstate()</code>	Eigenval & eigket of Qobj groundstate.
Matrix Element	<code>Q.matrix_element(bra, ket)</code>	Matrix element $\langle \text{bra} Q \text{ket} \rangle$
Norm	<code>Q.norm()</code>	Returns L2 norm for states, trace norm for operators.
Overlap	<code>Q.overlap(state)</code>	Overlap between current Qobj and a given state.
Partial Trace	<code>Q.ptrace(sel)</code>	Partial trace returning components selected using 'sel' parameter.
Permute	<code>Q.permute(order)</code>	Permutes the tensor structure of a composite object in the given order.
Projector	<code>Q.proj()</code>	Form projector operator from given ket or bra vector.
Sine	<code>Q.sinm()</code>	Sine of quantum operator.
Sqrt	<code>Q.sqrrm()</code>	Matrix sqrt of operator.
Tidyup	<code>Q.tidyup()</code>	Removes small elements from Qobj.
Trace	<code>Q.tr()</code>	Returns trace of quantum object.
Transform	<code>Q.transform(inpt)</code>	A basis transformation defined by matrix or list of kets 'inpt'.
Transpose	<code>Q.trans()</code>	Transpose of quantum object.
Truncate Neg	<code>Q.trunc_neg()</code>	Truncates negative eigenvalues
Unit	<code>Q.unit()</code>	Returns normalized (unit) vector $Q/Q.\text{norm}()$.

```
>>> basis(5, 3)
Quantum object: dims = [[5], [1]], shape = (5, 1), type = ket
Qobj data =
[[0.]
 [0.]
 [0.]
 [1.]
 [0.]]

>>> basis(5, 3).dag()
Quantum object: dims = [[1], [5]], shape = (1, 5), type = bra
Qobj data =
[[0. 0. 0. 1. 0.]]

>>> coherent_dm(5, 1)
Quantum object: dims = [[5], [5]], shape = (5, 5), type = oper, isherm = True
Qobj data =
[[0.36791117 0.36774407 0.26105441 0.14620658 0.08826704]
 [0.36774407 0.36757705 0.26093584 0.14614018 0.08822695]
 [0.26105441 0.26093584 0.18523331 0.10374209 0.06263061]
 [0.14620658 0.14614018 0.10374209 0.05810197 0.035077 ]
 [0.08826704 0.08822695 0.06263061 0.035077  0.0211765 ]]
```

(continues on next page)

(continued from previous page)

```
>>> coherent_dm(5, 1).diag()
array([0.36791117, 0.36757705, 0.18523331, 0.05810197, 0.0211765 ])

>>> coherent_dm(5, 1).full()
array([[0.36791117+0.j, 0.36774407+0.j, 0.26105441+0.j, 0.14620658+0.j,
        0.08826704+0.j],
       [0.36774407+0.j, 0.36757705+0.j, 0.26093584+0.j, 0.14614018+0.j,
        0.08822695+0.j],
       [0.26105441+0.j, 0.26093584+0.j, 0.18523331+0.j, 0.10374209+0.j,
        0.06263061+0.j],
       [0.14620658+0.j, 0.14614018+0.j, 0.10374209+0.j, 0.05810197+0.j,
        0.035077 +0.j],
       [0.08826704+0.j, 0.08822695+0.j, 0.06263061+0.j, 0.035077 +0.j,
        0.0211765 +0.j]])

>>> coherent_dm(5, 1).norm()
1.0000000175063126

>>> coherent_dm(5, 1).sqrtm()
Quantum object: dims = [[5], [5]], shape = (5, 5), type = oper, isherm = False
Qobj data =
[[0.36791117+3.66778589e-09j 0.36774407-2.13388761e-09j
 0.26105441-1.51480558e-09j 0.14620658-8.48384618e-10j
 0.08826704-5.12182118e-10j]
 [0.36774407-2.13388761e-09j 0.36757705+2.41479965e-09j
 0.26093584-1.11446422e-09j 0.14614018+8.98971115e-10j
 0.08822695+6.40705133e-10j]
 [0.26105441-1.51480558e-09j 0.26093584-1.11446422e-09j
 0.18523331+4.02032413e-09j 0.10374209-3.39161017e-10j
 0.06263061-3.71421368e-10j]
 [0.14620658-8.48384618e-10j 0.14614018+8.98971115e-10j
 0.10374209-3.39161017e-10j 0.05810197+3.36300708e-10j
 0.035077 +2.36883273e-10j]
 [0.08826704-5.12182118e-10j 0.08822695+6.40705133e-10j
 0.06263061-3.71421368e-10j 0.035077 +2.36883273e-10j
 0.0211765 +1.71630348e-10j]]

>>> coherent_dm(5, 1).tr()
1.0

>>> (basis(4, 2) + basis(4, 1)).unit()
Quantum object: dims = [[4], [1]], shape = (4, 1), type = ket
Qobj data =
[[0.
 0.70710678
 0.70710678
 0.
  ]]
```

3.3 Manipulating States and Operators

3.3.1 Introduction

In the previous guide section *Basic Operations on Quantum Objects*, we saw how to create states and operators, using the functions built into QuTiP. In this portion of the guide, we will look at performing basic operations with states and operators. For more detailed demonstrations on how to use and manipulate these objects, see the examples on the [tutorials](#) web page.

3.3.2 State Vectors (kets or bras)

Here we begin by creating a Fock `qutip.states.basis` vacuum state vector $|0\rangle$ with in a Hilbert space with 5 number states, from 0 to 4:

```
vac = basis(5, 0)

print(vac)
```

Output:

```
Quantum object: dims = [[5], [1]], shape = (5, 1), type = ket
Qobj data =
[[1.]
 [0.]
 [0.]
 [0.]
 [0.]]
```

and then create a lowering operator (\hat{a}) corresponding to 5 number states using the `qutip.destroy` function:

```
a = destroy(5)

print(a)
```

Output:

```
Quantum object: dims = [[5], [5]], shape = (5, 5), type = oper, isherm = False
Qobj data =
[[0.      1.      0.      0.      0.      ]
 [0.      0.      1.41421356 0.      0.      ]
 [0.      0.      0.      1.73205081 0.      ]
 [0.      0.      0.      0.      2.      ]
 [0.      0.      0.      0.      0.      ]]
```

Now lets apply the destruction operator to our vacuum state `vac`,

```
print(a * vac)
```

Output:

```
Quantum object: dims = [[5], [1]], shape = (5, 1), type = ket
Qobj data =
[[0.]
 [0.]
 [0.]
 [0.]
 [0.]]
```

We see that, as expected, the vacuum is transformed to the zero vector. A more interesting example comes from using the adjoint of the lowering operator, the raising operator \hat{a}^\dagger :

```
print(a.dag() * vac)
```

Output:

```
Quantum object: dims = [[5], [1]], shape = (5, 1), type = ket
Qobj data =
[[0.]
 [1.]
 [0.]
 [0.]
 [0.]]
```

The raising operator has in indeed raised the state *vac* from the vacuum to the $|1\rangle$ state. Instead of using the dagger `Qobj.dag()` method to raise the state, we could have also used the built in `qutip.create` function to make a raising operator:

```
c = create(5)
print(c * vac)
```

Output:

```
Quantum object: dims = [[5], [1]], shape = (5, 1), type = ket
Qobj data =
[[0.]
 [1.]
 [0.]
 [0.]
 [0.]]
```

which does the same thing. We can raise the vacuum state more than once by successively apply the raising operator:

```
print(c * c * vac)
```

Output:

```
Quantum object: dims = [[5], [1]], shape = (5, 1), type = ket
Qobj data =
[[0.      ]
 [0.      ]
 [1.41421356]
 [0.      ]
 [0.      ]]
```

or just taking the square of the raising operator $(\hat{a}^\dagger)^2$:

```
print(c ** 2 * vac)
```

Output:

```
Quantum object: dims = [[5], [1]], shape = (5, 1), type = ket
Qobj data =
[[0.      ]
 [0.      ]
 [1.41421356]
 [0.      ]
 [0.      ]]
```

Applying the raising operator twice gives the expected $\sqrt{n+1}$ dependence. We can use the product of $c * a$ to also apply the number operator to the state vector *vac*:

```
print(c * a * vac)
```

Output:

```
Quantum object: dims = [[5], [1]], shape = (5, 1), type = ket
Qobj data =
[[0.]
 [0.]
 [0.]
 [0.]
 [0.]]
```

or on the $|1\rangle$ state:

```
print(c * a * (c * vac))
```

Output:

```
Quantum object: dims = [[5], [1]], shape = (5, 1), type = ket
Qobj data =
[[0.]
 [1.]
 [0.]
 [0.]
 [0.]]
```

or the $|2\rangle$ state:

```
print(c * a * (c**2 * vac))
```

Output:

```
Quantum object: dims = [[5], [1]], shape = (5, 1), type = ket
Qobj data =
[[0.      ]
 [0.      ]
 [2.82842712]
 [0.      ]
 [0.      ]]
```

Notice how in this last example, application of the number operator does not give the expected value $n = 2$, but rather $2\sqrt{2}$. This is because this last state is not normalized to unity as $c|n\rangle = \sqrt{n+1}|n+1\rangle$. Therefore, we should normalize our vector first:

```
print(c * a * (c**2 * vac).unit())
```

Output:

```
Quantum object: dims = [[5], [1]], shape = (5, 1), type = ket
Qobj data =
[[0.]
 [0.]
 [2.]
 [0.]
 [0.]]
```

Since we are giving a demonstration of using states and operators, we have done a lot more work than we should have. For example, we do not need to operate on the vacuum state to generate a higher number Fock state. Instead we can use the `qutip.states.basis` (or `qutip.states.fock`) function to directly obtain the required state:

```
ket = basis(5, 2)

print(ket)
```

Output:

```
Quantum object: dims = [[5], [1]], shape = (5, 1), type = ket
Qobj data =
[[0.]
 [0.]
 [1.]
 [0.]
 [0.]]
```

Notice how it is automatically normalized. We can also use the built in `qutip.num` operator:

```
n = num(5)

print(n)
```

Output:

```
Quantum object: dims = [[5], [5]], shape = (5, 5), type = oper, isherm = True
Qobj data =
[[0. 0. 0. 0. 0.]
 [0. 1. 0. 0. 0.]
 [0. 0. 2. 0. 0.]
 [0. 0. 0. 3. 0.]
 [0. 0. 0. 0. 4.]]
```

Therefore, instead of `c * a * (c ** 2 * vac).unit()` we have:

```
print(n * ket)
```

Output:

```
Quantum object: dims = [[5], [1]], shape = (5, 1), type = ket
Qobj data =
[[0.]
 [0.]
 [2.]
 [0.]
 [0.]]
```

We can also create superpositions of states:

```
ket = (basis(5, 0) + basis(5, 1)).unit()

print(ket)
```

Output:

```
Quantum object: dims = [[5], [1]], shape = (5, 1), type = ket
Qobj data =
[[0.70710678]
 [0.70710678]
 [0.         ]
 [0.         ]
 [0.         ]]
```

where we have used the `qutip.Qobj.unit` method to again normalize the state. Operating with the number function again:

```
print(n * ket)
```

Output:

```
Quantum object: dims = [[5], [1]], shape = (5, 1), type = ket
Qobj data =
[[0.      ]
 [0.70710678]
 [0.      ]
 [0.      ]
 [0.      ]]
```

We can also create coherent states and squeezed states by applying the `qutip.displace` and `qutip.squeeze` functions to the vacuum state:

```
vac = basis(5, 0)

d = displace(5, 1j)

s = squeeze(5, np.complex(0.25, 0.25))

print(d * vac)
```

Output:

```
Quantum object: dims = [[5], [1]], shape = (5, 1), type = ket
Qobj data =
[[ 0.60655682+0.j      ]
 [ 0.      +0.60628133j]
 [-0.4303874 +0.j      ]
 [ 0.      -0.24104351j]
 [ 0.14552147+0.j      ]]
```

```
print(d * s * vac)
```

Output:

```
Quantum object: dims = [[5], [1]], shape = (5, 1), type = ket
Qobj data =
[[ 0.65893786+0.08139381j]
 [ 0.10779462+0.51579735j]
 [-0.37567217-0.01326853j]
 [-0.02688063-0.23828775j]
 [ 0.26352814+0.11512178j]]
```

Of course, displacing the vacuum gives a coherent state, which can also be generated using the built in `qutip.states.coherent` function.

3.3.3 Density matrices

One of the main purpose of QuTiP is to explore the dynamics of **open** quantum systems, where the most general state of a system is no longer a state vector, but rather a density matrix. Since operations on density matrices operate identically to those of vectors, we will just briefly highlight creating and using these structures.

The simplest density matrix is created by forming the outer-product $|\psi\rangle\langle\psi|$ of a ket vector:

```
ket = basis(5, 2)

print(ket * ket.dag())
```

Output:

```
Quantum object: dims = [[5], [5]], shape = (5, 5), type = oper, isherm = True
Qobj data =
[[0. 0. 0. 0. 0.]
 [0. 0. 0. 0. 0.]
 [0. 0. 1. 0. 0.]
 [0. 0. 0. 0. 0.]
 [0. 0. 0. 0. 0.]]
```

A similar task can also be accomplished via the `qutip.states.fock_dm` or `qutip.states.ket2dm` functions:

```
print(fock_dm(5, 2))
```

Output:

```
Quantum object: dims = [[5], [5]], shape = (5, 5), type = oper, isherm = True
Qobj data =
[[0. 0. 0. 0. 0.]
 [0. 0. 0. 0. 0.]
 [0. 0. 1. 0. 0.]
 [0. 0. 0. 0. 0.]
 [0. 0. 0. 0. 0.]]
```

```
print(ket2dm(ket))
```

Output:

```
Quantum object: dims = [[5], [5]], shape = (5, 5), type = oper, isherm = True
Qobj data =
[[0. 0. 0. 0. 0.]
 [0. 0. 0. 0. 0.]
 [0. 0. 1. 0. 0.]
 [0. 0. 0. 0. 0.]
 [0. 0. 0. 0. 0.]]
```

If we want to create a density matrix with equal classical probability of being found in the $|2\rangle$ or $|4\rangle$ number states we can do the following:

```
print(0.5 * ket2dm(basis(5, 4)) + 0.5 * ket2dm(basis(5, 2)))
```

Output:

```
Quantum object: dims = [[5], [5]], shape = (5, 5), type = oper, isherm = True
Qobj data =
[[0. 0. 0. 0. 0.]
 [0. 0. 0. 0. 0.]
 [0. 0. 0.5 0. 0.]
 [0. 0. 0. 0. 0.]
 [0. 0. 0. 0. 0.5]]
```

or use `0.5 * fock_dm(5, 2) + 0.5 * fock_dm(5, 4)`. There are also several other built-in functions for creating predefined density matrices, for example `qutip.states.coherent_dm` and `qutip.states.thermal_dm` which create coherent state and thermal state density matrices, respectively.

```
print(coherent_dm(5, 1.25))
```

Output:

```
Quantum object: dims = [[5], [5]], shape = (5, 5), type = oper, isherm = True
Qobj data =
[[0.20980701 0.26141096 0.23509686 0.15572585 0.13390765]
```

(continues on next page)

(continued from previous page)

```
[0.26141096 0.32570738 0.29292109 0.19402805 0.16684347]
[0.23509686 0.29292109 0.26343512 0.17449684 0.1500487 ]
[0.15572585 0.19402805 0.17449684 0.11558499 0.09939079]
[0.13390765 0.16684347 0.1500487 0.09939079 0.0854655 ]]
```

```
print(thermal_dm(5, 1.25))
```

Output:

```
Quantum object: dims = [[5], [5]], shape = (5, 5), type = oper, isherm = True
Qobj data =
[[0.46927974 0.          0.          0.          0.          ]
 [0.          0.26071096 0.          0.          0.          ]
 [0.          0.          0.14483942 0.          0.          ]
 [0.          0.          0.          0.08046635 0.          ]
 [0.          0.          0.          0.          0.04470353]]
```

QuTiP also provides a set of distance metrics for determining how close two density matrix distributions are to each other. Included are the trace distance `qutip.core.metrics.tracedist`, fidelity `qutip.core.metrics.fidelity`, Hilbert-Schmidt distance `qutip.core.metrics.hilbert_dist`, Bures distance `qutip.core.metrics.bures_dist`, Bures angle `qutip.core.metrics.bures_angle`, and quantum Hellinger distance `qutip.core.metrics.hellinger_dist`.

```
x = coherent_dm(5, 1.25)

y = coherent_dm(5, np.complex(0, 1.25)) # <-- note the 'j'

z = thermal_dm(5, 0.125)

np.testing.assert_almost_equal(fidelity(x, x), 1)

np.testing.assert_almost_equal(hellinger_dist(x, y), 1.3819080728932833)
```

We also know that for two pure states, the trace distance (T) and the fidelity (F) are related by $T = \sqrt{1 - F^2}$, while the quantum Hellinger distance (QHE) between two pure states $|\psi\rangle$ and $|\phi\rangle$ is given by $QHE = \sqrt{2 - 2|\langle\psi|\phi\rangle|^2}$.

```
np.testing.assert_almost_equal(tracedist(y, x), np.sqrt(1 - fidelity(y, x) ** 2))
```

For a pure state and a mixed state, $1 - F^2 \leq T$ which can also be verified:

```
assert 1 - fidelity(x, z) ** 2 < tracedist(x, z)
```

3.3.4 Qubit (two-level) systems

Having spent a fair amount of time on basis states that represent harmonic oscillator states, we now move on to qubit, or two-level quantum systems (for example a spin-1/2). To create a state vector corresponding to a qubit system, we use the same `qutip.states.basis`, or `qutip.states.fock`, function with only two levels:

```
spin = basis(2, 0)
```

Now at this point one may ask how this state is different than that of a harmonic oscillator in the vacuum state truncated to two energy levels?

```
vac = basis(2, 0)
```

At this stage, there is no difference. This should not be surprising as we called the exact same function twice. The difference between the two comes from the action of the spin operators `qutip.sigmax`, `qutip.sigmay`,

`qutip.sigmaz`, `qutip.sigmap`, and `qutip.sigmam` on these two-level states. For example, if `vac` corresponds to the vacuum state of a harmonic oscillator, then, as we have already seen, we can use the raising operator to get the $|1\rangle$ state:

```
print(vac)
```

Output:

```
Quantum object: dims = [[2], [1]], shape = (2, 1), type = ket
Qobj data =
[[1.]
 [0.]]
```

```
c = create(2)
print(c * vac)
```

Output:

```
Quantum object: dims = [[2], [1]], shape = (2, 1), type = ket
Qobj data =
[[0.]
 [1.]]
```

For a spin system, the operator analogous to the raising operator is the sigma-plus operator `qutip.sigmap`. Operating on the spin state gives:

```
print(spin)
```

Output:

```
Quantum object: dims = [[2], [1]], shape = (2, 1), type = ket
Qobj data =
[[1.]
 [0.]]
```

```
print(sigmap() * spin)
```

Output:

```
Quantum object: dims = [[2], [1]], shape = (2, 1), type = ket
Qobj data =
[[0.]
 [0.]]
```

Now we see the difference! The `qutip.sigmap` operator acting on the spin state returns the zero vector. Why is this? To see what happened, let us use the `qutip.sigmaz` operator:

```
print(sigmaz())
```

Output:

```
Quantum object: dims = [[2], [2]], shape = (2, 2), type = oper, isherm = True
Qobj data =
[[ 1.  0.]
 [ 0. -1.]]
```

```
print(sigmaz() * spin)
```

Output:

```
Quantum object: dims = [[2], [1]], shape = (2, 1), type = ket
Qobj data =
[[1.]
 [0.]]
```

```
spin2 = basis(2, 1)

print(spin2)
```

Output:

```
Quantum object: dims = [[2], [1]], shape = (2, 1), type = ket
Qobj data =
[[0.]
 [1.]]
```

```
print(sigmaz() * spin2)
```

Output:

```
Quantum object: dims = [[2], [1]], shape = (2, 1), type = ket
Qobj data =
[[ 0.]
 [-1.]]
```

The answer is now apparent. Since the QuTiP `qutip.sigmaz` function uses the standard z-basis representation of the sigma-z spin operator, the `spin` state corresponds to the $|\uparrow\rangle$ state of a two-level spin system while `spin2` gives the $|\downarrow\rangle$ state. Therefore, in our previous example `sigmaz() * spin`, we raised the qubit state out of the truncated two-level Hilbert space resulting in the zero state.

While at first glance this convention might seem somewhat odd, it is in fact quite handy. For one, the spin operators remain in the conventional form. Second, when the spin system is in the $|\uparrow\rangle$ state:

```
print(sigmaz() * spin)
```

Output:

```
Quantum object: dims = [[2], [1]], shape = (2, 1), type = ket
Qobj data =
[[1.]
 [0.]]
```

the non-zero component is the zeroth-element of the underlying matrix (remember that python uses c-indexing, and matrices start with the zeroth element). The $|\downarrow\rangle$ state therefore has a non-zero entry in the first index position. This corresponds nicely with the quantum information definitions of qubit states, where the excited $|\uparrow\rangle$ state is label as $|0\rangle$, and the $|\downarrow\rangle$ state by $|1\rangle$.

If one wants to create spin operators for higher spin systems, then the `qutip.jmat` function comes in handy.

3.3.5 Expectation values

Some of the most important information about quantum systems comes from calculating the expectation value of operators, both Hermitian and non-Hermitian, as the state or density matrix of the system varies in time. Therefore, in this section we demonstrate the use of the `qutip.expect` function. To begin:

```
vac = basis(5, 0)

one = basis(5, 1)
```

(continues on next page)

(continued from previous page)

```
c = create(5)
N = num(5)
np.testing.assert_almost_equal(expect(N, vac), 0)
np.testing.assert_almost_equal(expect(N, one), 1)
coh = coherent_dm(5, 1.0j)
np.testing.assert_almost_equal(expect(N, coh), 0.9970555745806597)
cat = (basis(5, 4) + 1.0j * basis(5, 3)).unit()
np.testing.assert_almost_equal(expect(c, cat), 0.9999999999999998j)
```

The `qutip.expect` function also accepts lists or arrays of state vectors or density matrices for the second input:

```
states = [(c**k * vac).unit() for k in range(5)] # must normalize
print(expect(N, states))
```

Output:

```
[0. 1. 2. 3. 4.]
```

```
cat_list = [(basis(5, 4) + x * basis(5, 3)).unit() for x in [0, 1.0j, -1.0, -1.0j]]
print(expect(c, cat_list))
```

Output:

```
[ 0.+0.j  0.+1.j -1.+0.j  0.-1.j]
```

Notice how in this last example, all of the return values are complex numbers. This is because the `qutip.expect` function looks to see whether the operator is Hermitian or not. If the operator is Hermitian, then the output will always be real. In the case of non-Hermitian operators, the return values may be complex. Therefore, the `qutip.expect` function will return an array of complex values for non-Hermitian operators when the input is a list/array of states or density matrices.

Of course, the `qutip.expect` function works for spin states and operators:

```
up = basis(2, 0)
down = basis(2, 1)
np.testing.assert_almost_equal(expect(sigmaz(), up), 1)
np.testing.assert_almost_equal(expect(sigmaz(), down), -1)
```

as well as the composite objects discussed in the next section *Using Tensor Products and Partial Traces*:

```
spin1 = basis(2, 0)
spin2 = basis(2, 1)
two_spins = tensor(spin1, spin2)
sz1 = tensor(sigmaz(), qeye(2))
sz2 = tensor(qeye(2), sigmaz())
```

(continues on next page)

(continued from previous page)

```
np.testing.assert_almost_equal(expect(sz1, two_spins), 1)
np.testing.assert_almost_equal(expect(sz2, two_spins), -1)
```

3.3.6 Superoperators and Vectorized Operators

In addition to state vectors and density operators, QuTiP allows for representing maps that act linearly on density operators using the Kraus, Liouville supermatrix and Choi matrix formalisms. This support is based on the correspondence between linear operators acting on a Hilbert space, and vectors in two copies of that Hilbert space, $\text{vec} : \mathcal{L}(\mathcal{H}) \rightarrow \mathcal{H} \otimes \mathcal{H}$ [Hav03], [Wat13].

This isomorphism is implemented in QuTiP by the `operator_to_vector` and `vector_to_operator` functions:

```
psi = basis(2, 0)
rho = ket2dm(psi)
print(rho)
```

Output:

```
Quantum object: dims = [[2], [2]], shape = (2, 2), type = oper, isherm = True
Qobj data =
[[1. 0.]
 [0. 0.]]
```

```
vec_rho = operator_to_vector(rho)
print(vec_rho)
```

Output:

```
Quantum object: dims = [[2], [2]], [1]], shape = (4, 1), type = operator-ket
Qobj data =
[[1.]
 [0.]
 [0.]
 [0.]]
```

```
rho2 = vector_to_operator(vec_rho)
np.testing.assert_almost_equal((rho - rho2).norm(), 0)
```

The `type` attribute indicates whether a quantum object is a vector corresponding to an operator (operator-ket), or its Hermitian conjugate (operator-bra).

Note that QuTiP uses the *column-stacking* convention for the isomorphism between $\mathcal{L}(\mathcal{H})$ and $\mathcal{H} \otimes \mathcal{H}$:

```
A = Qobj(np.arange(4).reshape((2, 2)))
print(A)
```

Output:

```
Quantum object: dims = [[2], [2]], shape = (2, 2), type = oper, isherm = False
Qobj data =
```

(continues on next page)

(continued from previous page)

```
[[0. 1.]
 [2. 3.]]
```

```
print(operator_to_vector(A))
```

Output:

```
Quantum object: dims = [[[2], [2]], [1]], shape = (4, 1), type = operator-ket
Qobj data =
[[0.]
 [2.]
 [1.]
 [3.]]
```

Since $\mathcal{H} \otimes \mathcal{H}$ is a vector space, linear maps on this space can be represented as matrices, often called *superoperators*. Using the `Qobj`, the `spre` and `spost` functions, supermatrices corresponding to left- and right-multiplication respectively can be quickly constructed.

```
X = sigmax()
S = spre(X) * spost(X.dag()) # Represents conjugation by X.
```

Note that this is done automatically by the `to_super` function when given `type='oper'` input.

```
S2 = to_super(X)
np.testing.assert_almost_equal((S - S2).norm(), 0)
```

Quantum objects representing superoperators are denoted by `type='super'`:

```
print(S)
```

Output:

```
Quantum object: dims = [[[2], [2]], [[2], [2]]], shape = (4, 4), type = super,
↳ isherm = True
Qobj data =
[[0. 0. 0. 1.]
 [0. 0. 1. 0.]
 [0. 1. 0. 0.]
 [1. 0. 0. 0.]]
```

Information about superoperators, such as whether they represent completely positive maps, is exposed through the `iscp`, `istp` and `iscptp` attributes:

```
print(S.iscp, S.istp, S.iscptp)
```

Output:

```
True True True
```

In addition, dynamical generators on this extended space, often called *Liouvillian superoperators*, can be created using the `liouvillian` function. Each of these takes a Hamiltonian along with a list of collapse operators, and returns a `type="super"` object that can be exponentiated to find the superoperator for that evolution.

```
H = 10 * sigmaz()
c1 = destroy(2)
L = liouvillian(H, [c1])
```

(continues on next page)

(continued from previous page)

```
print(L)

S = (12 * L).expm()
```

Output:

```
Quantum object: dims = [[2], [2]], [[2], [2]], shape = (4, 4), type = super,
↳ isherm = False
Qobj data =
[[ 0. +0.j  0. +0.j  1. +0.j]
 [ 0. +0.j -0.5+20.j  0. +0.j]
 [ 0. +0.j  0. +0.j -0.5-20.j  0. +0.j]
 [ 0. +0.j  0. +0.j  0. +0.j -1. +0.j]]
```

For qubits, a particularly useful way to visualize superoperators is to plot them in the Pauli basis, such that $S_{\mu,\nu} = \langle\langle\sigma_\mu|S[\sigma_\nu]\rangle\rangle$. Because the Pauli basis is Hermitian, $S_{\mu,\nu}$ is a real number for all Hermitian-preserving superoperators S , allowing us to plot the elements of S as a [Hinton diagram](#). In such diagrams, positive elements are indicated by white squares, and negative elements by black squares. The size of each element is indicated by


the size of the corresponding square. For instance, let $S[\rho] = \sigma_x \rho \sigma_x^\dagger$. Then $S[\sigma_\mu] = \sigma_\mu \cdot \begin{cases} +1 & \mu = 0, x \\ -1 & \mu = y, z \end{cases}$. We can quickly see this by noting that the Y and Z elements of the Hinton diagram for S are negative:

```
from qutip import *
settings.colorblind_safe = True

import matplotlib.pyplot as plt
plt.rcParams['savefig.transparent'] = True

X = sigmax()
S = spre(X) * spost(X.dag())

hinton(S)
```



3.3.7 Choi, Kraus, Stinespring and χ Representations

In addition to the superoperator representation of quantum maps, QuTiP supports several other useful representations. First, the Choi matrix $J(\Lambda)$ of a quantum map Λ is useful for working with ancilla-assisted process tomography (AAPT), and for reasoning about properties of a map or channel. Up to normalization, the Choi matrix is defined by acting Λ on half of an entangled pair. In the column-stacking convention,

$$J(\Lambda) = (\mathbb{I} \otimes \Lambda)[|\mathcal{K}\rangle\rangle\langle\langle\mathcal{K}|].$$

In QuTiP, $J(\Lambda)$ can be found by calling the `to_choi` function on a `type="super"` `Qobj`.

```
X = sigmax()
S = sprepost(X, X)
J = to_choi(S)
print(J)
```

Output:

```
Quantum object: dims = [[2], [2]], [[2], [2]], shape = (4, 4), type = super,
→ isherm = True, superrep = choi
Qobj data =
[[0. 0. 0. 0.]
 [0. 1. 1. 0.]
 [0. 1. 1. 0.]
 [0. 0. 0. 0.]
```



```
print(to_choi(spre(qeye(2))))
```

Output:

```
Quantum object: dims = [[[2], [2]], [[2], [2]]], shape = (4, 4), type = super,
↪ isherm = True, superrep = choi
Qobj data =
[[1. 0. 0. 1.]
 [0. 0. 0. 0.]
 [0. 0. 0. 0.]
 [1. 0. 0. 1.]]
```

If a Qobj instance is already in the Choi superrep, then calling `to_choi` does nothing:

```
print(to_choi(J))
```

Output:

```
Quantum object: dims = [[[2], [2]], [[2], [2]]], shape = (4, 4), type = super,
↪ isherm = True, superrep = choi
Qobj data =
[[0. 0. 0. 0.]
 [0. 1. 1. 0.]
 [0. 1. 1. 0.]
 [0. 0. 0. 0.]]
```

To get back to the superoperator representation, simply use the `to_super` function. As with `to_choi`, `to_super` is idempotent:

```
print(to_super(J) - S)
```

Output:

```
Quantum object: dims = [[[2], [2]], [[2], [2]]], shape = (4, 4), type = super,
↪ isherm = True
Qobj data =
[[0. 0. 0. 0.]
 [0. 0. 0. 0.]
 [0. 0. 0. 0.]
 [0. 0. 0. 0.]]
```

```
print(to_super(S))
```

Output:

```
Quantum object: dims = [[[2], [2]], [[2], [2]]], shape = (4, 4), type = super,
↪ isherm = True
Qobj data =
[[0. 0. 0. 1.]
 [0. 0. 1. 0.]
 [0. 1. 0. 0.]
 [1. 0. 0. 0.]]
```

We can quickly obtain another useful representation from the Choi matrix by taking its eigendecomposition. In particular, let $\{A_i\}$ be a set of operators such that $J(\Lambda) = \sum_i |A_i\rangle\rangle\langle\langle A_i|$. We can write $J(\Lambda)$ in this way for any hermicity-preserving map; that is, for any map Λ such that $J(\Lambda) = J^\dagger(\Lambda)$. These operators then form the Kraus representation of Λ . In particular, for any input ρ ,

$$\Lambda(\rho) = \sum_i A_i \rho A_i^\dagger.$$

Notice using the column-stacking identity that $(C^T \otimes A)|B\rangle\rangle = |ABC\rangle\rangle$, we have that

$$\sum_i (K \otimes A_i)(K \otimes A_i)^\dagger |K\rangle\rangle \langle\langle K| = \sum_i |A_i\rangle\rangle \langle\langle A_i| = J(\Lambda).$$

The Kraus representation of a hermicity-preserving map can be found in QuTiP using the `to_kraus` function.

```
del sum # np.sum overwrote sum and caused a bug.
```

```
I, X, Y, Z = qeye(2), sigmax(), sigmay(), sigmaz()
```

```
S = sum([sprepost(P, P) for P in (I, X, Y, Z)]) / 4
print(S)
```

Output:

```
Quantum object: dims = [[[2], [2]], [[2], [2]]], shape = (4, 4), type = super,
↳ isherm = True
Qobj data =
[[0.5 0.  0.  0.5]
 [0.  0.  0.  0. ]
 [0.  0.  0.  0. ]
 [0.5 0.  0.  0.5]]
```

```
J = to_choi(S)
print(J)
```

Output:

```
Quantum object: dims = [[[2], [2]], [[2], [2]]], shape = (4, 4), type = super,
↳ isherm = True, superrep = choi
Qobj data =
[[0.5 0.  0.  0. ]
 [0.  0.5 0.  0. ]
 [0.  0.  0.5 0. ]
 [0.  0.  0.  0.5]]
```

```
print(J.eigenstates()[1])
```

Output:

```
[Quantum object: dims = [[[2], [2]], [1, 1]], shape = (4, 1), type = operator-ket
Qobj data =
[[1.]
 [0.]
 [0.]
 [0.]]
Quantum object: dims = [[[2], [2]], [1, 1]], shape = (4, 1), type = operator-ket
Qobj data =
[[0.]
 [1.]
 [0.]
 [0.]]
Quantum object: dims = [[[2], [2]], [1, 1]], shape = (4, 1), type = operator-ket
Qobj data =
[[0.]
 [0.]
 [1.]
 [0.]]
Quantum object: dims = [[[2], [2]], [1, 1]], shape = (4, 1), type = operator-ket
Qobj data =
```

(continues on next page)

(continued from previous page)

```
[[0.]
 [0.]
 [0.]
 [1.]]]
```

```
K = to_kraus(S)
print(K)
```

Output:

```
[Quantum object: dims = [[2], [2]], shape = (2, 2), type = oper, isherm = True
Qobj data =
[[0.70710678 0.          ]
 [0.          0.          ]], Quantum object: dims = [[2], [2]], shape = (2, 2), type =
↪= oper, isherm = False
Qobj data =
[[0.          0.          ]
 [0.70710678 0.          ]], Quantum object: dims = [[2], [2]], shape = (2, 2), type =
↪= oper, isherm = False
Qobj data =
[[0.          0.70710678]
 [0.          0.          ]], Quantum object: dims = [[2], [2]], shape = (2, 2), type =
↪= oper, isherm = True
Qobj data =
[[0.          0.          ]
 [0.          0.70710678]]]
```

As with the other representation conversion functions, `to_kraus` checks the `superrep` attribute of its input, and chooses an appropriate conversion method. Thus, in the above example, we can also call `to_kraus` on `J`.

```
KJ = to_kraus(J)
print(KJ)
```

Output:

```
[Quantum object: dims = [[2], [2]], shape = (2, 2), type = oper, isherm = True
Qobj data =
[[0.70710678 0.          ]
 [0.          0.          ]], Quantum object: dims = [[2], [2]], shape = (2, 2), type =
↪= oper, isherm = False
Qobj data =
[[0.          0.          ]
 [0.70710678 0.          ]], Quantum object: dims = [[2], [2]], shape = (2, 2), type =
↪= oper, isherm = False
Qobj data =
[[0.          0.70710678]
 [0.          0.          ]], Quantum object: dims = [[2], [2]], shape = (2, 2), type =
↪= oper, isherm = True
Qobj data =
[[0.          0.          ]
 [0.          0.70710678]]]
```

```
for A, AJ in zip(K, KJ):
    print(A - AJ)
```

Output:

```
Quantum object: dims = [[2], [2]], shape = (2, 2), type = oper, isherm = True
Qobj data =
[[0. 0.]
```

(continues on next page)

(continued from previous page)

```
[0. 0.]]
Quantum object: dims = [[2], [2]], shape = (2, 2), type = oper, isherm = True
Qobj data =
[[0. 0.]
 [0. 0.]]
Quantum object: dims = [[2], [2]], shape = (2, 2), type = oper, isherm = True
Qobj data =
[[0. 0.]
 [0. 0.]]
Quantum object: dims = [[2], [2]], shape = (2, 2), type = oper, isherm = True
Qobj data =
[[0. 0.]
 [0. 0.]]
```

The Stinespring representation is closely related to the Kraus representation, and consists of a pair of operators A and B such that for all operators X acting on \mathcal{H} ,

$$\Lambda(X) = \text{Tr}_2(AXB^\dagger),$$

where the partial trace is over a new index that corresponds to the index in the Kraus summation. Conversion to Stinespring is handled by the `to_stinespring` function.

```
a = create(2).dag()

S_ad = sprepost(a * a.dag(), a * a.dag()) + sprepost(a, a.dag())
S = 0.9 * sprepost(I, I) + 0.1 * S_ad

print(S)
```

Output:

```
Quantum object: dims = [[[2], [2]], [[2], [2]]], shape = (4, 4), type = super,
↪ isherm = False
Qobj data =
[[1.  0.  0.  0.1]
 [0.  0.9 0.  0. ]
 [0.  0.  0.9 0. ]
 [0.  0.  0.  0.9]]
```

```
A, B = to_stinespring(S)
print(A)
```

Output:

```
Quantum object: dims = [[2, 3], [2]], shape = (6, 2), type = oper, isherm = False
Qobj data =
[[-0.98845443  0.          ]
 [ 0.          0.31622777]
 [ 0.15151842  0.          ]
 [ 0.          -0.93506452]
 [ 0.          0.          ]
 [ 0.          -0.16016975]]
```

```
print(B)
```

Output:

```
Quantum object: dims = [[2, 3], [2]], shape = (6, 2), type = oper, isherm = False
Qobj data =
[[-0.98845443  0.          ]
```

(continues on next page)

(continued from previous page)

```
[ 0.          0.31622777]
[ 0.15151842  0.          ]
[ 0.          -0.93506452]
[ 0.          0.          ]
[ 0.          -0.16016975]]
```

Notice that a new index has been added, such that A and B have dimensions $[[2, 3], [2]]$, with the length-3 index representing the fact that the Choi matrix is rank-3 (alternatively, that the map has three Kraus operators).

```
to_kraus(S)
print(to_choi(S).eigenenergies())
```

Output:

```
[0.          0.04861218  0.1          1.85138782]
```

Finally, the last superoperator representation supported by QuTiP is the χ -matrix representation,

$$\Lambda(\rho) = \sum_{\alpha, \beta} \chi_{\alpha, \beta} B_{\alpha} \rho B_{\beta}^{\dagger},$$

where $\{B_{\alpha}\}$ is a basis for the space of matrices acting on \mathcal{H} . In QuTiP, this basis is taken to be the Pauli basis $B_{\alpha} = \sigma_{\alpha}/\sqrt{2}$. Conversion to the χ formalism is handled by the `to_chi` function.

```
chi = to_chi(S)
print(chi)
```

Output:

```
Quantum object: dims = [[[2], [2]], [[2], [2]]], shape = (4, 4), type = super,
↳ isherm = True, superrep = chi
Qobj data =
[[3.7+0.j  0. +0.j  0. +0.j  0.1+0.j ]
 [0. +0.j  0.1+0.j  0. +0.1j  0. +0.j ]
 [0. +0.j  0. -0.1j  0.1+0.j  0. +0.j ]
 [0.1+0.j  0. +0.j  0. +0.j  0.1+0.j ]]
```

One convenient property of the χ matrix is that the average gate fidelity with the identity map can be read off directly from the χ_{00} element:

```
np.testing.assert_almost_equal(average_gate_fidelity(S), 0.9499999999999998)
print(chi[0, 0] / 4)
```

Output:

```
(0.925+0j)
```

Here, the factor of 4 comes from the dimension of the underlying Hilbert space \mathcal{H} . As with the superoperator and Choi representations, the χ representation is denoted by the `superrep`, such that `to_super`, `to_choi`, `to_kraus`, `to_stinespring` and `to_chi` all convert from the χ representation appropriately.

3.3.8 Properties of Quantum Maps

In addition to converting between the different representations of quantum maps, QuTiP also provides attributes to make it easy to check if a map is completely positive, trace preserving and/or hermicity preserving. Each of these attributes uses `superrep` to automatically perform any needed conversions.

In particular, a quantum map is said to be positive (but not necessarily completely positive) if it maps all positive operators to positive operators. For instance, the transpose map $\Lambda(\rho) = \rho^T$ is a positive map. We run into problems, however, if we tensor Λ with the identity to get a partial transpose map.

```
rho = ket2dm(bell_state())
rho_out = partial_transpose(rho, [0, 1])
print(rho_out.eigenenergies())
```

Output:

```
[-0.5  0.5  0.5  0.5]
```

Notice that even though we started with a positive map, we got an operator out with negative eigenvalues. Complete positivity addresses this by requiring that a map returns positive operators for all positive operators, and does so even under tensoring with another map. The Choi matrix is very useful here, as it can be shown that a map is completely positive if and only if its Choi matrix is positive [Wat13]. QuTiP implements this check with the `iscp` attribute. As an example, notice that the snippet above already calculates the Choi matrix of the transpose map by acting it on half of an entangled pair. We simply need to manually set the `dims` and `superrep` attributes to reflect the structure of the underlying Hilbert space and the chosen representation.

```
J = rho_out
J.dims = [[[2], [2]], [[2], [2]]]
J.superrep = 'choi'
print(J.iscp)
```

Output:

```
False
```

This confirms that the transpose map is not completely positive. On the other hand, the transpose map does satisfy a weaker condition, namely that it is hermicity preserving. That is, $\Lambda(\rho) = (\Lambda(\rho))^\dagger$ for all ρ such that $\rho = \rho^\dagger$. To see this, we note that $(\rho^T)^\dagger = \rho^*$, the complex conjugate of ρ . By assumption, $\rho = \rho^\dagger = (\rho^*)^T$, though, such that $\Lambda(\rho) = \Lambda(\rho^\dagger) = \rho^*$. We can confirm this by checking the `ishp` attribute:

```
print(J.ishp)
```

Output:

```
True
```

Next, we note that the transpose map does preserve the trace of its inputs, such that $\text{Tr}(\Lambda[\rho]) = \text{Tr}(\rho)$ for all ρ . This can be confirmed by the `istp` attribute:

```
print(J.istp)
```

Output:

```
False
```

Finally, a map is called a quantum channel if it always maps valid states to valid states. Formally, a map is a channel if it is both completely positive and trace preserving. Thus, QuTiP provides a single attribute to quickly check that this is true.

```
>>> print(J.iscftp)
False

>>> print(to_super(qeye(2)).iscftp)
True
```

3.4 Using Tensor Products and Partial Traces

3.4.1 Tensor products

To describe the states of multipartite quantum systems - such as two coupled qubits, a qubit coupled to an oscillator, etc. - we need to expand the Hilbert space by taking the tensor product of the state vectors for each of the system components. Similarly, the operators acting on the state vectors in the combined Hilbert space (describing the coupled system) are formed by taking the tensor product of the individual operators.

In QuTiP the function `qutip.core.tensor.tensor` is used to accomplish this task. This function takes as argument a collection:

```
>>> tensor(op1, op2, op3)
```

or a list:

```
>>> tensor([op1, op2, op3])
```

of state vectors *or* operators and returns a composite quantum object for the combined Hilbert space. The function accepts an arbitrary number of states or operators as argument. The type returned quantum object is the same as that of the input(s).

For example, the state vector describing two qubits in their ground states is formed by taking the tensor product of the two single-qubit ground state vectors:

```
print(tensor(basis(2, 0), basis(2, 0)))
```

Output:

```
Quantum object: dims = [[2, 2], [1, 1]], shape = (4, 1), type = ket
Qobj data =
[[1.]
 [0.]
 [0.]
 [0.]]
```

or equivalently using the list format:

```
print(tensor([basis(2, 0), basis(2, 0)]))
```

Output:

```
Quantum object: dims = [[2, 2], [1, 1]], shape = (4, 1), type = ket
Qobj data =
[[1.]
 [0.]
 [0.]
 [0.]]
```

This is straightforward to generalize to more qubits by adding more component state vectors in the argument list to the `qutip.core.tensor.tensor` function, as illustrated in the following example:

```
print(tensor((basis(2, 0) + basis(2, 1)).unit(), (basis(2, 0) + basis(2, 1)).
↪unit(), basis(2, 0)))
```

Output:

```
Quantum object: dims = [[2, 2, 2], [1, 1, 1]], shape = (8, 1), type = ket
Qobj data =
[[0.5]
 [0. ]
 [0.5]
 [0. ]
 [0.5]
 [0. ]
 [0.5]
 [0. ]]
```

This state is slightly more complicated, describing two qubits in a superposition between the up and down states, while the third qubit is in its ground state.

To construct operators that act on an extended Hilbert space of a combined system, we similarly pass a list of operators for each component system to the `qutip.core.tensor.tensor` function. For example, to form the operator that represents the simultaneous action of the σ_x operator on two qubits:

```
print(tensor(sigmax(), sigmax()))
```

Output:

```
Quantum object: dims = [[2, 2], [2, 2]], shape = (4, 4), type = oper, isherm = True
Qobj data =
[[0. 0. 0. 1.]
 [0. 0. 1. 0.]
 [0. 1. 0. 0.]
 [1. 0. 0. 0.]]
```

To create operators in a combined Hilbert space that only act on a single component, we take the tensor product of the operator acting on the subspace of interest, with the identity operators corresponding to the components that are to be unchanged. For example, the operator that represents σ_z on the first qubit in a two-qubit system, while leaving the second qubit unaffected:

```
print(tensor(sigmaz(), identity(2)))
```

Output:

```
Quantum object: dims = [[2, 2], [2, 2]], shape = (4, 4), type = oper, isherm = True
Qobj data =
[[ 1.  0.  0.  0.]
 [ 0.  1.  0.  0.]
 [ 0.  0. -1.  0.]
 [ 0.  0.  0. -1.]]
```


3.4.2 Example: Constructing composite Hamiltonians

The `qutip.core.tensor.tensor` function is extensively used when constructing Hamiltonians for composite systems. Here we'll look at some simple examples.

Two coupled qubits

First, let's consider a system of two coupled qubits. Assume that both the qubits have equal energy splitting, and that the qubits are coupled through a $\sigma_x \otimes \sigma_x$ interaction with strength $g = 0.05$ (in units where the bare qubit energy splitting is unity). The Hamiltonian describing this system is:

```
H = tensor(sigmaz(), identity(2)) + tensor(identity(2), sigmaz()) + 0.05 *
↳ tensor(sigmax(), sigmax())

print(H)
```

Output:

```
Quantum object: dims = [[2, 2], [2, 2]], shape = (4, 4), type = oper, isherm = True
Qobj data =
[[ 2.    0.    0.    0.05]
 [ 0.    0.    0.05  0. ]
 [ 0.    0.05  0.    0. ]
 [ 0.05  0.    0.   -2. ]]
```

Three coupled qubits

The two-qubit example is easily generalized to three coupled qubits:

```
H = (tensor(sigmaz(), identity(2), identity(2)) + tensor(identity(2), sigmaz(),
↳ identity(2)) + tensor(identity(2), identity(2), sigmaz())) + 0.5 *
↳ tensor(sigmax(), sigmax(), identity(2)) + 0.25 * tensor(identity(2), sigmax(),
↳ sigmax()))

print(H)
```

Output:

```
Quantum object: dims = [[2, 2, 2], [2, 2, 2]], shape = (8, 8), type = oper, isherm
↳ = True
Qobj data =
[[ 3.    0.    0.    0.25  0.    0.    0.5    0. ]
 [ 0.    1.    0.25  0.    0.    0.    0.    0.5 ]
 [ 0.    0.25  1.    0.    0.5    0.    0.    0. ]
 [ 0.25  0.    0.   -1.    0.    0.5    0.    0. ]
 [ 0.    0.    0.5    0.    1.    0.    0.    0.25]
 [ 0.    0.    0.    0.5    0.   -1.    0.25  0. ]
 [ 0.5    0.    0.    0.    0.    0.25 -1.    0. ]
 [ 0.    0.5    0.    0.    0.25  0.    0.   -3. ]]
```

A two-level system coupled to a cavity: The Jaynes-Cummings model

The simplest possible quantum mechanical description for light-matter interaction is encapsulated in the Jaynes-Cummings model, which describes the coupling between a two-level atom and a single-mode electromagnetic field (a cavity mode). Denoting the energy splitting of the atom and cavity ω_a and ω_c , respectively, and the atom-cavity interaction strength g , the Jaynes-Cummings Hamiltonian can be constructed as:

```
N = 10

omega_a = 1.0

omega_c = 1.25

g = 0.05

a = tensor(identity(2), destroy(N))

sm = tensor(destroy(2), identity(N))

sz = tensor(sigmaz(), identity(N))

H = 0.5 * omega_a * sz + omega_c * a.dag() * a + g * (a.dag() * sm + a * sm.dag())

print(H)
```

Output:

```
Quantum object: dims = [[2, 10], [2, 10]], shape = (20, 20), type = oper, isherm = True
Qobj data =
[[ 0.5      0.      0.      0.      0.      0.
  0.      0.      0.      0.      0.      0.
  0.      0.      0.      0.      0.      0.
  0.      0.      ]
 [ 0.      1.75    0.      0.      0.      0.
  0.      0.      0.      0.      0.05    0.
  0.      0.      0.      0.      0.      0.
  0.      0.      ]
 [ 0.      0.      3.      0.      0.      0.
  0.      0.      0.      0.      0.      0.07071068
  0.      0.      0.      0.      0.      0.
  0.      0.      ]
 [ 0.      0.      0.      4.25    0.      0.
  0.      0.      0.      0.      0.      0.
  0.08660254 0.      0.      0.      0.      0.
  0.      0.      ]
 [ 0.      0.      0.      0.      5.5     0.
  0.      0.      0.      0.      0.      0.
  0.      0.1     0.      0.      0.      0.
  0.      0.      ]
 [ 0.      0.      0.      0.      0.      6.75
  0.      0.      0.      0.      0.      0.
  0.      0.      0.1118034 0.      0.      0.
  0.      0.      ]
 [ 0.      0.      0.      0.      0.      0.
  8.      0.      0.      0.      0.      0.
  0.      0.      0.      0.12247449 0.      0.
  0.      0.      ]
 [ 0.      0.      0.      0.      0.      0.
  0.      9.25    0.      0.      0.      0.
  0.      0.      0.      0.      0.13228757 0.
  0.      0.      ]
```

(continues on next page)

(continued from previous page)

```
[ 0.      0.      0.      0.      0.      0.
  0.      0.     10.5     0.      0.      0.
  0.      0.      0.      0.      0.     0.14142136
  0.      0.      ]
[ 0.      0.      0.      0.      0.      0.
  0.      0.      0.     11.75     0.      0.
  0.      0.      0.      0.      0.      0.
  0.15     0.      ]
[ 0.      0.05     0.      0.      0.      0.
  0.      0.      0.      0.     -0.5     0.
  0.      0.      0.      0.      0.      0.
  0.      0.      ]
[ 0.      0.      0.07071068  0.      0.      0.
  0.      0.      0.      0.      0.     0.75
  0.      0.      0.      0.      0.      0.
  0.      0.      ]
[ 0.      0.      0.      0.08660254  0.      0.
  0.      0.      0.      0.      0.      0.
  2.      0.      0.      0.      0.      0.
  0.      0.      ]
[ 0.      0.      0.      0.      0.1      0.
  0.      0.      0.      0.      0.      0.
  0.      3.25     0.      0.      0.      0.
  0.      0.      ]
[ 0.      0.      0.      0.      0.      0.1118034
  0.      0.      0.      0.      0.      0.
  0.      0.      4.5     0.      0.      0.
  0.      0.      ]
[ 0.      0.      0.      0.      0.      0.
  0.12247449  0.      0.      0.      0.      0.
  0.      0.      0.      5.75     0.      0.
  0.      0.      ]
[ 0.      0.      0.      0.      0.      0.
  0.      0.13228757  0.      0.      0.      0.
  0.      0.      0.      0.      7.      0.
  0.      0.      ]
[ 0.      0.      0.      0.      0.      0.
  0.      0.      0.14142136  0.      0.      0.
  0.      0.      0.      0.      0.      8.25
  0.      0.      ]
[ 0.      0.      0.      0.      0.      0.
  0.      0.      0.      0.15     0.      0.
  0.      0.      0.      0.      0.      0.
  9.5     0.      ]
[ 0.      0.      0.      0.      0.      0.
  0.      0.      0.      0.      0.      0.
  0.      0.      0.      0.      0.      0.
  0.      10.75   ]]
```

Here N is the number of Fock states included in the cavity mode.

3.4.3 Partial trace

The partial trace is an operation that reduces the dimension of a Hilbert space by eliminating some degrees of freedom by averaging (tracing). In this sense it is therefore the converse of the tensor product. It is useful when one is interested in only a part of a coupled quantum system. For open quantum systems, this typically involves tracing over the environment leaving only the system of interest. In QuTiP the class method `qutip.Qobj.ptrace` is used to take partial traces. `qutip.Qobj.ptrace` acts on the `qutip.Qobj` instance for which it is called, and it takes one argument `sel`, which is a list of integers that mark the component systems that should be **kept**. All other components are traced out.

For example, the density matrix describing a single qubit obtained from a coupled two-qubit system is obtained via:

```
>>> psi = tensor(basis(2, 0), basis(2, 1))

>>> psi.ptrace(0)
Quantum object: dims = [[2], [2]], shape = (2, 2), type = oper, isherm = True
Qobj data =
[[1. 0.]
 [0. 0.]]

>>> psi.ptrace(1)
Quantum object: dims = [[2], [2]], shape = (2, 2), type = oper, isherm = True
Qobj data =
[[0. 0.]
 [0. 1.]]
```

Note that the partial trace always results in a density matrix (mixed state), regardless of whether the composite system is a pure state (described by a state vector) or a mixed state (described by a density matrix):

```
>>> psi = tensor((basis(2, 0) + basis(2, 1)).unit(), basis(2, 0))

>>> psi
Quantum object: dims = [[2, 2], [1, 1]], shape = (4, 1), type = ket
Qobj data =
[[0.70710678]
 [0.         ]
 [0.70710678]
 [0.         ]]

>>> psi.ptrace(0)
Quantum object: dims = [[2], [2]], shape = (2, 2), type = oper, isherm = True
Qobj data =
[[0.5 0.5]
 [0.5 0.5]]

>>> rho = tensor(ket2dm((basis(2, 0) + basis(2, 1)).unit()), fock_dm(2, 0))

>>> rho
Quantum object: dims = [[2, 2], [2, 2]], shape = (4, 4), type = oper, isherm = True
Qobj data =
[[0.5 0.  0.5 0. ]
 [0.  0.  0.  0. ]
 [0.5 0.  0.5 0. ]
 [0.  0.  0.  0. ]]

>>> rho.ptrace(0)
Quantum object: dims = [[2], [2]], shape = (2, 2), type = oper, isherm = True
Qobj data =
[[0.5 0.5]
 [0.5 0.5]]
```

3.4.4 Superoperators and Tensor Manipulations

As described in *Superoperators and Vectorized Operators*, *superoperators* are operators that act on Liouville space, the vectorspace of linear operators. Superoperators can be represented using the isomorphism $\text{vec} : \mathcal{L}(\mathcal{H}) \rightarrow \mathcal{H} \otimes \mathcal{H}$ [Hav03], [Wat13]. To represent superoperators acting on $\mathcal{L}(\mathcal{H}_1 \otimes \mathcal{H}_2)$ thus takes some tensor rearrangement to get the desired ordering $\mathcal{H}_1 \otimes \mathcal{H}_2 \otimes \mathcal{H}_1 \otimes \mathcal{H}_2$.

In particular, this means that `qutip.tensor` does not act as one might expect on the results of `qutip.superop_reps.to_super`:

```
>>> A = qeye([2])
>>> B = qeye([3])
>>> to_super(tensor(A, B)).dims
[[2, 3], [2, 3]], [[2, 3], [2, 3]]
>>> tensor(to_super(A), to_super(B)).dims
[[[2], [2], [3], [3]], [[2], [2], [3], [3]]]
```

In the former case, the result correctly has four copies of the compound index with dims `[2, 3]`. In the latter case, however, each of the Hilbert space indices is listed independently and in the wrong order.

The `qutip.tensor.super_tensor` function performs the needed rearrangement, providing the most direct analog to `qutip.tensor` on the underlying Hilbert space. In particular, for any two `type="oper"` Qobjs `A` and `B`, `to_super(tensor(A, B)) == super_tensor(to_super(A), to_super(B))` and `operator_to_vector(tensor(A, B)) == super_tensor(operator_to_vector(A), operator_to_vector(B))`. Returning to the previous example:

```
>>> super_tensor(to_super(A), to_super(B)).dims
[[[2, 3], [2, 3]], [[2, 3], [2, 3]]]
```

The `qutip.tensor.composite` function automatically switches between `qutip.tensor` and `qutip.tensor.super_tensor` based on the type of its arguments, such that `composite(A, B)` returns an appropriate Qobj to represent the composition of two systems.

```
>>> composite(A, B).dims
[[2, 3], [2, 3]]
>>> composite(to_super(A), to_super(B)).dims
[[[2, 3], [2, 3]], [[2, 3], [2, 3]]]
```

QuTiP also allows more general tensor manipulations that are useful for converting between superoperator representations [WBC11]. In particular, the `tensor_contract` function allows for contracting one or more pairs of indices. As detailed in the [channel contraction tutorial](#), this can be used to find superoperators that represent partial trace maps. Using this functionality, we can construct some quite exotic maps, such as a map from 3×3 operators to 2×2 operators:

```
>>> tensor_contract(composite(to_super(A), to_super(B)), (1, 3), (4, 6)).dims
[[[2], [2]], [[3], [3]]]
```

3.5 Time Evolution and Quantum System Dynamics

3.5.1 Introduction

Although in some cases, we want to find the stationary states of a quantum system, often we are interested in the dynamics: how the state of a system or an ensemble of systems evolves with time. QuTiP provides many ways to model dynamics.

Broadly speaking, there are two categories of dynamical models: unitary and non-unitary. In unitary evolution, the state of the system remains normalized. In non-unitary, or dissipative, systems, it does not.

There are two kinds of quantum systems: open systems that interact with a larger environment and closed systems that do not. In a closed system, the state can be described by a state vector, although when there is entanglement a density matrix may be needed instead. When we are modeling an open system, or an ensemble of systems, the use of the density matrix is mandatory.

Collapse operators are used to model the collapse of the state vector that can occur when a measurement is performed.

The following tables lists some of the solvers QuTiP provides for dynamic quantum systems and indicates the type of object returned by the solver:

Table 1: QuTiP Solvers

Solver	Returns	Remarks
<code>sesolve()</code>	<code>qutip.solver.Result</code>	Unitary evolution, single system
<code>mesolve()</code>	<code>qutip.solver.Result</code>	Lindblad master eqn. or Von Neuman eqn. Density matrix.
<code>mcsolve()</code>	<code>qutip.solver.Result</code>	Monte Carlo with collapse operators
<code>essolve()</code>	Array of expectation values	Exponential series with collapse operators
<code>bloch_redfield_solve()</code>	<code>qutip.solver</code>	
<code>floquet_markov_solve()</code>	<code>qutip.solver.Result</code>	Floquet-Markov master equation
<code>fmmsolve()</code>	<code>qutip.solver</code>	Floquet-Markov master equation
<code>smesolve()</code>	<code>qutip.solver.Result</code>	Stochastic master equation
<code>ssesolve()</code>	<code>qutip.solver.Result</code>	Stochastic Schrödinger equation

3.5.2 Dynamics Simulation Results

The `solver.Result` Class

Before embarking on simulating the dynamics of quantum systems, we will first look at the data structure used for returning the simulation results. This object is a `qutip.Result` class that stores all the crucial data needed for analyzing and plotting the results of a simulation. A generic `Result` object `result` contains the following properties for storing simulation data:

Property	Description
<code>result.solver</code>	String indicating which solver was used to generate the data.
<code>result.times</code>	List/array of times at which simulation data is calculated.
<code>result.expect</code>	List/array of expectation values, if requested.
<code>result.e_data</code>	Dictionary of expectation values, if requested.
<code>result.states</code>	List/array of state vectors/density matrices calculated at <code>times</code> , if requested.
<code>result.final_state</code>	State vector or density matrix at the last time of the evolution.
<code>result.stats</code>	Various statistics about the evolution including the integration method used, number of collapse operators etc.

Accessing Result Data

To understand how to access the data in a `Result` object we will use an example as a guide, although we do not worry about the simulation details at this stage. Like all solvers, the Master Equation solver used in this example returns an `Result` object, here called simply `result`. To see what is contained inside `result` we can use the `print` function:

```
>>> print(result)
<Result
  Solver: mesolve
  Solver stats:
    method: 'scipy zvode adams'
    init time: 0.0001876354217529297
    preparation time: 0.007544517517089844
    run time: 0.001268625259399414
    solver: 'Master Equation Evolution'
    num_collapse: 1
  Time interval: [0, 1.0] (2 steps)
  Number of e_ops: 1
  State not saved.
>
```

The first line tells us that this data object was generated from the Master Equation solver `mesolve`. Next we have the statistics including the ODE solver used, setup time, number of collapses. Then the integration interval is described, followed with the number of expectation value computed. Finally, it says whether the states are stored.

Now we have all the information needed to analyze the simulation results. To access the data for the two expectation values one can do:

```
expt0 = result.expect[0]
expt1 = result.expect[1]
```

Recall that Python uses C-style indexing that begins with zero (i.e., `[0]` => 1st collapse operator data). Alternatively, expectation values can be obtained as a dictionary:

```
e_ops = {"sx": sigmax(), "sy": sigmay(), "sz": sigmaz()}
...
expt_sx = result.e_data["sx"]
```

When `e_ops` is a list, `e_data` can be used with the list index. Together with the array of times at which these expectation values are calculated:

```
times = result.times
```

we can plot the resulting expectation values:

```
plot(times, expt0)
plot(times, expt1)
show()
```

State vectors, or density matrices, are accessed in a similar manner, although typically one does not need an index (i.e [0]) since there is only one list for each of these components. Some other solver can have other output, `heomsolve`'s results can have `ado_states` output if the options `store_ados` is set, similarly, `fmesolve` can return `floquet_states`.

Multiple Trajectories Solver Results

Solver which compute multiple trajectories such as the Monte Carlo Equations Solvers or the Stochastics Solvers result will differ depending on whether the trajectories are flags to be saved. For example:

```
>>> mcsolve(H, psi, np.linspace(0, 1, 11), c_ops, e_ops=[num(N)], ntraj=25,
↳ options={"keep_runs_results": False})
>>> np.shape(result.expect)
(1, 11)

>>> mcsolve(H, psi, np.linspace(0, 1, 11), c_ops, e_ops=[num(N)], ntraj=25,
↳ options={"keep_runs_results": True})
>>> np.shape(result.expect)
(1, 25, 11)
```

When the runs are not saved, the expectation values and states are averaged over all trajectories, while a list over the runs are given when they are stored. For a fix output format, `average_expect` return the average, while `runs_states` return the list over trajectories. The `runs_` output will return `None` when the trajectories are not saved. Standard derivation of the expectation values is also available:

Reduced result	Trajectories results	Description
<code>average_states</code>	<code>runs_states</code>	State vectors or density matrices calculated at each times of tlist
<code>average_final_state</code>	<code>runs_final_state</code>	State vectors or density matrices calculated at the last time of tlist
<code>average_expect</code>	<code>runs_expect</code>	List/array of expectation values, if requested.
<code>std_expect</code>		List/array of standard derivation of the expectation values.
<code>average_e_data</code>	<code>runs_e_data</code>	Dictionary of expectation values, if requested.
<code>std_e_data</code>		Dictionary of standard derivation of the expectation values.

Multiple trajectories results also keep the trajectories seeds to allows recomputing the results.

```
seeds = result.seeds
```

3.5.3 Lindblad Master Equation Solver

Unitary evolution

The dynamics of a closed (pure) quantum system is governed by the Schrödinger equation

$$i\hbar \frac{\partial}{\partial t} \Psi = \hat{H} \Psi, \quad (3.1)$$

where Ψ is the wave function, \hat{H} the Hamiltonian, and \hbar is Planck's constant. In general, the Schrödinger equation is a partial differential equation (PDE) where both Ψ and \hat{H} are functions of space and time. For computational

purposes it is useful to expand the PDE in a set of basis functions that span the Hilbert space of the Hamiltonian, and to write the equation in matrix and vector form


$$i\hbar \frac{d}{dt} |\psi\rangle = H |\psi\rangle$$

where $|\psi\rangle$ is the state vector and H is the matrix representation of the Hamiltonian. This matrix equation can, in principle, be solved by diagonalizing the Hamiltonian matrix H . In practice, however, it is difficult to perform this diagonalization unless the size of the Hilbert space (dimension of the matrix H) is small. Analytically, it is a formidable task to calculate the dynamics for systems with more than two states. If, in addition, we consider dissipation due to the inevitable interaction with a surrounding environment, the computational complexity grows even larger, and we have to resort to numerical calculations in all realistic situations. This illustrates the importance of numerical calculations in describing the dynamics of open quantum systems, and the need for efficient and accessible tools for this task.

The Schrödinger equation, which governs the time-evolution of closed quantum systems, is defined by its Hamiltonian and state vector. In the previous section, *Using Tensor Products and Partial Traces*, we showed how Hamiltonians and state vectors are constructed in QuTiP. Given a Hamiltonian, we can calculate the unitary (non-dissipative) time-evolution of an arbitrary state vector $|\psi_0\rangle$ (`psi0`) using the QuTiP function `qutip.sesolve`. It evolves the state vector and evaluates the expectation values for a set of operators `e_ops` at the points in time in the list `times`, using an ordinary differential equation solver.

For example, the time evolution of a quantum spin-1/2 system with tunneling rate 0.1 that initially is in the up state is calculated, and the expectation values of the σ_z operator evaluated, with the following code

```
>>> H = 2*np.pi * 0.1 * sigmax()
>>> psi0 = basis(2, 0)
>>> times = np.linspace(0.0, 10.0, 20)
>>> result = sesolve(H, psi0, times, e_ops=[sigmaz()])
```




See the next section for examples on how dissipation is included by defining a list of collapse operators and using

qutip.mesolve instead.

The function returns an instance of `qutip.Result`, as described in the previous section [Dynamics Simulation Results](#). The attribute `expect` in `result` is a list of expectation values for the operators that are included in the list in the fifth argument. Adding operators to this list results in a larger output list returned by the function (one array of numbers, corresponding to the times in `times`, for each operator)

```
>>> result = sesolve(H, psi0, times, e_ops=[sigmaz(), sigmay()])
>>> result.expect
[array([ 1.          ,  0.78914057,  0.24548559, -0.40169513, -0.8794735 ,
        -0.98636142, -0.67728219, -0.08258023,  0.54694721,  0.94581685,
         0.94581769,  0.54694945, -0.08257765, -0.67728015, -0.98636097,
        -0.87947476, -0.40169736,  0.24548326,  0.78913896,  1.          ]),
 array([ 0.00000000e+00, -6.14212640e-01, -9.69400240e-01, -9.15773457e-01,
        -4.75947849e-01,  1.64593874e-01,  7.35723339e-01,  9.96584419e-01,
         8.37167094e-01,  3.24700624e-01, -3.24698160e-01, -8.37165632e-01,
        -9.96584633e-01, -7.35725221e-01, -1.64596567e-01,  4.75945525e-01,
         9.15772479e-01,  9.69400830e-01,  6.14214701e-01,  2.77159958e-06])]
```




The resulting list of expectation values can easily be visualized using matplotlib's plotting functions:


```
>>> H = 2*np.pi * 0.1 * sigmax()
>>> psi0 = basis(2, 0)
>>> times = np.linspace(0.0, 10.0, 100)
>>> result = sesolve(H, psi0, times, [sigmaz(), sigmay()])
>>> fig, ax = plt.subplots()
>>> ax.plot(result.times, result.expect[0])
>>> ax.plot(result.times, result.expect[1])
>>> ax.set_xlabel('Time')
>>> ax.set_ylabel('Expectation values')
```

(continues on next page)

(continued from previous page)

```
>>> ax.legend(("Sigma-Z", "Sigma-Y"))
>>> plt.show()
```





If an empty list of operators is passed to the `e_ops` parameter, the `qutip.sesolve` and `qutip.mesolve` functions return a `qutip.Result` instance that contains a list of state vectors for the times specified in `times`

```
>>> times = [0.0, 1.0]
>>> result = sesolve(H, psi0, times, [])
>>> result.states
[Quantum object: dims = [[2], [1]], shape = (2, 1), type = ket
Qobj data =
[[1.]
 [0.]], Quantum object: dims = [[2], [1]], shape = (2, 1), type = ket
Qobj data =
[[0.80901699+0.j]
 [0.          -0.58778526j]]]
```

Non-unitary evolution

While the evolution of the state vector in a closed quantum system is deterministic, open quantum systems are stochastic in nature. The effect of an environment on the system of interest is to induce stochastic transitions between energy levels, and to introduce uncertainty in the phase difference between states of the system. The state of an open quantum system is therefore described in terms of ensemble averaged states using the density matrix formalism. A density matrix ρ describes a probability distribution of quantum states $|\psi_n\rangle$, in a matrix representation $\rho = \sum_n p_n |\psi_n\rangle \langle\psi_n|$, where p_n is the classical probability that the system is in the quantum state $|\psi_n\rangle$. The time evolution of a density matrix ρ is the topic of the remaining portions of this section.

The Lindblad Master equation

The standard approach for deriving the equations of motion for a system interacting with its environment is to expand the scope of the system to include the environment. The combined quantum system is then closed, and its evolution is governed by the von Neumann equation

$$\dot{\rho}_{\text{tot}}(t) = -\frac{i}{\hbar}[H_{\text{tot}}, \rho_{\text{tot}}(t)], \quad (3.2)$$

the equivalent of the Schrödinger equation (3.1) in the density matrix formalism. Here, the total Hamiltonian

$$H_{\text{tot}} = H_{\text{sys}} + H_{\text{env}} + H_{\text{int}},$$

includes the original system Hamiltonian H_{sys} , the Hamiltonian for the environment H_{env} , and a term representing the interaction between the system and its environment H_{int} . Since we are only interested in the dynamics of the system, we can at this point perform a partial trace over the environmental degrees of freedom in Eq. (3.2), and thereby obtain a master equation for the motion of the original system density matrix. The most general trace-preserving and completely positive form of this evolution is the Lindblad master equation for the reduced density matrix $\rho = \text{Tr}_{\text{env}}[\rho_{\text{tot}}]$

$$\dot{\rho}(t) = -\frac{i}{\hbar}[H(t), \rho(t)] + \sum_n \frac{1}{2} [2C_n \rho(t) C_n^\dagger - \rho(t) C_n^\dagger C_n - C_n^\dagger C_n \rho(t)] \quad (3.3)$$

where the $C_n = \sqrt{\gamma_n} A_n$ are collapse operators, and A_n are the operators through which the environment couples to the system in H_{int} , and γ_n are the corresponding rates. The derivation of Eq. (3.3) may be found in several sources, and will not be reproduced here. Instead, we emphasize the approximations that are required to arrive at the master equation in the form of Eq. (3.3) from physical arguments, and hence perform a calculation in QuTiP:

- **Separability:** At $t = 0$ there are no correlations between the system and its environment such that the total density matrix can be written as a tensor product $\rho_{\text{tot}}^I(0) = \rho^I(0) \otimes \rho_{\text{env}}^I(0)$.
- **Born approximation:** Requires: (1) that the state of the environment does not significantly change as a result of the interaction with the system; (2) The system and the environment remain separable throughout the evolution. These assumptions are justified if the interaction is weak, and if the environment is much larger than the system. In summary, $\rho_{\text{tot}}(t) \approx \rho(t) \otimes \rho_{\text{env}}$.
- **Markov approximation** The time-scale of decay for the environment τ_{env} is much shorter than the smallest time-scale of the system dynamics $\tau_{\text{sys}} \gg \tau_{\text{env}}$. This approximation is often deemed a “short-memory environment” as it requires that environmental correlation functions decay on a time-scale fast compared to those of the system.
- **Secular approximation** Stipulates that elements in the master equation corresponding to transition frequencies satisfy $|\omega_{ab} - \omega_{cd}| \ll 1/\tau_{\text{sys}}$, i.e., all fast rotating terms in the interaction picture can be neglected. It also ignores terms that lead to a small renormalization of the system energy levels. This approximation is not strictly necessary for all master-equation formalisms (e.g., the Block-Redfield master equation), but it is required for arriving at the Lindblad form (3.3) which is used in `qutip.mesolve`.

For systems with environments satisfying the conditions outlined above, the Lindblad master equation (3.3) governs the time-evolution of the system density matrix, giving an ensemble average of the system dynamics. In order to ensure that these approximations are not violated, it is important that the decay rates γ_n be smaller than the minimum energy splitting in the system Hamiltonian. Situations that demand special attention therefore include, for

example, systems strongly coupled to their environment, and systems with degenerate or nearly degenerate energy levels.


For non-unitary evolution of a quantum systems, i.e., evolution that includes incoherent processes such as relaxation and dephasing, it is common to use master equations. In QuTiP, the function `qutip.mesolve` is used for both: the evolution according to the Schrödinger equation and to the master equation, even though these two equations of motion are very different. The `qutip.mesolve` function automatically determines if it is sufficient to use the Schrödinger equation (if no collapse operators were given) or if it has to use the master equation (if collapse operators were given). Note that to calculate the time evolution according to the Schrödinger equation is easier and much faster (for large systems) than using the master equation, so if possible the solver will fall back on using the Schrödinger equation.

What is new in the master equation compared to the Schrödinger equation are processes that describe dissipation in the quantum system due to its interaction with an environment. These environmental interactions are defined by the operators through which the system couples to the environment, and rates that describe the strength of the processes.

In QuTiP, the product of the square root of the rate and the operator that describe the dissipation process is called a collapse operator. A list of collapse operators (`c_ops`) is passed as the fourth argument to the `qutip.mesolve` function in order to define the dissipation processes in the master equation. When the `c_ops` isn't empty, the `qutip.mesolve` function will use the master equation instead of the unitary Schrödinger equation.

Using the example with the spin dynamics from the previous section, we can easily add a relaxation process (describing the dissipation of energy from the spin to its environment), by adding `np.sqrt(0.05) * sigmax()` in the fourth parameter to the `qutip.mesolve` function and moving the expectation operators [`sigmaz()`, `sigmay()`] to the fifth argument.


```
>>> times = np.linspace(0.0, 10.0, 100)
>>> result = mesolve(H, psi0, times, [np.sqrt(0.05) * sigmax()], e_ops=[sigmaz(),
↳sigmay()])
>>> fig, ax = plt.subplots()
>>> ax.plot(times, result.expect[0])
>>> ax.plot(times, result.expect[1])
>>> ax.set_xlabel('Time')
>>> ax.set_ylabel('Expectation values')
>>> ax.legend(("Sigma-Z", "Sigma-Y"))
>>> plt.show()
```



Here, 0.05 is the rate and the operator σ_x (`qutip.sigmax`) describes the dissipation process.

Now a slightly more complex example: Consider a two-level atom coupled to a leaky single-mode cavity through a dipole-type interaction, which supports a coherent exchange of quanta between the two systems. If the atom initially is in its groundstate and the cavity in a 5-photon Fock state, the dynamics is calculated with the lines following code

```
>>> times = np.linspace(0.0, 10.0, 200)
>>> psi0 = tensor(fock(2,0), fock(10, 5))
>>> a = tensor(qeye(2), destroy(10))
>>> sm = tensor(destroy(2), qeye(10))
>>> H = 2 * np.pi * a.dag() * a + 2 * np.pi * sm.dag() * sm + 2 * np.pi * 0.25 * ↪
↪ (sm * a.dag() + sm.dag() * a)
>>> result = mesolve(H, psi0, times, [np.sqrt(0.1)*a], e_ops=[a.dag()*a, sm.
↪ dag()*sm])
>>> plt.figure()
>>> plt.plot(times, result.expect[0])
>>> plt.plot(times, result.expect[1])
>>> plt.xlabel('Time')
>>> plt.ylabel('Expectation values')
>>> plt.legend(("cavity photon number", "atom excitation probability"))
>>> plt.show()
```



3.5.4 Monte Carlo Solver

Introduction

Whereas the density matrix formalism describes the ensemble average over many identical realizations of a quantum system, the Monte Carlo (MC), or quantum-jump approach to wave function evolution, allows for simulating an individual realization of the system dynamics. Here, the environment is continuously monitored, resulting in a series of quantum jumps in the system wave function, conditioned on the increase in information gained about the state of the system via the environmental measurements. In general, this evolution is governed by the Schrödinger equation with a **non-Hermitian** effective Hamiltonian

$$H_{\text{eff}} = H_{\text{sys}} - \frac{i\hbar}{2} \sum_i C_n^+ C_n, \quad (3.4)$$

where again, the C_n are collapse operators, each corresponding to a separate irreversible process with rate γ_n . Here, the strictly negative non-Hermitian portion of Eq. (3.4) gives rise to a reduction in the norm of the wave function, that to first-order in a small time δt , is given by $\langle \psi(t + \delta t) | \psi(t + \delta t) \rangle = 1 - \delta p$ where

$$\delta p = \delta t \sum_n \langle \psi(t) | C_n^+ C_n | \psi(t) \rangle, \quad (3.5)$$

and δt is such that $\delta p \ll 1$. With a probability of remaining in the state $|\psi(t + \delta t)\rangle$ given by $1 - \delta p$, the corresponding quantum jump probability is thus Eq. (3.5). If the environmental measurements register a quantum jump, say via the emission of a photon into the environment, or a change in the spin of a quantum dot, the wave function undergoes a jump into a state defined by projecting $|\psi(t)\rangle$ using the collapse operator C_n corresponding to the measurement

$$|\psi(t + \delta t)\rangle = C_n |\psi(t)\rangle / \langle \psi(t) | C_n^+ C_n | \psi(t) \rangle^{1/2}. \quad (3.6)$$

If more than a single collapse operator is present in Eq. (3.4), the probability of collapse due to the i th-operator C_i is given by

$$P_i(t) = \langle \psi(t) | C_i^\dagger C_i | \psi(t) \rangle / \delta p. \quad (3.7)$$

Evaluating the MC evolution to first-order in time is quite tedious. Instead, QuTiP uses the following algorithm to simulate a single realization of a quantum system. Starting from a pure state $|\psi(0)\rangle$:

- **Ia:** Choose a random number r_1 between zero and one, representing the probability that a quantum jump occurs.
- **Ib:** Choose a random number r_2 between zero and one, used to select which collapse operator was responsible for the jump.
- **II:** Integrate the Schrödinger equation, using the effective Hamiltonian (3.4) until a time τ such that the norm of the wave function satisfies $\langle \psi(\tau) | \psi(\tau) \rangle = r_1$, at which point a jump occurs.
- **III:** The resultant jump projects the system at time τ into one of the renormalized states given by Eq. (3.6). The corresponding collapse operator C_n is chosen such that n is the smallest integer satisfying:

$$\sum_{i=1}^n P_n(\tau) \geq r_2 \quad (3.8)$$

where the individual P_n are given by Eq. (3.7). Note that the left hand side of Eq. (3.8) is, by definition, normalized to unity.

- **IV:** Using the renormalized state from step III as the new initial condition at time τ , draw a new random number, and repeat the above procedure until the final simulation time is reached.

Monte Carlo in QuTiP


In QuTiP, Monte Carlo evolution is implemented with the `qutip.mcsolve` function. It takes nearly the same arguments as the `qutip.mesolve` function for master-equation evolution, except that the initial state must be a ket vector, as oppose to a density matrix, and there is an optional keyword parameter `ntraj` that defines the number of stochastic trajectories to be simulated. By default, `ntraj=500` indicating that 500 Monte Carlo trajectories will be performed.

To illustrate the use of the Monte Carlo evolution of quantum systems in QuTiP, let's again consider the case of a two-level atom coupled to a leaky cavity. The only differences to the master-equation treatment is that in this case we invoke the `qutip.mcsolve` function instead of `qutip.mesolve`


```
from qutip.solver.mcsolve import MCSolver, mcsolve

times = np.linspace(0.0, 10.0, 200)
psi0 = tensor(fock(2, 0), fock(10, 8))
a = tensor(qeye(2), destroy(10))
sm = tensor(destroy(2), qeye(10))
H = 2*np.pi*a.dag()*a + 2*np.pi*sm.dag()*sm + 2*np.pi*0.25*(sm*a.dag() + sm.
↪dag()*a)
data = mcsolve(H, psi0, times, [np.sqrt(0.1) * a], e_ops=[a.dag() * a, sm.dag() *
↪sm])

plt.figure()
plt.plot(times, data.expect[0], times, data.expect[1])
plt.title('Monte Carlo time evolution')
plt.xlabel('Time')
plt.ylabel('Expectation values')
plt.legend(("cavity photon number", "atom excitation probability"))
plt.show()
```



Monte Carlo time evolution




The advantage of the Monte Carlo method over the master equation approach is that only the state vector is required to be kept in the computers memory, as opposed to the entire density matrix. For large quantum system this becomes a significant advantage, and the Monte Carlo solver is therefore generally recommended for such systems. For example, simulating a Heisenberg spin-chain consisting of 10 spins with random parameters and initial states takes almost 7 times longer using the master equation rather than Monte Carlo approach with the default number of trajectories running on a quad-CPU machine. Furthermore, it takes about 7 times the memory as well. However, for small systems, the added overhead of averaging a large number of stochastic trajectories to obtain the open system dynamics, as well as starting the multiprocessing functionality, outweighs the benefit of the minor (in this case) memory saving. Master equation methods are therefore generally more efficient when Hilbert space sizes are on the order of a couple of hundred states or smaller.

Monte Carlo Solver Result

The Monte Carlo solver returns a `qutip.MultitrajResult` object consisting of expectation values and/or states. The main difference with `qutip.mesolve's` `qutip.Result` is that it optionally stores the result of each trajectory together with their averages. When trajectories are stored, `result.runs_expect` is a list over the expectation operators, trajectories and times in that order. The averages are stored in `result.average_expect` and the standard derivation of the expectation values in `result.std_expect`. When the states are returned, `result.runs_states` will be an array of length `ntraj`. Each element contains an array of “Qobj” type ket with the same number of elements as `times`. `result.average_states` is a list of density matrices computed as the average of the states at each time step. Furthermore, the output will also contain a list of times at which the collapse occurred, and which collapse operators did the collapse. These can be obtained in `result.col_times` and `result.col_which` respectively. Lastly `result.photocurrent` contain the measurement of the evolution.

```
times = np.linspace(0.0, 10.0, 200)
psi0 = tensor(fock(2, 0), fock(10, 8))
a = tensor(qeye(2), destroy(10))
sm = tensor(destroy(2), qeye(10))
H = 2*np.pi*a.dag()*a + 2*np.pi*sm.dag()*sm + 2*np.pi*0.25*(sm*a.dag() + sm.
↳dag()*a)
data = mcsolve(H, psi0, times, [np.sqrt(0.1) * a], e_ops=[a.dag() * a, sm.dag() *
↳sm])

plt.figure()
plt.plot((times[:-1] + times[1:])/2, data.photocurrent[0])
plt.title('Monte Carlo Photocurrent')
plt.xlabel('Time')
plt.ylabel('Photon detections')
plt.show()
```



Changing the Number of Trajectories

By default, the `mcsolve` function runs 500 trajectories. This value was chosen because it gives good accuracy, Monte Carlo errors scale as $1/n$ where n is the number of trajectories, and simultaneously does not take an excessive amount of time to run. However, you can change the number of trajectories to fit your needs. In order to run 1000 trajectories in the above example, we can simply modify the call to `mcsolve` like:

```
data = mcsolve(H, psi0, times, [np.sqrt(0.1) * a], e_ops=[a.dag() * a, sm.dag() *
↪sm], ntraj=1000)
```

where we have added the keyword argument `ntraj=1000` at the end of the inputs. Now, the Monte Carlo solver will calculate expectation values for both operators, `a.dag() * a`, `sm.dag() * sm` averaging over 1000 trajectories.

Reusing Hamiltonian Data

Note: This section covers a specialized topic and may be skipped if you are new to QuTiP.

In order to solve a given simulation as fast as possible, the solvers in QuTiP take the given input operators and break them down into simpler components before passing them on to the ODE solvers. Although these operations are reasonably fast, the time spent organizing data can become appreciable when repeatedly solving a system over, for example, many different initial conditions. In cases such as this, the Monte Carlo Solver may be reused after the initial configuration, thus speeding up calculations.

Using the previous example, we will calculate the dynamics for two different initial states, with the Hamiltonian data being reused on the second call


```

times = np.linspace(0.0, 10.0, 200)
psi0 = tensor(fock(2, 0), fock(10, 5))
a = tensor(qeye(2), destroy(10))
sm = tensor(destroy(2), qeye(10))

H = 2*np.pi*a.dag()*a + 2*np.pi*sm.dag()*sm + 2*np.pi*0.25*(sm*a.dag() + sm.
    ↪dag()*a)
solver = MCSolver(H, c_ops=[np.sqrt(0.1) * a])
data1 = solver.run(psi0, times, e_ops=[a.dag()*a, sm.dag()*sm], ntraj=100)
psi1 = tensor(fock(2, 0), coherent(10, 2 - 1j))
data2 = solver.run(psi1, times, e_ops=[a.dag()*a, sm.dag()*sm], ntraj=100)

plt.figure()
plt.plot(times, data1.expect[0], "b", times, data1.expect[1], "r", lw=2)
plt.plot(times, data2.expect[0], 'b--', times, data2.expect[1], 'r--', lw=2)
plt.title('Monte Carlo time evolution')
plt.xlabel('Time', fontsize=14)
plt.ylabel('Expectation values', fontsize=14)
plt.legend(("cavity photon number", "atom excitation probability"))
plt.show()

```



The `MCSolver` also allows adding new trajectories after the first computation. This is shown in the next example where the results of two separated runs with identical conditions are merged into a single result object.

```

times = np.linspace(0.0, 10.0, 200)
psi0 = tensor(fock(2, 0), fock(10, 5))
a = tensor(qeye(2), destroy(10))
sm = tensor(destroy(2), qeye(10))


```

(continues on next page)

(continued from previous page)

```
H = 2*np.pi*a.dag()*a + 2*np.pi*sm.dag()*sm + 2*np.pi*0.25*(sm*a.dag() + sm.
↪dag()*a)
solver = MCSolver(H, c_ops=[np.sqrt(0.1) * a])
data1 = solver.run(psi0, times, e_ops=[a.dag() * a, sm.dag() * sm], ntraj=1, ↪
↪seed=1)
data2 = solver.run(psi0, times, e_ops=[a.dag() * a, sm.dag() * sm], ntraj=1, ↪
↪seed=3)
data_merged = data1 + data2

plt.figure()
plt.plot(times, data1.expect[0], times, data1.expect[1], lw=2)
plt.plot(times, data2.expect[0], '--', times, data2.expect[1], '--', lw=2)
plt.plot(times, data_merged.expect[0], ':', times, data_merged.expect[1], ':', ↪
↪lw=2)
plt.title('Monte Carlo time evolution')
plt.xlabel('Time', fontsize=14)
plt.ylabel('Expectation values', fontsize=14)
plt.legend(("cavity photon number", "atom excitation probability"))
plt.show()
```



This can be used to explore the convergence of the Monte Carlo solver. For example, the following code block plots expectation values for 1, 10 and 100 trajectories:

```
solver = MCSolver(H, c_ops=[np.sqrt(0.1) * a])

data1 = solver.run(psi0, times, e_ops=[a.dag() * a, sm.dag() * sm], ntraj=1)
data10 = data1 + solver.run(psi0, times, e_ops=[a.dag() * a, sm.dag() * sm], ↪
↪ntraj=9)
```


(continues on next page)

(continued from previous page)

```
data100 = data10 + solver.run(psi0, times, e_ops=[a.dag() * a, sm.dag() * sm],
    ↪ ntraj=90)

expt1 = data1.expect
expt10 = data10.expect
expt100 = data100.expect

plt.figure()
plt.plot(times, expt1[0], label="ntraj=1")
plt.plot(times, expt10[0], label="ntraj=10")
plt.plot(times, expt100[0], label="ntraj=100")
plt.title('Monte Carlo time evolution')
plt.xlabel('Time')
plt.ylabel('Expectation values')
plt.legend()
plt.show()
```



3.5.5 Krylov Solver

Introduction

The Krylov-subspace method is a standard method to approximate quantum dynamics. Let $|\psi\rangle$ be a state in a D -dimensional complex Hilbert space that evolves under a time-independent Hamiltonian H . Then, the N -dimensional Krylov subspace associated with that state and Hamiltonian is given by

$$\mathcal{K}_N = \text{span} \{ |\psi\rangle, H|\psi\rangle, \dots, H^{N-1}|\psi\rangle \}, \quad (3.9)$$

where the dimension $N < D$ is a parameter of choice. To construct an orthonormal basis B_N for \mathcal{K}_N , the simplest algorithm is the well-known Lanczos algorithm, which provides a sort of Gram-Schmidt procedure that harnesses the fact that orthonormalization needs to be imposed only for the last two vectors in the basis. Written in this basis the time-evolved state can be approximated as

$$|\psi(t)\rangle = e^{-iHt}|\psi\rangle \approx \mathbb{P}_N e^{-iHt} \mathbb{P}_N |\psi\rangle = \mathbb{V}_N^\dagger e^{-iT_N t} \mathbb{V}_N |\psi\rangle \equiv |\psi_N(t)\rangle, \quad (3.10)$$

where $T_N = \mathbb{V}_N H \mathbb{V}_N^\dagger$ is the Hamiltonian reduced to the Krylov subspace (which takes a tridiagonal matrix form), and \mathbb{V}_N^\dagger is the matrix containing the vectors of the Krylov basis as columns.

With the above approximation, the time-evolution is calculated only with a smaller square matrix of the desired size. Therefore, the Krylov method provides huge speed-ups in computation of short-time evolutions when the dimension of the Hamiltonian is very large, a point at which exact calculations on the complete subspace are practically impossible.

One of the biggest problems with this type of method is the control of the error. After a short time, the error starts to grow exponentially. However, this can be easily corrected by restarting the subspace when the error reaches a certain threshold. Therefore, a series of M Krylov-subspace time evolutions provides accurate solutions for the complete time evolution. Within this scheme, the magic of Krylov resides not only in its ability to capture complex time evolutions from very large Hilbert spaces with very small dimensions M , but also in the computing speed-up it presents.


For exceptional cases, the Lanczos algorithm might arrive at the exact evolution of the initial state at a dimension $M_{hb} < M$. This is called a happy breakdown. For example, if a Hamiltonian has a symmetry subspace $D_{\text{sim}} < M$, then the algorithm will optimize using the value $M_{\text{hb}} < M$, at which the evolution is not only exact but also cheap.

Krylov Solver in QuTiP

In QuTiP, Krylov-subspace evolution is implemented as the function `qutip.krylovsolve`. Arguments are nearly the same as `qutip.sesolve` function for master-equation evolution, except that the initial state must be a ket vector, as opposed to a density matrix, and the additional parameter `krylov_dim` that defines the maximum allowed Krylov-subspace dimension.

Let's solve a simple example using the algorithm in QuTiP to get familiar with the method.

```
>>> from qutip import jmat, rand_ket
>>> from qutip.solver.krylovsolve import krylovsolve
>>> import numpy as np
>>> import matplotlib.pyplot as plt
>>> dim = 100
>>> e_ops = [jmat((dim - 1) / 2.0, "x"), jmat((dim - 1) / 2.0, "y"), jmat((dim - 1) / 2.0, "z")]
>>> H = .5*jmat((dim - 1) / 2.0, "z") + .5*jmat((dim - 1) / 2.0, "x")
>>> psi0 = rand_ket(dim, seed=1)
>>> tlist = np.linspace(0.0, 10.0, 200)
>>> results = krylovsolve(H, psi0, tlist, krylov_dim=20, e_ops=e_ops)
>>> plt.figure()
>>> for expect in results.expect:
>>>     plt.plot(tlist, expect)
>>> plt.legend(['jmat x', 'jmat y', 'jmat z'])
>>> plt.xlabel('Time')
>>> plt.ylabel('Expectation values')
>>> plt.show()
```

3.5.6 Stochastic Solver - Photocurrent

Photocurrent method, like monte-carlo method, allows for simulating an individual realization of the system evolution under continuous measurement.

Closed system

Photocurrent evolution have the state evolve deterministically between quantum jumps. During the deterministic part, the system evolve by schrodinger equation with a non-hermitian, norm conserving effective Hamiltonian.

$$H_{\text{eff}} = H_{\text{sys}} + \frac{i\hbar}{2} \left(- \sum_n C_n^\dagger C_n + |C_n \psi|^2 \right). \quad (3.11)$$

With C_n , the collapse operators. This effective Hamiltonian is equivalent to the monte-carlo effective Hamiltonian with an extra term to keep the state normalized. At each time step of δt , the wave function has a probability

$$\delta p_n = \langle \psi(t) | C_n^\dagger C_n | \psi(t) \rangle \delta t \quad (3.12)$$

of making a quantum jump. δt must be chosen small enough to keep that probability small $\delta p \ll 1$. *If multiple jumps happen at the same time step, the state become unphysical.* Each jump result in a sharp variation of the state by,

$$\delta \psi = \left(\frac{C_n \psi}{|C_n \psi|} - \psi \right) \quad (3.13)$$

The basic photocurrent method directly integrates these equations to the first-order. Starting from a state $|\psi(0)\rangle$, it evolves the state according to

$$\delta \psi(t) = -iH_{\text{sys}}\psi(t)\delta t + \sum_n \left(-\frac{C_n^\dagger C_n}{2} \psi(t)\delta t + \frac{|C_n \psi|^2}{2} \delta t + \delta N_n \left(\frac{C_n \psi}{|C_n \psi|} - \psi \right) \right), \quad (3.14)$$

for each time-step. Here $\delta N = 1$ with a probability of $\delta\omega$ and $\delta N_n = 0$ with a probability of $1 - \delta\omega$.

Trajectories obtained with this algorithm are equivalent to those obtained with monte-carlo evolution (up to $O(\delta t^2)$). In most cases, `qutip.mcsolve` is more efficient than `qutip.stochastic.photocurrent_solve`.

Open system

Photocurrent approach allows to obtain trajectories for a system with both measured and dissipative interaction with the bath. The system evolves according to the master equation between jumps with a modified liouvillian

$$L_{\text{eff}}(\rho(t)) = L_{\text{sys}}(\rho(t)) + \sum_n \left(\text{tr}(C_n^\dagger C_n \rho C_n^\dagger C_n) - C_n^\dagger C_n \rho C_n^\dagger C_n \right), \quad (3.15)$$

with the probability of jumps in a time step δt given by

$$\delta p = \text{tr}(C \rho C^\dagger) \delta t. \quad (3.16)$$

After a jump, the density matrix become

$$\rho' = \frac{C \rho C^\dagger}{\text{tr}(C \rho C^\dagger)}.$$

The evolution of the system at each time step is thus given by

$$\rho(t + \delta t) = \rho(t) + L_{\text{eff}}(\rho) \delta t + \delta N \left(\frac{C \rho C^\dagger}{\text{tr}(C \rho C^\dagger)} - \rho \right). \quad (3.17)$$

3.5.7 Stochastic Solver

When a quantum system is subjected to continuous measurement, through homodyne detection for example, it is possible to simulate the conditional quantum state using stochastic Schrodinger and master equations. The solution of these stochastic equations are quantum trajectories, which represent the conditioned evolution of the system given a specific measurement record.

In general, the stochastic evolution of a quantum state is calculated in QuTiP by solving the general equation

$$d\rho(t) = d_1 \rho dt + \sum_n d_{2,n} \rho dW_n, \quad (3.18)$$

where dW_n is a Wiener increment, which has the expectation values $E[dW] = 0$ and $E[dW^2] = dt$. Stochastic evolution is implemented with the `qutip.stochastic.general_stochastic` function.

Stochastic Schrodinger Equation

The stochastic Schrodinger equation is given by (see section 4.4, [Wis09])

$$d\psi(t) = -iH\psi(t)dt - \sum_n \left(\frac{S_n^\dagger S_n}{2} - \frac{e_n}{2} S_n + \frac{e_n^2}{8} \right) \psi(t)dt + \sum_n \left(S_n - \frac{e_n}{2} \right) \psi(t)dW_n, \quad (3.19)$$

where H is the Hamiltonian, S_n are the stochastic collapse operators, and e_n is

$$e_n = \langle \psi(t) | S_n + S_n^\dagger | \psi(t) \rangle \quad (3.20)$$

In QuTiP, this equation can be solved using the function `qutip.stochastic.ssesolve`, which is implemented by defining d_1 and $d_{2,n}$ from Equation (3.18) as

$$d_1 = -iH - \frac{1}{2} \sum_n \left(S_n^\dagger S_n - e_n S_n + \frac{e_n^2}{4} \right), \quad (3.21)$$

and

$$d_{2,n} = S_n - \frac{e_n}{2}. \quad (3.22)$$

The solver `qutip.stochastic.ssesolve` will construct the operators d_1 and $d_{2,n}$ once the user passes the Hamiltonian (H) and the stochastic operator list (`sc_ops`). As with the `qutip.mcsolve`, the number of trajectories and the seed for the noise realisation can be fixed using the arguments: `ntraj` and `noise`, respectively. If the user also requires the measurement output, the argument `store_measurement=True` should be included.

Additionally, homodyne and heterodyne detections can be easily simulated by passing the arguments `method='homodyne'` or `method='heterodyne'` to `qutip.stochastic.ssesolve`.

Examples of how to solve the stochastic Schrodinger equation using QuTiP can be found in this [development notebook](#).

Stochastic Master Equation

When the initial state of the system is a density matrix ρ , the stochastic master equation solver `qutip.stochastic.smesolve` must be used. The stochastic master equation is given by (see section 4.4, [Wis09])

$$d\rho(t) = -i[H, \rho(t)]dt + D[A]\rho(t)dt + \mathcal{H}[A]\rho dW(t) \quad (3.23)$$

where

$$D[A]\rho = \frac{1}{2} [2A\rho A^\dagger - \rho A^\dagger A - A^\dagger A\rho], \quad (3.24)$$

and

$$\mathcal{H}[A]\rho = A\rho(t) + \rho(t)A^\dagger - \text{tr}[A\rho(t) + \rho(t)A^\dagger]. \quad (3.25)$$

In QuTiP, solutions for the stochastic master equation are obtained using the solver `qutip.stochastic.smesolve`. The implementation takes into account 2 types of collapse operators. C_i (`c_ops`) represent the dissipation in the environment, while S_n (`sc_ops`) are monitored operators. The deterministic part of the evolution, described by the d_1 in Equation (3.18), takes into account all operators C_i and S_n :

$$d_1 = -i[H(t), \rho(t)] + \sum_i D[C_i]\rho + \sum_n D[S_n]\rho, \quad (3.26)$$

The stochastic part, $d_{2,n}$, is given solely by the operators S_n

$$d_{2,n} = S_n\rho(t) + \rho(t)S_n^\dagger - \text{tr}(S_n\rho(t) + \rho(t)S_n^\dagger)\rho(t). \quad (3.27)$$

As in the stochastic Schrodinger equation, the detection method can be specified using the `method` argument.

Example

Below, we solve the dynamics for an optical cavity at 0K whose output is monitored using homodyne detection. The cavity decay rate is given by κ and the Δ is the cavity detuning with respect to the driving field. The measurement operators can be passed using the option `m_ops`. The homodyne current J_x is calculated using

$$J_x = \langle x \rangle + dW, \quad (3.28)$$

where x is the operator passed using `m_ops`. The results are available in `result.measurements`.

```
import numpy as np
import matplotlib.pyplot as plt
import qutip as qt
```

```
# parameters
```

(continues on next page)

(continued from previous page)


```
DIM = 20                # Hilbert space dimension
DELTA = 5*2*np.pi      # cavity detuning
KAPPA = 2               # cavity decay rate
INTENSITY = 4           # intensity of initial state
NUMBER_OF_TRAJECTORIES = 500

# operators
a = qt.destroy(DIM)
x = a + a.dag()
H = DELTA*a.dag()*a

rho_0 = qt.coherent(DIM, np.sqrt(INTENSITY))
times = np.arange(0, 1, 0.0025)

stoc_solution = qt.smesolve(H, rho_0, times,
                             c_ops=[],
                             sc_ops=[np.sqrt(KAPPA) * a],
                             e_ops=[x],
                             ntraj=NUMBER_OF_TRAJECTORIES,
                             nsubsteps=2,
                             store_measurement=True,
                             dW_factors=[1],
                             method='homodyne')

fig, ax = plt.subplots()
ax.set_title('Stochastic Master Equation - Homodyne Detection')
ax.plot(times, np.array(stoc_solution.measurement).mean(axis=0)[:].real,
        'r', lw=2, label=r'$J_x$')
ax.plot(times, stoc_solution.expect[0], 'k', lw=2,
        label=r'$\langle x \rangle$')
ax.set_xlabel('Time')
ax.legend()
```



For other examples on `qutip.stochastic.smesolve`, see the [following notebook](#), as well as these notebooks available at [QuTiP Tutorials page](#): [heterodyne detection](#), [inefficient detection](#), and [feedback control](#).

3.5.8 Solving Problems with Time-dependent Hamiltonians

Time-Dependent Operators

In the previous examples of quantum evolution, we assumed that the systems under consideration were described by time-independent Hamiltonians. However, many systems have explicit time dependence in either the Hamiltonian, or the collapse operators describing coupling to the environment, and sometimes both components might depend on time. The time-evolutions solvers such as `sesolve`, `brmesolve`, etc. are all capable of handling time-dependent Hamiltonians and collapse terms. QuTiP use `QobjEvo` to represent time-dependent quantum operators. There are three different ways to build a `QobjEvo`:

1. **Function based:** Build the time dependent operator from a function returning a `Qobj`:

```
def oper(t):
    return num(N) + (destroy(N) + create(N)) * np.sin(t)
H_t = QobjEvo(oper)
```

1. **List based:** The time dependent quantum operator is represented as a list of `qobj` and `[qobj, coefficient]` pairs.

```
H_t = QobjEvo([num(N), [create(N), lambda t: np.sin(t)], [destroy(N), lambda t: np.
    ↪ sin(t)]]])
```

3. **coefficient based:** The product of a `Qobj` with a `Coefficient` result in a `QobjEvo`:

```
coeff = coefficient(lambda t: np.sin(t))
H_t = num(N) + (destroy(N) + create(N)) * coeff
```

These 3 examples will create the same time dependent operator, however the function based method will usually be slower when used in solver.

Solvers will accept a `QobjEvo`: when an operator is expected: this include the Hamiltonian H , collapse operators, expectation values operators, the operator of `brmesolve`'s `a_ops`, etc. Exception are `krylovsolve`'s Hamiltonian and HEOM's Bath operators.

Most solvers will accept any format that could be made into a `QobjEvo`: for the Hamiltonian. All of the following are equivalent:

```
result = mesolve(H_t, ...)
result = mesolve([num(N), [destroy(N) + create(N), lambda t: np.sin(t)]], ...)
result = mesolve(oper, ...)
```

Collapse operator also accept a list of object that could be made into `QobjEvo`:. However one needs to be careful about not confusing the list nature of the `c_ops` parameter with list format quantum system. In the following call:

```
result = mesolve(H_t, ..., c_ops=[num(N), [destroy(N) + create(N), lambda t: np.
    ↪ sin(t)]])
```

`mesolve` will see 2 collapses operators: `num(N)` and `[destroy(N) + create(N), lambda t: np.sin(t)]`. It is therefore preferred to pass each collapse operator as either a `Qobj`: or a `QobjEvo`:.

As an example, we will look at a case with a time-dependent Hamiltonian of the form $H = H_0 + f(t)H_1$ where $f(t)$ is the time-dependent driving strength given as $f(t) = A \exp[-(t/\sigma)^2]$. The following code sets up the problem

```
ustate = basis(3, 0)
excited = basis(3, 1)
ground = basis(3, 2)

N = 2 # Set where to truncate Fock state for cavity
sigma_ge = tensor(qeye(N), ground * excited.dag()) # |g><e|
sigma_ue = tensor(qeye(N), ustate * excited.dag()) # |u><e|
a = tensor(destroy(N), qeye(3))
ada = tensor(num(N), qeye(3))

c_ops = [] # Build collapse operators
kappa = 1.5 # Cavity decay rate
c_ops.append(np.sqrt(kappa) * a)
gamma = 6 # Atomic decay rate
c_ops.append(np.sqrt(5*gamma/9) * sigma_ue) # Use Rb branching ratio of 5/9 e->u
c_ops.append(np.sqrt(4*gamma/9) * sigma_ge) # 4/9 e->g

t = np.linspace(-15, 15, 100) # Define time vector
psi0 = tensor(basis(N, 0), ustate) # Define initial state

state_GG = tensor(basis(N, 1), ground) # Define states onto which to project
sigma_GG = state_GG * state_GG.dag()
state_UU = tensor(basis(N, 0), ustate)
sigma_UU = state_UU * state_UU.dag()

g = 5 # coupling strength
H0 = -g * (sigma_ge.dag() * a + a.dag() * sigma_ge) # time-independent term
H1 = (sigma_ue.dag() + sigma_ue) # time-dependent term
```

Given that we have a single time-dependent Hamiltonian term, and constant collapse terms, we need to specify a single Python function for the coefficient $f(t)$. In this case, one can simply do

```
def H1_coeff(t):
    return 9 * np.exp(-(t / 5.) ** 2)
```

In this case, the return value depends only on time. However it is possible to add optional arguments to the call, see [Using arguments](#). Having specified our coefficient function, we can now specify the Hamiltonian in list format and call the solver (in this case `qutip.mesolve`)

```
H = [H0, [H1, H1_coeff]]
output = mesolve(H, psi0, t, c_ops, [ada, sigma_UU, sigma_GG])
```

We can call the Monte Carlo solver in the exact same way (if using the default `ntraj=500`):

```
output = mcsolve(H, psi0, t, c_ops, [ada, sigma_UU, sigma_GG])
```

The output from the master equation solver is identical to that shown in the examples, the Monte Carlo however will be noticeably off, suggesting we should increase the number of trajectories for this example. In addition, we can also consider the decay of a simple Harmonic oscillator with time-varying decay rate

```
kappa = 0.5

def col_coeff(t, args): # coefficient function
    return np.sqrt(kappa * np.exp(-t))

N = 10 # number of basis states
a = destroy(N)
H = a.dag() * a # simple HO
psi0 = basis(N, 9) # initial state
c_ops = [QobjEvo([a, col_coeff])] # time-dependent collapse term
times = np.linspace(0, 10, 100)
output = mesolve(H, psi0, times, c_ops, [a.dag() * a])
```

Qobjevo

`QobjEvo` as a time dependent quantum system, as it's main functionality create a `Qobj` at a time:

```
>>> print(H_t(np.pi / 2))
Quantum object: dims=[[2], [2]], shape=(2, 2), type='oper', isherm=True
Qobj data =
[[0. 1.]
 [1. 1.]]
```

`QobjEvo` shares a lot of properties with the `Qobj`.

Property	Attribute	Description
Dimensions	<code>Q.dims</code>	List keeping track of shapes for individual components of a multipartite system (for tensor products and partial traces).
Shape	<code>Q.shape</code>	Dimensions of underlying data matrix.
Type	<code>Q.type</code>	Is object of type 'ket', 'bra', 'oper', or 'super'?
is constant?	<code>Q.isconstant</code>	Is the operator Hermitian or not?

`QobjEvo`'s follow the same mathematical operations rules than `Qobj`. They can be added, subtracted and multiplied with scalar, `Qobj` and `QobjEvo`. They also support the *dag* and *trans* and *conj* method and can be used for tensor operations and super operator transformation:

```
H = tensor(H_t, qeye(2))
c_op = tensor(QobjEvo([destroy(N), lambda t: np.exp(-t)]), sigmax())
```

(continues on next page)

(continued from previous page)

```
L = -1j * (spre(H) - spost(H.dag()))
L += spre(c_op) * spost(c_op.dag()) - 0.5 * spre(c_op.dag() * c_op) - 0.5 *
↪spost(c_op.dag() * c_op)
```

Or equivalently:

```
L = liouvillian(H, [c_op])
```

Using arguments

Until now, the coefficient were only functions of time. In the definition of `H1_coeff`, the driving amplitude `A` and width `sigma` were hardcoded with their numerical values. This is fine for problems that are specialized, or that we only want to run once. However, in many cases, we would like study the same problem with a range of parameters and not have to worry about manually changing the values on each run. QuTiP allows you to accomplish this using by adding extra arguments to coefficients function that make the `QobjEvo`. For instance, instead of explicitly writing 9 for the amplitude and 5 for the width of the gaussian driving term, we can add an *args* positional variable:

```
def H1_coeff(t, args):
    return args['A'] * np.exp(-(t/args['sigma'])**2)
```

or, new from v5, add the extra parameter directly:

```
def H1_coeff(t, A, sigma):
    return A * np.exp(-(t / sigma)**2)
```

When the second positional input of the coefficient function is named *args*, the arguments are passed as a Python dictionary of key: value pairs. Otherwise the coefficient function is called as `coeff(t, **args)`. In the last example, `args = {'A': a, 'sigma': b}` where *a* and *b* are the two parameters for the amplitude and width, respectively. This *args* dictionary need to be given at creation of the `QobjEvo` when function using then are included:

```
system = [H0, [H1, H1_coeff]]
args={'A': 9, 'sigma': 5}
qevo = QobjEvo(system, args=args)
```

But without *args*, the `QobjEvo` creation will fail:

```
try:
    QobjEvo(system)
except TypeError as err:
    print(err)
```

When evaluation the `QobjEvo` at a time, new arguments can be passed either with the *args* dictionary positional arguments, or with specific keywords arguments:

```
print(qevo(1))
print(qevo(1, {"A": 5, "sigma": 0.2}))
print(qevo(1, A=5))
```

Whether the original coefficient used the *args* or specific input does not matter. It is fine to mix the different signatures.

Solver calls take an *args* input that is used to build the time dependent system. If the Hamiltonian or collapse operators are already `QobjEvo`, their arguments will be overwritten.


```
def system(t, A, sigma):
    return H0 + H1 * (A * np.exp(-(t / sigma)**2))

mesolve(system, ..., args=args)
```

To update arguments of an existing time dependent quantum system, you can pass the previous object as the input of a `QobjEvo` with new args:

```
print(qevo(1))
print(qevo(1, {"A": 5, "sigma": 0.2}))
new_qevo = QobjEvo(qevo, args={"A": 5, "sigma": 0.2})
print(new_qevo(1))
```

`QobjEvo` created from a monolithic function can also use arguments:

```
def oper(t, w):
    return num(N) + (destroy(N) + create(N)) * np.sin(t*w)

H_t = QobjEvo(oper, args={"w": np.pi})
```

When merging two or more `QobjEvo`, each will keep its arguments, but calling it with updated args will affect all parts:

```
qevo1 = QobjEvo([sigmap(), lambda t, a: a], [sigmam(), lambda t, a, b: a+1j*b]),
args={"a": 1, "b": 2})
qevo2 = QobjEvo([num(2), lambda t, a, c: a+1j*c], args={"a": 2, "c": 2})
summed_evo = qevo1 + qevo2
print(summed_evo(0))
print(summed_evo(0, a=3, b=1))
```

Coefficients

To build time dependent quantum system we often use a list of `Qobj` and *coefficient*. These *coefficients* represent the strength of the corresponding quantum object as a function of time. Up to now, we used functions for these, but QuTiP supports multiple formats: callable, strings, array.

Function coefficients : Use a callable with the signature `f(t: double, ...) -> double` as coefficient. Any function or method that can be called by `f(t, args)`, `f(t, **args)` is accepted.

```
def coeff(t, A, sigma):
    return A * np.exp(-(t / sigma)**2)

H = QobjEvo([H0, [H1, coeff]], args=args)
```

String coefficients : Use a string containing a simple Python expression. The variable `t`, common mathematical functions such as `sin` or `exp` and a variable in `args` will be available. If available, the string will be compiled using cython, fixing variable type when possible, allowing slightly faster execution than function. While the speed up is usually very small, in long evolution, numerous calls to the functions are made and it can accumulate. From version 5, compilation of the coefficient is done only once and saved between sessions. When Cython is not available, the code will be executed in python with the same environment. This, however, has no advantage over using python function.

```
coeff = "A * exp(-(t / sigma)**2)"

H = QobjEvo([H0, [H1, coeff]], args=args)
```

Here is a list of defined variables: `sin, cos, tan, asin, acos, atan, pi, sinh, cosh, tanh, asinh, acosh, atanh, exp, log, log10, erf, zeta, sqrt, real, imag, conj, abs, norm, arg, proj, np (numpy) and spe (scipy.special)`.

Array coefficients : Use the spline interpolation of an array. Useful when the coefficient is hard to define as a function or obtained from experimental data. The times at which the array are defined must be passed as `tlist`:

```
times = np.linspace(-sigma*5, sigma*5, 500)
coeff = A * exp(-(times / sigma)**2)

H = QobjEvo([H0, [H1, coeff]], tlist=times)
```

Per default, a cubic spline interpolation is used, but the order of the interpolation can be controlled with the `order` input: Outside the interpolation range, the first or last value are used.


```
times = np.array([0, 0.1, 0.3, 0.6, 1.0])
coeff = times * (1.1 - times)
tlist = np.linspace(-0.1, 1.1, 25)

H = QobjEvo([qeye(1), coeff], tlist=times)
plt.plot(tlist, [H(t).norm() for t in tlist], label="CubicSpline")

H = QobjEvo([qeye(1), coeff], tlist=times, order=0)
plt.plot(tlist, [H(t).norm() for t in tlist], label="step")

H = QobjEvo([qeye(1), coeff], tlist=times, order=1)
plt.plot(tlist, [H(t).norm() for t in tlist], label="linear")

plt.legend()
```




When using array coefficients in solver, if the time dependent quantum system is in list format, the solver `tlist` is used as times of the array. This is often not ideal as the interpolation is usually less precise close the extremities of the range. It is therefore better to create the `QobjEvo` using an extended range prior to the solver:

```

N = 5
times = np.linspace(-0.1, 1.1, 13)
coeff = np.exp(-times)

c_ops = [QobjEvo([destroy(N), coeff], tlist=times)]
plt.plot(
    mesolve(qeye(N), basis(N, N-1), np.linspace(0, 1, 11), c_ops=c_ops, e_
    ↪ops=[num(N)]).expect
)

```



Different coefficient types can be mixed in a `QobjEvo`.

Given the multiple choices of input style, the first question that arises is which option to choose? In short, the function based method (first option) is the most general, allowing for essentially arbitrary coefficients expressed via user defined functions. However, by automatically compiling your system into C++ code, the second option (string based) tends to be more efficient and run faster. Of course, for small system sizes and evolution times, the difference will be minor. Lastly the spline method is usually as fast the string method, but it cannot be modified once created.

Accessing the state from solver

In QuTiP 4.4 to 4.7, it was possible to request that the solver pass the state, expectation values or collapse operators via arguments to `QobjEvo`. Support for this is not yet available in QuTiP 5.

3.5.9 Bloch-Redfield master equation

Introduction

The Lindblad master equation introduced earlier is constructed so that it describes a physical evolution of the density matrix (i.e., trace and positivity preserving), but it does not provide a connection to any underlying microscopic physical model. The Lindblad operators (collapse operators) describe phenomenological processes, such as for example dephasing and spin flips, and the rates of these processes are arbitrary parameters in the model. In many situations the collapse operators and their corresponding rates have clear physical interpretation, such as dephasing and relaxation rates, and in those cases the Lindblad master equation is usually the method of choice.

However, in some cases, for example systems with varying energy biases and eigenstates and that couple to an environment in some well-defined manner (through a physically motivated system-environment interaction operator), it is often desirable to derive the master equation from more fundamental physical principles, and relate it to for example the noise-power spectrum of the environment.

The Bloch-Redfield formalism is one such approach to derive a master equation from a microscopic system. It starts from a combined system-environment perspective, and derives a perturbative master equation for the system alone, under the assumption of weak system-environment coupling. One advantage of this approach is that the dissipation processes and rates are obtained directly from the properties of the environment. On the downside, it does not intrinsically guarantee that the resulting master equation unconditionally preserves the physical properties of the density matrix (because it is a perturbative method). The Bloch-Redfield master equation must therefore be used with care, and the assumptions made in the derivation must be honored. (The Lindblad master equation is in a sense more robust – it always results in a physical density matrix – although some collapse operators might not be physically justified). For a full derivation of the Bloch Redfield master equation, see e.g. [Coh92] or [Bre02]. Here we present only a brief version of the derivation, with the intention of introducing the notation and how it relates to the implementation in QuTiP.

Brief Derivation and Definitions

The starting point of the Bloch-Redfield formalism is the total Hamiltonian for the system and the environment (bath): $H = H_S + H_B + H_I$, where H is the total system+bath Hamiltonian, H_S and H_B are the system and bath Hamiltonians, respectively, and H_I is the interaction Hamiltonian.

The most general form of a master equation for the system dynamics is obtained by tracing out the bath from the von-Neumann equation of motion for the combined system ($\dot{\rho} = -i\hbar^{-1}[H, \rho]$). In the interaction picture the result is

$$\frac{d}{dt}\rho_S(t) = -\hbar^{-2} \int_0^t d\tau \text{Tr}_B[H_I(t), [H_I(\tau), \rho_S(\tau) \otimes \rho_B]], \quad (3.29)$$

where the additional assumption that the total system-bath density matrix can be factorized as $\rho(t) \approx \rho_S(t) \otimes \rho_B$. This assumption is known as the Born approximation, and it implies that there never is any entanglement between the system and the bath, neither in the initial state nor at any time during the evolution. *It is justified for weak system-bath interaction.*

The master equation (3.29) is non-Markovian, i.e., the change in the density matrix at a time t depends on states at all times $\tau < t$, making it intractable to solve both theoretically and numerically. To make progress towards a manageable master equation, we now introduce the Markovian approximation, in which $\rho_S(\tau)$ is replaced by $\rho_S(t)$ in Eq. (3.29). The result is the Redfield equation

$$\frac{d}{dt}\rho_S(t) = -\hbar^{-2} \int_0^t d\tau \text{Tr}_B[H_I(t), [H_I(\tau), \rho_S(t) \otimes \rho_B]], \quad (3.30)$$

which is local in time with respect the density matrix, but still not Markovian since it contains an implicit dependence on the initial state. By extending the integration to infinity and substituting $\tau \rightarrow t - \tau$, a fully Markovian master equation is obtained:

$$\frac{d}{dt}\rho_S(t) = -\hbar^{-2} \int_0^\infty d\tau \text{Tr}_B[H_I(t), [H_I(t-\tau), \rho_S(t) \otimes \rho_B]]. \quad (3.31)$$

The two Markovian approximations introduced above are valid if the time-scale with which the system dynamics changes is large compared to the time-scale with which correlations in the bath decays (corresponding to a “short-memory” bath, which results in Markovian system dynamics).

The master equation (3.31) is still on a too general form to be suitable for numerical implementation. We therefore assume that the system-bath interaction takes the form $H_I = \sum_\alpha A_\alpha \otimes B_\alpha$ and where A_α are system operators and B_α are bath operators. This allows us to write master equation in terms of system operators and bath correlation functions:

$$\begin{aligned} \frac{d}{dt}\rho_S(t) = -\hbar^{-2} \sum_{\alpha\beta} \int_0^\infty d\tau \{ & g_{\alpha\beta}(\tau) [A_\alpha(t)A_\beta(t-\tau)\rho_S(t) - A_\alpha(t-\tau)\rho_S(t)A_\beta(t)] \\ & g_{\alpha\beta}(-\tau) [\rho_S(t)A_\alpha(t-\tau)A_\beta(t) - A_\alpha(t)\rho_S(t)A_\beta(t-\tau)] \}, \end{aligned}$$

where $g_{\alpha\beta}(\tau) = \text{Tr}_B [B_\alpha(t)B_\beta(t-\tau)\rho_B] = \langle B_\alpha(\tau)B_\beta(0) \rangle$, since the bath state ρ_B is a steady state.

In the eigenbasis of the system Hamiltonian, where $A_{mn}(t) = A_{mn}e^{i\omega_{mn}t}$, $\omega_{mn} = \omega_m - \omega_n$ and ω_m are the eigenfrequencies corresponding the eigenstate $|m\rangle$, we obtain in matrix form in the Schrödinger picture

$$\begin{aligned} \frac{d}{dt}\rho_{ab}(t) = -i\omega_{ab}\rho_{ab}(t) - \hbar^{-2} \sum_{\alpha,\beta} \sum_{c,d}^{\text{sec}} \int_0^\infty d\tau \left\{ g_{\alpha\beta}(\tau) \left[\delta_{bd} \sum_n A_{an}^\alpha A_{nc}^\beta e^{i\omega_{cn}\tau} - A_{ac}^\alpha A_{db}^\beta e^{i\omega_{ca}\tau} \right] \right. \\ \left. + g_{\alpha\beta}(-\tau) \left[\delta_{ac} \sum_n A_{dn}^\alpha A_{nb}^\beta e^{i\omega_{nd}\tau} - A_{ac}^\alpha A_{db}^\beta e^{i\omega_{bd}\tau} \right] \right\} \rho_{cd}(t), \end{aligned}$$

where the “sec” above the summation symbol indicate summation of the secular terms which satisfy $|\omega_{ab} - \omega_{cd}| \ll \tau_{\text{decay}}$. This is an almost-useful form of the master equation. The final step before arriving at the form of the Bloch-Redfield master equation that is implemented in QuTiP, involves rewriting the bath correlation function $g(\tau)$ in terms of the noise-power spectrum of the environment $S(\omega) = \int_{-\infty}^\infty d\tau e^{i\omega\tau} g(\tau)$:

$$\int_0^\infty d\tau g_{\alpha\beta}(\tau) e^{i\omega\tau} = \frac{1}{2} S_{\alpha\beta}(\omega) + i\lambda_{\alpha\beta}(\omega), \quad (3.32)$$

where $\lambda_{ab}(\omega)$ is an energy shift that is neglected here. The final form of the Bloch-Redfield master equation is

$$\frac{d}{dt}\rho_{ab}(t) = -i\omega_{ab}\rho_{ab}(t) + \sum_{c,d}^{\text{sec}} R_{abcd}\rho_{cd}(t), \quad (3.33)$$

where

$$\begin{aligned} R_{abcd} = -\frac{\hbar^{-2}}{2} \sum_{\alpha,\beta} \left\{ \delta_{bd} \sum_n A_{an}^\alpha A_{nc}^\beta S_{\alpha\beta}(\omega_{cn}) - A_{ac}^\alpha A_{db}^\beta S_{\alpha\beta}(\omega_{ca}) \right. \\ \left. + \delta_{ac} \sum_n A_{dn}^\alpha A_{nb}^\beta S_{\alpha\beta}(\omega_{dn}) - A_{ac}^\alpha A_{db}^\beta S_{\alpha\beta}(\omega_{db}) \right\}, \end{aligned}$$

is the Bloch-Redfield tensor.

The Bloch-Redfield master equation in the form Eq. (3.33) is suitable for numerical implementation. The input parameters are the system Hamiltonian H , the system operators through which the environment couples to the system A_α , and the noise-power spectrum $S_{\alpha\beta}(\omega)$ associated with each system-environment interaction term.

To simplify the numerical implementation we assume that A_α are Hermitian and that cross-correlations between different environment operators vanish, so that the final expression for the Bloch-Redfield tensor that is imple-

mented in QuTiP is

$$R_{abcd} = -\frac{\hbar^{-2}}{2} \sum_{\alpha} \left\{ \delta_{bd} \sum_n A_{an}^{\alpha} A_{nc}^{\alpha} S_{\alpha}(\omega_{cn}) - A_{ac}^{\alpha} A_{db}^{\alpha} S_{\alpha}(\omega_{ca}) + \delta_{ac} \sum_n A_{dn}^{\alpha} A_{nb}^{\alpha} S_{\alpha}(\omega_{dn}) - A_{ac}^{\alpha} A_{db}^{\alpha} S_{\alpha}(\omega_{db}) \right\}.$$

Bloch-Redfield master equation in QuTiP

In QuTiP, the Bloch-Redfield tensor Eq. (3.34) can be calculated using the function `qutip.bloch_redfield.bloch_redfield_tensor`. It takes two mandatory arguments: The system Hamiltonian H , a nested list of operator A_{α} , spectral density functions $S_{\alpha}(\omega)$ pairs that characterize the coupling between system and bath. The spectral density functions are Python callback functions that takes the (angular) frequency as a single argument.

To illustrate how to calculate the Bloch-Redfield tensor, let's consider a two-level atom

$$H = -\frac{1}{2}\Delta\sigma_x - \frac{1}{2}\epsilon_0\sigma_z \quad (3.34)$$

```
delta = 0.2 * 2*np.pi
eps0 = 1.0 * 2*np.pi
gamma1 = 0.5

H = - delta/2.0 * sigmax() - eps0/2.0 * sigmaz()

def ohmic_spectrum(w):
    if w == 0.0: # dephasing inducing noise
        return gamma1
    else: # relaxation inducing noise
        return gamma1 / 2 * (w / (2 * np.pi)) * (w > 0.0)

R, ekets = bloch_redfield_tensor(H, a_ops=[[sigmax(), ohmic_spectrum]])

print(R)
```

Output:

```
Quantum object: dims = [[2], [2]], [[2], [2]], shape = (4, 4), type = super,
↳ isherm = False
Qobj data =
[[ 0.          +0.j          0.          +0.j          0.          +0.j
  0.24514517+0.j          ]
 [ 0.          +0.j         -0.16103412-6.4076169j  0.          +0.j
  0.          +0.j          ]
 [ 0.          +0.j          0.          +0.j         -0.16103412+6.4076169j
  0.          +0.j          ]
 [ 0.          +0.j          0.          +0.j          0.          +0.j
 -0.24514517+0.j          ]]
```

Note that it is also possible to add Lindblad dissipation superoperators in the Bloch-Redfield tensor by passing the operators via the `c_ops` keyword argument like you would in the `qutip.mesolve` or `qutip.mcsolve` functions. For convenience, the function `qutip.bloch_redfield_tensor` also returns the basis transformation operator, the eigen vector matrix, since they are calculated in the process of calculating the Bloch-Redfield tensor R , and the *ekets* are usually needed again later when transforming operators between the laboratory basis and the eigen basis. The tensor can be obtained in the laboratory basis by setting `fock_basis=True`, in that case, the transformation operator is not returned.

The evolution of a wavefunction or density matrix, according to the Bloch-Redfield master equation (3.33), can be calculated using the QuTiP function `qutip.mesolve` using Bloch-Redfield tensor in the laboratory basis instead

of a liouvillian. For example, to evaluate the expectation values of the σ_x , σ_y , and σ_z operators for the example above, we can use the following code:

```
delta = 0.2 * 2*np.pi
eps0 = 1.0 * 2*np.pi
gamma1 = 0.5

H = - delta/2.0 * sigmax() - eps0/2.0 * sigmaz()

def ohmic_spectrum(w):
    if w == 0.0: # dephasing inducing noise
        return gamma1
    else: # relaxation inducing noise
        return gamma1 / 2 * (w / (2 * np.pi)) * (w > 0.0)

R = bloch_redfield_tensor(H, [[sigmax(), ohmic_spectrum]], fock_basis=True)

tlist = np.linspace(0, 15.0, 1000)

psi0 = rand_ket(2, seed=1)

e_ops = [sigmax(), sigmay(), sigmaz()]

expt_list = mesolve(R, psi0, tlist, e_ops=e_ops).expect


sphere = Bloch()

sphere.add_points([expt_list[0], expt_list[1], expt_list[2]])

sphere.vector_color = ['r']

sphere.add_vectors(np.array([delta, 0, eps0]) / np.sqrt(delta ** 2 + eps0 ** 2))

sphere.make_sphere()
```



The two steps of calculating the Bloch-Redfield tensor and evolving according to the corresponding master equation can be combined into one by using the function `qutip.brmsolve`, which takes same arguments as `qutip.mesolve` and `qutip.mcsolve`, save for the additional nested list of operator-spectrum pairs that is called `a_ops`.

```
output = brmsolve(H, psi0, tlist, a_ops=[[sigmax(), ohmic_spectrum]], e_ops=e_ops)
```

where the resulting `output` is an instance of the class `qutip.Result`.

Time-dependent Bloch-Redfield Dynamics


If you have not done so already, please read the section: *Solving Problems with Time-dependent Hamiltonians*.

As we have already discussed, the Bloch-Redfield master equation requires transforming into the eigenbasis of the system Hamiltonian. For time-independent systems, this transformation need only be done once. However, for time-dependent systems, one must move to the instantaneous eigenbasis at each time-step in the evolution, thus greatly increasing the computational complexity of the dynamics. In addition, the requirement for computing all the eigenvalues severely limits the scalability of the method. Fortunately, this eigen decomposition occurs at the Hamiltonian level, as opposed to the super-operator level, and thus, with efficient programming, one can tackle many systems that are commonly encountered.

For time-dependent Hamiltonians, the Hamiltonian itself can be passed into the solver like any other time dependent Hamiltonian, as thus we will not discuss this topic further. Instead, here the focus is on time-dependent bath coupling terms. To this end, suppose that we have a dissipative harmonic oscillator, where the white-noise dissipation rate decreases exponentially with time $\kappa(t) = \kappa(0) \exp(-t)$. In the Lindblad or monte-carlo solvers, this could be implemented as a time-dependent collapse operator list `c_ops = [[a, 'sqrt(kappa*exp(-t))']]`. In the Bloch-Redfield solver, the bath coupling terms must be Hermitian.

As such, in this example, our coupling operator is the position operator $a+a.dag()$. The complete example, and comparison to the analytic expression is:

```
N = 10 # number of basis states to consider
a = destroy(N)
H = a.dag() * a
psi0 = basis(N, 9) # initial state
kappa = 0.2 # coupling to oscillator
a_ops = [
    ([a+a.dag(), f'sqrt({kappa})*exp(-t)]), '(w>=0)')
]
tlist = np.linspace(0, 10, 100)
out = brmesolve(H, psi0, tlist, a_ops, e_ops=[a.dag() * a])
actual_answer = 9.0 * np.exp(-kappa * (1.0 - np.exp(-tlist)))
plt.figure()
plt.plot(tlist, out.expect[0])
plt.plot(tlist, actual_answer)
plt.show()
```



In many cases, the bath-coupling operators can take the form $A = f(t)a + f(t)^*a^\dagger$. The operator parts of the `a_ops` can be made of as many time-dependent terms as needed to construct such operator. For example consider a white-noise bath that is coupled to an operator of the form `exp(1j*t)*a + exp(-1j*t)*a.dag()`. In this example, the `a_ops` list would be:

```
a_ops = [
    ([[a, 'exp(1j*t)'], [a.dag(), 'exp(-1j*t)']], f'{kappa} * (w >= 0)')
]
```

where the first tuple element `[[a, 'exp(1j*t)'], [a.dag(), 'exp(-1j*t)']]` tells the solver what is the time-dependent Hermitian coupling operator. The second tuple `f'{kappa} * (w >= 0)'`, gives the noise power spectrum. A full example is:

```
N = 10

w0 = 1.0 * 2 * np.pi

g = 0.05 * w0

kappa = 0.15

times = np.linspace(0, 25, 1000)

a = destroy(N)

H = w0 * a.dag() * a + g * (a + a.dag())

psi0 = ket2dm((basis(N, 4) + basis(N, 2) + basis(N, 0)).unit())

a_ops = [
    QobjEvo([[a, 'exp(1j*t)'], [a.dag(), 'exp(-1j*t)']], (f'{kappa} * (w >= 0)')
)]

e_ops = [a.dag() * a, a + a.dag()]

res_brme = brmesolve(H, psi0, times, a_ops, e_ops)


plt.figure()

plt.plot(times, res_brme.expect[0], label=r'$a^{+}a$')

plt.plot(times, res_brme.expect[1], label=r'$a+a^{+}$')

plt.legend()

plt.show()
```



Further examples on time-dependent Bloch-Redfield simulations can be found in the online tutorials.

3.5.10 Floquet Formalism

Introduction

Many time-dependent problems of interest are periodic. The dynamics of such systems can be solved for directly by numerical integration of the Schrödinger or Master equation, using the time-dependent Hamiltonian. But they can also be transformed into time-independent problems using the Floquet formalism. Time-independent problems can be solve much more efficiently, so such a transformation is often very desirable.

In the standard derivations of the Lindblad and Bloch-Redfield master equations the Hamiltonian describing the system under consideration is assumed to be time independent. Thus, strictly speaking, the standard forms of these master equation formalisms should not blindly be applied to system with time-dependent Hamiltonians. However, in many relevant cases, in particular for weak driving, the standard master equations still turns out to be useful for many time-dependent problems. But a more rigorous approach would be to rederive the master equation taking the time-dependent nature of the Hamiltonian into account from the start. The Floquet-Markov Master equation is one such a formalism, with important applications for strongly driven systems (see e.g., [Gri98]).

Here we give an overview of how the Floquet and Floquet-Markov formalisms can be used for solving time-dependent problems in QuTiP. To introduce the terminology and naming conventions used in QuTiP we first give a brief summary of quantum Floquet theory.

Floquet theory for unitary evolution

The Schrödinger equation with a time-dependent Hamiltonian $H(t)$ is

$$H(t)\Psi(t) = i\hbar \frac{\partial}{\partial t} \Psi(t), \quad (3.35)$$

where $\Psi(t)$ is the wave function solution. Here we are interested in problems with periodic time-dependence, i.e., the Hamiltonian satisfies $H(t) = H(t + T)$ where T is the period. According to the Floquet theorem, there exist solutions to (3.35) of the form

$$\Psi_\alpha(t) = \exp(-i\epsilon_\alpha t/\hbar) \Phi_\alpha(t), \quad (3.36)$$

where $\Psi_\alpha(t)$ are the *Floquet states* (i.e., the set of wave function solutions to the Schrödinger equation), $\Phi_\alpha(t) = \Phi_\alpha(t + T)$ are the periodic *Floquet modes*, and ϵ_α are the *quasienergy levels*. The quasienergy levels are constants in time, but only uniquely defined up to multiples of $2\pi/T$ (i.e., unique value in the interval $[0, 2\pi/T]$).

If we know the Floquet modes (for $t \in [0, T]$) and the quasienergies for a particular $H(t)$, we can easily decompose any initial wavefunction $\Psi(t = 0)$ in the Floquet states and immediately obtain the solution for arbitrary t

$$\Psi(t) = \sum_\alpha c_\alpha \Psi_\alpha(t) = \sum_\alpha c_\alpha \exp(-i\epsilon_\alpha t/\hbar) \Phi_\alpha(t), \quad (3.37)$$

where the coefficients c_α are determined by the initial wavefunction $\Psi(0) = \sum_\alpha c_\alpha \Psi_\alpha(0)$.

This formalism is useful for finding $\Psi(t)$ for a given $H(t)$ only if we can obtain the Floquet modes $\Phi_\alpha(t)$ and quasienergies ϵ_α more easily than directly solving (3.35). By substituting (3.36) into the Schrödinger equation (3.35) we obtain an eigenvalue equation for the Floquet modes and quasienergies

$$\mathcal{H}(t)\Phi_\alpha(t) = \epsilon_\alpha \Phi_\alpha(t), \quad (3.38)$$

where $\mathcal{H}(t) = H(t) - i\hbar \partial_t$. This eigenvalue problem could be solved analytically or numerically, but in QuTiP we use an alternative approach for numerically finding the Floquet states and quasienergies [see e.g. Creffield et al., Phys. Rev. B 67, 165301 (2003)]. Consider the propagator for the time-dependent Schrödinger equation (3.35), which by definition satisfies

$$U(T + t, t)\Psi(t) = \Psi(T + t).$$

Inserting the Floquet states from (3.36) into this expression results in

$$U(T + t, t) \exp(-i\epsilon_\alpha t/\hbar) \Phi_\alpha(t) = \exp(-i\epsilon_\alpha(T + t)/\hbar) \Phi_\alpha(T + t),$$

or, since $\Phi_\alpha(T + t) = \Phi_\alpha(t)$,

$$U(T + t, t) \Phi_\alpha(t) = \exp(-i\epsilon_\alpha T/\hbar) \Phi_\alpha(t) = \eta_\alpha \Phi_\alpha(t),$$

which shows that the Floquet modes are eigenstates of the one-period propagator. We can therefore find the Floquet modes and quasienergies $\epsilon_\alpha = -\hbar \arg(\eta_\alpha)/T$ by numerically calculating $U(T + t, t)$ and diagonalizing it. In particular this method is useful to find $\Phi_\alpha(0)$ by calculating and diagonalize $U(T, 0)$.

The Floquet modes at arbitrary time t can then be found by propagating $\Phi_\alpha(0)$ to $\Phi_\alpha(t)$ using the wave function propagator $U(t, 0)\Psi_\alpha(0) = \Psi_\alpha(t)$, which for the Floquet modes yields

$$U(t, 0)\Phi_\alpha(0) = \exp(-i\epsilon_\alpha t/\hbar) \Phi_\alpha(t),$$

so that $\Phi_\alpha(t) = \exp(i\epsilon_\alpha t/\hbar) U(t, 0)\Phi_\alpha(0)$. Since $\Phi_\alpha(t)$ is periodic we only need to evaluate it for $t \in [0, T]$, and from $\Phi_\alpha(t \in [0, T])$ we can directly evaluate $\Phi_\alpha(t)$, $\Psi_\alpha(t)$ and $\Psi(t)$ for arbitrary large t .

Floquet formalism in QuTiP

QuTiP provides a family of functions to calculate the Floquet modes and quasi energies, Floquet state decomposition, etc., given a time-dependent Hamiltonian on the *callback format*, *list-string format* and *list-callback format* (see, e.g., `qutip.mesolve` for details).

Consider for example the case of a strongly driven two-level atom, described by the Hamiltonian

$$H(t) = -\frac{1}{2}\Delta\sigma_x - \frac{1}{2}\epsilon_0\sigma_z + \frac{1}{2}A\sin(\omega t)\sigma_z. \quad (3.39)$$

In QuTiP we can define this Hamiltonian as follows:

```
>>> delta = 0.2 * 2*np.pi
>>> eps0 = 1.0 * 2*np.pi
>>> A = 2.5 * 2*np.pi
>>> omega = 1.0 * 2*np.pi
>>> H0 = - delta/2.0 * sigmax() - eps0/2.0 * sigmaz()
>>> H1 = A/2.0 * sigmaz()
>>> args = {'w': omega}
>>> H = [H0, [H1, 'sin(w * t)']]
```

The $t = 0$ Floquet modes corresponding to the Hamiltonian (3.39) can then be calculated using the `qutip.FloquetBasis` class, which encapsulates the Floquet modes and the quasienergies:

```
>>> T = 2*np.pi / omega
>>> floquet_basis = FloquetBasis(H, T, args)
>>> f_energies = floquet_basis.e_quasi
>>> f_energies
array([-2.83131212,  2.83131212])
>>> f_modes_0 = floquet_basis.mode(0)
>>> f_modes_0
[Quantum object: dims = [[2], [1]], shape = (2, 1), type = ket
Qobj data =
[[ 0.72964231+0.j
   -0.39993746+0.554682j]],
Quantum object: dims = [[2], [1]], shape = (2, 1), type = ket
Qobj data =
[[0.39993746+0.554682j
   0.72964231+0.j      ]]]
```


For some problems interesting observations can be draw from the quasienergy levels alone. Consider for example the quasienergies for the driven two-level system introduced above as a function of the driving amplitude, calculated and plotted in the following example. For certain driving amplitudes the quasienergy levels cross. Since the quasienergies can be associated with the time-scale of the long-term dynamics due that the driving, degenerate quasienergies indicates a “freezing” of the dynamics (sometimes known as coherent destruction of tunneling).

```
>>> delta = 0.2 * 2 * np.pi
>>> eps0 = 0.0 * 2 * np.pi
>>> omega = 1.0 * 2 * np.pi
>>> A_vec = np.linspace(0, 10, 100) * omega
>>> T = (2 * np.pi) / omega
>>> tlist = np.linspace(0.0, 10 * T, 101)
>>> spsi0 = basis(2, 0)
>>> q_energies = np.zeros((len(A_vec), 2))
>>> H0 = delta / 2.0 * sigmaz() - eps0 / 2.0 * sigmax()
>>> args = {'w': omega}
>>> for idx, A in enumerate(A_vec):
>>>     H1 = A / 2.0 * sigmax()
>>>     H = [H0, [H1, lambda t: np.sin(args['w'] * t)]]
>>>     floquet_basis = FloquetBasis(H, T, args)
>>>     q_energies[idx,:] = floquet_basis.e_quasi
```

(continues on next page)

(continued from previous page)

```
>>> plt.figure()
>>> plt.plot(A_vec/omega, q_energies[:,0] / delta, 'b', A_vec/omega, q_energies[:,
↪ 1] / delta, 'r')
>>> plt.xlabel(r'$A/\omega$')
>>> plt.ylabel(r'Quasienergy / $\Delta$')
>>> plt.title(r'Floquet quasienergies')
>>> plt.show()
```



Given the Floquet modes at $t = 0$, we obtain the Floquet mode at some later time t using `FloquetBasis.mode`:

```
>>> f_modes_t = floquet_basis.mode(2.5)
>>> f_modes_t
[Quantum object: dims = [[2], [1]], shape = (2, 1), type = ket
Qobj data =
[[-0.89630512-0.23191946j]
 [ 0.37793106-0.00431336j]],
Quantum object: dims = [[2], [1]], shape = (2, 1), type = ket
Qobj data =
[[-0.37793106-0.00431336j]
 [-0.89630512+0.23191946j]]]
```

The purpose of calculating the Floquet modes is to find the wavefunction solution to the original problem (3.39) given some initial state $|\psi_0\rangle$. To do that, we first need to decompose the initial state in the Floquet states, using the function `FloquetBasis.to_floquet_basis`

```
>>> psi0 = rand_ket(2)
>>> f_coeff = floquet_basis.to_floquet_basis(psi0)
```

(continues on next page)

(continued from previous page)

```
>>> f_coeff
[(-0.645265993068382+0.7304552549315746j),
 (0.15517002114250228-0.1612116102238258j)]
```

and given this decomposition of the initial state in the Floquet states we can easily evaluate the wavefunction that is the solution to (3.39) at an arbitrary time t using the function `FloquetBasis.from_floquet_basis`:

```
>>> t = 10 * np.random.rand()
>>> psi_t = floquetbasis.from_floquet_basis(f_coeff, t)
```

The following example illustrates how to use the functions introduced above to calculate and plot the time-evolution of (3.39).

```
import numpy as np
from matplotlib import pyplot

import qutip

delta = 0.2 * 2*np.pi
eps0 = 1.0 * 2*np.pi
A = 0.5 * 2*np.pi
omega = 1.0 * 2*np.pi
T = (2*np.pi)/omega
tlist = np.linspace(0.0, 10 * T, 101)
psi0 = qutip.basis(2, 0)

H0 = - delta/2.0 * qutip.sigmax() - eps0/2.0 * qutip.sigmaz()
H1 = A/2.0 * qutip.sigmaz()
args = {'w': omega}
H = [H0, [H1, lambda t, w: np.sin(w * t)]]


# Create the floquet system for the time-dependent hamiltonian
floquetbasis = qutip.FloquetBasis(H, T, args)

# decompose the initial state in the floquet modes
f_coeff = floquetbasis.to_floquet_basis(psi0)

# calculate the wavefunctions using the from the floquet modes coefficients
p_ex = np.zeros(len(tlist))
for n, t in enumerate(tlist):
    psi_t = floquetbasis.from_floquet_basis(f_coeff, t)
    p_ex[n] = qutip.expect(qutip.num(2), psi_t)

# For reference: calculate the same thing with mesolve
p_ex_ref = qutip.mesolve(H, psi0, tlist, [], [qutip.num(2)], args).expect[0]

# plot the results
pyplot.plot(tlist, np.real(p_ex), 'ro', tlist, 1-np.real(p_ex), 'bo')
pyplot.plot(tlist, np.real(p_ex_ref), 'r', tlist, 1-np.real(p_ex_ref), 'b')
pyplot.xlabel('Time')
pyplot.ylabel('Occupation probability')
pyplot.legend(("Floquet $P_1$", "Floquet $P_0$", "Lindblad $P_1$", "Lindblad $P_0$
↔"))
pyplot.show()
```



Pre-computing the Floquet modes for one period

When evaluating the Floquet states or the wavefunction at many points in time it is useful to pre-compute the Floquet modes for the first period of the driving with the required times. The list of times to pre-compute modes for may be passed to `FloquetBasis` using `precompute=tlist`, and then `:meth:`FloquetBasis.from_floquet_basis` and FloquetBasis.to_floquet_basis can be used to efficiently retrieve the wave function at the pre-computed times. The following example illustrates how the example from the previous section can be solved more efficiently using these functions for pre-computing the Floquet modes:`

```
import numpy as np
from matplotlib import pyplot
import qutip

delta = 0.0 * 2*np.pi
eps0 = 1.0 * 2*np.pi
A = 0.25 * 2*np.pi
omega = 1.0 * 2*np.pi
T = 2*np.pi / omega
tlist = np.linspace(0.0, 10 * T, 101)
psi0 = qutip.basis(2,0)

H0 = - delta/2.0 * qutip.sigmax() - eps0/2.0 * qutip.sigmaz()
H1 = A/2.0 * qutip.sigmax()
args = {'w': omega}
H = [H0, [H1, lambda t, w: np.sin(w * t)]]

# find the floquet modes for the time-dependent hamiltonian
floquetbasis = qutip.FloquetBasis(H, T, args, precompute=tlist)

# decompose the initial state in the floquet modes
f_coeff = floquetbasis.to_floquet_basis(psi0)


# calculate the wavefunctions using the from the floquet modes coefficients
p_ex = np.zeros(len(tlist))
for n, t in enumerate(tlist):
    psi_t = floquetbasis.from_floquet_basis(f_coeff, t)
    p_ex[n] = qutip.expect(qutip.num(2), psi_t)

# For reference: calculate the same thing with mesolve
p_ex_ref = qutip.mesolve(H, psi0, tlist, [], [qutip.num(2)], args).expect[0]
```

(continues on next page)

(continued from previous page)

```
# plot the results
pyplot.plot(tlist, np.real(p_ex), 'ro', tlist, 1-np.real(p_ex), 'bo')
pyplot.plot(tlist, np.real(p_ex_ref), 'r', tlist, 1-np.real(p_ex_ref), 'b')
pyplot.xlabel('Time')
pyplot.ylabel('Occupation probability')
pyplot.legend(("Floquet $P_1$", "Floquet $P_0$", "Lindblad $P_1$", "Lindblad $P_0$
↔"))
pyplot.show()
```



Note that the parameters and the Hamiltonian used in this example is not the same as in the previous section, and hence the different appearance of the resulting figure.

For convenience, all the steps described above for calculating the evolution of a quantum system using the Floquet formalisms are encapsulated in the function `qutip.floquet.fsesolve`. Using this function, we could have achieved the same results as in the examples above using

```
output = fsesolve(H, psi0=psi0, tlist=tlist, e_ops=[qutip.num(2)], args=args)
p_ex = output.expect[0]
```

Floquet theory for dissipative evolution

A driven system that is interacting with its environment is not necessarily well described by the standard Lindblad master equation, since its dissipation process could be time-dependent due to the driving. In such cases a rigorous approach would be to take the driving into account when deriving the master equation. This can be done in many different ways, but one way common approach is to derive the master equation in the Floquet basis. That approach results in the so-called Floquet-Markov master equation, see Grifoni et al., Physics Reports 304, 299 (1998) for details.

For a brief summary of the derivation, the important contents for the implementation in QuTiP are listed below.

The floquet mode $|\phi_\alpha(t)\rangle$ refers to a full class of quasienergies defined by $\epsilon_\alpha + k\Omega$ for arbitrary k . Hence, the quasienergy difference between two floquet modes is given by

$$\Delta_{\alpha\beta k} = \frac{\epsilon_\alpha - \epsilon_\beta}{\hbar} + k\Omega$$

For any coupling operator q (given by the user) the matrix elements in the floquet basis are calculated as:

$$X_{\alpha\beta k} = \frac{1}{T} \int_0^T dt e^{-ik\Omega t} \langle \phi_\alpha(t) | q | \phi_\beta(t) \rangle$$

From the matrix elements and the spectral density $J(\omega)$, the decay rate $\gamma_{\alpha\beta k}$ is defined:

$$\gamma_{\alpha\beta k} = 2\pi J(\Delta_{\alpha\beta k}) |X_{\alpha\beta k}|^2$$

The master equation is further simplified by the RWA, which makes the following matrix useful:

$$A_{\alpha\beta} = \sum_{k=-\infty}^{\infty} [\gamma_{\alpha\beta k} + n_{th}(|\Delta_{\alpha\beta k}|)(\gamma_{\alpha\beta k} + \gamma_{\alpha\beta-k})]$$

The density matrix of the system then evolves according to:

$$\begin{aligned} \dot{\rho}_{\alpha\alpha}(t) &= \sum_{\nu} (A_{\alpha\nu} \rho_{\nu\nu}(t) - A_{\nu\alpha} \rho_{\alpha\alpha}(t)) \\ \dot{\rho}_{\alpha\beta}(t) &= -\frac{1}{2} \sum_{\nu} (A_{\nu\alpha} + A_{\nu\beta}) \rho_{\alpha\beta}(t) \quad \alpha \neq \beta \end{aligned}$$

The Floquet-Markov master equation in QuTiP

The QuTiP function `qutip.floquet.fmmsolve` implements the Floquet-Markov master equation. It calculates the dynamics of a system given its initial state, a time-dependent Hamiltonian, a list of operators through which the system couples to its environment and a list of corresponding spectral-density functions that describes the environment. In contrast to the `qutip.mesolve` and `qutip.mcsolve`, and the `qutip.floquet.fmmsolve` does characterize the environment with dissipation rates, but extract the strength of the coupling to the environment from the noise spectral-density functions and the instantaneous Hamiltonian parameters (similar to the Bloch-Redfield master equation solver `qutip.bloch_redfield.brmsolve`).

Note: Currently the `qutip.floquet.fmmsolve` can only accept a single environment coupling operator and spectral-density function.

The noise spectral-density function of the environment is implemented as a Python callback function that is passed to the solver. For example:

```
gamma1 = 0.1
def noise_spectrum(omega):
    return (omega>0) * 0.5 * gamma1 * omega/(2*pi)
```

The other parameters are similar to the `qutip.mesolve` and `qutip.mcsolve`, and the same format for the return value is used `qutip.solve.solver.Result`. The following example extends the example studied above, and uses `qutip.floquet.fmmsolve` to introduce dissipation into the calculation

```
import numpy as np
from matplotlib import pyplot
import qutip

delta = 0.0 * 2*np.pi
eps0 = 1.0 * 2*np.pi
A = 0.25 * 2*np.pi
omega = 1.0 * 2*np.pi
T = 2*np.pi / omega
tlist = np.linspace(0.0, 20 * T, 301)
psi0 = qutip.basis(2,0)

H0 = - delta/2.0 * qutip.sigmamax() - eps0/2.0 * qutip.sigmaz()
H1 = A/2.0 * qutip.sigmamax()
args = {'w': omega}
H = [H0, [H1, lambda t, w: np.sin(w * t)]]
```

(continues on next page)

(continued from previous page)

```

# noise power spectrum
gamma1 = 0.1
def noise_spectrum(omega):
    return (omega>0) * 0.5 * gamma1 * omega/(2*np.pi)


# solve the floquet-markov master equation
output = qutip.fmmsolve(
    H, psi0, tlist, [qutip.sigmax()],
    spectra_cb=[noise_spectrum], T=T,
    args=args, options={"store_floquet_states": True}
)

# calculate expectation values in the computational basis
p_ex = np.zeros(tlist.shape, dtype=np.complex128)
for idx, t in enumerate(tlist):
    f_coeff_t = output.floquet_states[idx]
    psi_t = output.floquet_basis.from_floquet_basis(f_coeff_t, t)
    # Alternatively
    psi_t = output.states[idx]
    p_ex[idx] = qutip.expect(qutip.num(2), psi_t)

# For reference: calculate the same thing with mesolve
output = qutip.mesolve(H, psi0, tlist,
                      [np.sqrt(gamma1) * qutip.sigmax()], [qutip.num(2)],
                      args)
p_ex_ref = output.expect[0]

# plot the results
pyplot.plot(tlist, np.real(p_ex), 'r--', tlist, 1-np.real(p_ex), 'b--')
pyplot.plot(tlist, np.real(p_ex_ref), 'r', tlist, 1-np.real(p_ex_ref), 'b')
pyplot.xlabel('Time')
pyplot.ylabel('Occupation probability')
pyplot.legend(("Floquet  $P_1$ ", "Floquet  $P_0$ ", "Lindblad  $P_1$ ", "Lindblad  $P_0$ "
              "\n↔"))
pyplot.show()

```



Finally, `qutip.solver.floquet.fmmsolve` always expects the `e_ops` to be specified in the laboratory basis (as for other solvers) and we can calculate expectation values using:

```
output = fmmsolve(H, psi0, tlist, [sigmax()], e_ops=[num(2)], spectra_cb=[noise_spectrum], T=T,
```

```
args=args) p_ex = output.expect[0]
```

3.5.11 Permutational Invariance

Permutational Invariant Quantum Solver (PIQS)

The *Permutational Invariant Quantum Solver (PIQS)* is a QuTiP module that allows to study the dynamics of an open quantum system consisting of an ensemble of identical qubits that can dissipate through local and collective baths according to a Lindblad master equation.

The Liouvillian of an ensemble of N qubits, or two-level systems (TLSs), $\mathcal{D}_{TLS}(\rho)$, can be built using only polynomial – instead of exponential – resources. This has many applications for the study of realistic quantum optics models of many TLSs and in general as a tool in cavity QED.

Consider a system evolving according to the equation

$$\begin{aligned} \dot{\rho} = \mathcal{D}_{TLS}(\rho) = & -\frac{i}{\hbar}[H, \rho] + \frac{\gamma_{CE}}{2}\mathcal{L}_{J_-}[\rho] + \frac{\gamma_{CD}}{2}\mathcal{L}_{J_z}[\rho] + \frac{\gamma_{CP}}{2}\mathcal{L}_{J_+}[\rho] \\ & + \sum_{n=1}^N \left(\frac{\gamma_E}{2}\mathcal{L}_{J_{-,n}}[\rho] + \frac{\gamma_D}{2}\mathcal{L}_{J_{z,n}}[\rho] + \frac{\gamma_P}{2}\mathcal{L}_{J_{+,n}}[\rho] \right) \end{aligned}$$

where $J_{\alpha,n} = \frac{1}{2}\sigma_{\alpha,n}$ are SU(2) Pauli spin operators, with $\alpha = x, y, z$ and $J_{\pm,n} = \sigma_{\pm,n}$. The collective spin operators are $J_{\alpha} = \sum_n J_{\alpha,n}$. The Lindblad super-operators are $\mathcal{L}_A = 2A\rho A^\dagger - A^\dagger A\rho - \rho A^\dagger A$.

The inclusion of local processes in the dynamics lead to using a Liouvillian space of dimension 4^N . By exploiting the permutational invariance of identical particles [2-8], the Liouvillian $\mathcal{D}_{TLS}(\rho)$ can be built as a block-diagonal matrix in the basis of Dicke states $|j, m\rangle$.

The system under study is defined by creating an object of the `Dicke` class, e.g. simply named `system`, whose first attribute is

- `system.N`, the number of TLSs of the system N .

The rates for collective and local processes are simply defined as

- `collective_emission` defines γ_{CE} , collective (superradiant) emission
- `collective_dephasing` defines γ_{CD} , collective dephasing
- `collective_pumping` defines γ_{CP} , collective pumping.
- `emission` defines γ_E , incoherent emission (losses)
- `dephasing` defines γ_D , local dephasing
- `pumping` defines γ_P , incoherent pumping.

Then the `system.lindbladian()` creates the total TLS Lindbladian superoperator matrix. Similarly, `system.hamiltonian` defines the TLS hamiltonian of the system H_{TLS} .

The system's Liouvillian can be built using `system.liouvillian()`. The properties of a `Piqs` object can be visualized by simply calling `system`. We give two basic examples on the use of *PIQS*. In the first example the incoherent emission of N driven TLSs is considered.

```
from piqs import Dicke
from qutip import steadystate
N = 10
system = Dicke(N, emission = 1, pumping = 2)
L = system.liouvillian()
steady = steadystate(L)
```

For more example of use, see the “Permutational Invariant Lindblad Dynamics” section in the tutorials section of the website, <https://qutip.org/tutorials.html>.

Table 2: Useful PIQS functions.

Operators	Command	Description
Collective spin algebra J_x, J_y, J_z	<code>jspin(N)</code>	The collective spin algebra J_x, J_y, J_z for N TLSs
Collective spin J_x	<code>jspin(N, "x")</code>	The collective spin operator J_x . Requires N number of TLSs
Collective spin J_y	<code>jspin(N, "y")</code>	The collective spin operator J_y . Requires N number of TLSs
Collective spin J_z	<code>jspin(N, "z")</code>	The collective spin operator J_z . Requires N number of TLSs
Collective spin J_+	<code>jspin(N, "+")</code>	The collective spin operator J_+ .
Collective spin J_-	<code>jspin(N, "-")</code>	The collective spin operator J_- .
Collective spin J_z in uncoupled basis	<code>jspin(N, "z", basis='uncoupled')</code>	The collective spin operator J_z in the uncoupled basis of dimension 2^N .
Dicke state $ j, m\rangle$ density matrix	<code>dicke(N, j, m)</code>	The density matrix for the Dicke state given by $ j, m\rangle$
Excited-state density matrix in Dicke basis	<code>excited(N)</code>	The excited state in the Dicke basis
Excited-state density matrix in uncoupled basis	<code>excited(N, basis="uncoupled")</code>	The excited state in the uncoupled basis
Ground-state density matrix in Dicke basis	<code>ground(N)</code>	The ground state in the Dicke basis
GHZ-state density matrix in the Dicke basis	<code>ghz(N)</code>	The GHZ-state density matrix in the Dicke (default) basis for N number of TLS
Collapse operators of the ensemble	<code>Dicke.c_ops()</code>	The collapse operators for the ensemble can be called by the <code>c_ops</code> method of the Dicke class.

Note that the mathematical object representing the density matrix of the full system that is manipulated (or obtained from *steadystate*) in the Dicke-basis formalism used here is a *representative of the density matrix*. This *representative object* is of linear size N^2 , whereas the full density matrix is defined over a 2^N Hilbert space. In order to calculate nonlinear functions of such density matrix, such as the Von Neumann entropy or the purity, it is necessary to take into account the degeneracy of each block of such block-diagonal density matrix. Note that as long as one calculates expected values of operators, being $\text{Tr}[A \cdot \rho]$ a *linear* function of ρ , the *representative density matrix* give straightforwardly the correct result. When a *nonlinear* function of the density matrix needs to be calculated, one needs to weigh each degenerate block correctly; this is taken care by the *dicke_function_trace* in *qutip.piqs*, and the user can use it to define general nonlinear functions that can be described as the trace of a Taylor expandable function. Two nonlinear functions that use *dicke_function_trace* and are already implemented are *purity_dicke*, to calculate the purity of a density matrix in the Dicke basis, and *entropy_vn_dicke*, which can be used to calculate the Von Neumann entropy.

More functions relative to the *qutip.piqs* module can be found at [API documentation](#). Attributes to the `qutip.piqs.Dicke` and `qutip.piqs.Pim` class can also be found there.

3.5.12 Setting Options for the Dynamics Solvers

Occasionally it is necessary to change the built in parameters of the dynamics solvers used by for example the `qutip.mesolve` and `qutip.mcsolve` functions. The options for all dynamics solvers may be changed by using the dictionaries.

```
options = {"store_states": True, "atol": 1e-12}
```

Supported items come from 2 sources, the solver and the ODE integration method. Supported solver options and their default can be seen using the class interface:

```
help(MESolver.options)
```

Options supported by the ODE integration depend on the “method” options of the solver, they can be listed through the integrator method of the solvers:

```
help(MESolver.integrator("adams").options)
```

See [Integrator](#) for a list of supported methods.

As an example, let us consider changing the integrator, turn the GUI off, and strengthen the absolute tolerance.

```
options = {method="bdf", "atol": 1e-10, "progress_bar": False}
```

To use these new settings we can use the keyword argument `options` in either the `qutip.mesolve` and `qutip.mcsolve` function:

```
>>> mesolve(H0, psi0, tlist, c_op_list, [sigmaz()], options=options)
```

or:

```
>>> MCSolver(H0, c_op_list, options=options)
```

3.6 Hierarchical Equations of Motion

3.6.1 Introduction

The Hierarchical Equations of Motion (HEOM) method was originally developed by Tanimura and Kubo [TK89] in the context of physical chemistry to “exactly” solve a quantum system in contact with a bosonic environment, encapsulated in the Hamiltonian:

$$H = H_s + \sum_k \omega_k a_k^\dagger a_k + \hat{Q} \sum_k g_k (a_k + a_k^\dagger).$$

As in other solutions to this problem, the properties of the bath are encapsulated by its temperature and its spectral density,

$$J(\omega) = \pi \sum_k g_k^2 \delta(\omega - \omega_k).$$

In the HEOM, for bosonic baths, one typically chooses a Drude-Lorentz spectral density:

$$J_D = \frac{2\lambda\gamma\omega}{(\gamma^2 + \omega^2)},$$

or an under-damped Brownian motion spectral density:

$$J_U = \frac{\alpha^2 \Gamma \omega}{[(\omega_c^2 - \omega^2)^2 + \Gamma^2 \omega^2]}.$$

Given the spectral density, the HEOM requires a decomposition of the bath correlation functions in terms of exponentials. In [Describing the system and bath](#) we describe how this is done with code examples, and how these expansions are passed to the solver.

In addition to support for bosonic environments, QuTiP also provides support for fermionic environments which is described in [Fermionic Environments](#).

Both bosonic and fermionic environments are supported via a single solver, `HEOMSolver`, that supports solving for both dynamics and steady-states.

solver.heom##### Bosonic Environments #####

In this section we consider a simple two-level system coupled to a Drude-Lorentz bosonic bath. The system Hamiltonian, H_{sys} , and the bath spectral density, J_D , are

$$H_{sys} = \frac{\epsilon\sigma_z}{2} + \frac{\Delta\sigma_x}{2}$$

$$J_D = \frac{2\lambda\gamma\omega}{(\gamma^2 + \omega^2)},$$

We will demonstrate how to describe the bath using two different expansions of the spectral density correlation function (Matsubara's expansion and a Padé expansion), how to evolve the system in time, and how to calculate the steady state.

First we will do this in the simplest way, using the built-in implementations of the two bath expansions, `DrudeLorentzBath` and `DrudeLorentzPadéBath`. We will do this both with a truncated expansion and show how to include an approximation to all of the remaining terms in the bath expansion.

Afterwards, we will show how to calculate the bath expansion coefficients and to use those coefficients to construct your own bath description so that you can implement your own bosonic baths.

Finally, we will demonstrate how to simulate a system coupled to multiple independent baths, as occurs, for example, in certain photosynthesis processes.

A notebook containing a complete example similar to this one implemented in BoFiN can be found in [example notebook 1a](#).

3.6.2 Describing the system and bath

First, let us construct the system Hamiltonian, H_{sys} , and the initial system state, ρ_0 :

```
from qutip import basis, sigmax, sigmaz

# The system Hamiltonian:
eps = 0.5 # energy of the 2-level system
Del = 1.0 # tunnelling term
H_sys = 0.5 * eps * sigmaz() + 0.5 * Del * sigmax()

# Initial state of the system:
rho0 = basis(2,0) * basis(2,0).dag()
```

Now let us describe the bath properties:

```
# Bath properties:
gamma = 0.5 # cut off frequency
lam = 0.1 # coupling strength
T = 0.5 # temperature

# System-bath coupling operator:
Q = sigmaz()
```

where γ (gamma), λ (lam) and T are the parameters of a Drude-Lorentz bath, and Q is the coupling operator between the system and the bath.

We may then pass these parameters to either `DrudeLorentzBath` or `DrudeLorentzPadéBath` to construct an expansion of the bath correlations:

```
from qutip.solver.heom import DrudeLorentzBath
from qutip.solver.heom import DrudeLorentzPadéBath

# Number of expansion terms to retain:
Nk = 2

# Matsubara expansion:
```

(continues on next page)

(continued from previous page)

```
bath = DrudeLorentzBath(Q, lam, gamma, T, Nk)

# Pad  expansion:
bath = DrudeLorentzPadeBath(Q, lam, gamma, T, Nk)
```

Where N_k is the number of terms to retain within the expansion of the bath.

3.6.3 System and bath dynamics

Now we are ready to construct a solver:

```
from qutip.solver.heom import HEOMSolver

max_depth = 5 # maximum hierarchy depth to retain
options = {"nsteps": 15_000}

solver = HEOMSolver(H_sys, bath, max_depth=max_depth, options=options)
```

and to calculate the system evolution as a function of time:

```
tlist = [0, 10, 20] # times to evaluate the system state at
result = solver.run(rho0, tlist)
```

The `max_depth` parameter determines how many levels of the hierarchy to retain. As a first approximation hierarchy depth may be thought of as similar to the order of Feynman Diagrams (both classify terms by increasing number of interactions).

The `result` is a standard QuTiP results object with the attributes:

- `times`: the times at which the state was evaluated (i.e. `tlist`)
- `states`: the system states at each time
- `expect`: a list with the values of each `e_ops` at each time
- `e_data`: a dictionary with the values of each `e_op` at each time
- `ado_states`: see below (an instance of `HierarchyADOsState`)

If `ado_return=True` is passed to `.run(...)` the full set of auxilliary density operators (ADOs) that make up the hierarchy at each time will be returned as `.ado_states`. We will describe how to use these to determine other properties, such as system-bath currents, later in the fermionic guide (see [Determining currents](#)).

If one has a full set of ADOs from a previous call of `.run(...)` you may supply it as the initial state of the solver by calling `.run(result.ado_states[-1], tlist, ado_init=True)`.

As with other QuTiP solvers, if expectation operators or functions are supplied using `.run(..., e_ops=[...])` the expectation values are available in `result.expect` and `result.e_data`.

Below we run the solver again, but use `e_ops` to store the expectation values of the population of the system states and the coherence:

```
# Define the operators that measure the populations of the two
# system states:
P11p = basis(2,0) * basis(2,0).dag()
P22p = basis(2,1) * basis(2,1).dag()

# Define the operator that measures the 0, 1 element of density matrix
# (corresponding to coherence):
P12p = basis(2,0) * basis(2,1).dag()


# Run the solver:
tlist = np.linspace(0, 20, 101)
```

(continues on next page)

(continued from previous page)

```
result = solver.run(rho0, tlist, e_ops={"11": P11p, "22": P22p, "12": P12p})

# Plot the results:
fig, axes = plt.subplots(1, 1, sharex=True, figsize=(8,8))
axes.plot(result.times, result.e_data["11"], 'b', linewidth=2, label="P11")
axes.plot(result.times, result.e_data["12"], 'r', linewidth=2, label="P12")
axes.set_xlabel(r't', fontsize=28)
axes.legend(loc=0, fontsize=12)
```



3.6.4 Steady-state

Using the same solver, we can also determine the steady state of the combined system and bath using:

```
steady_state, steady_ados = solver.steady_state()
```

where `steady_state` is the steady state of the system and `steady_ados` if the steady state of the full hierarchy. The ADO states are described more fully in [Determining currents](#) and [HierarchyADOsState](#).

3.6.5 Matsubara Terminator

When constructing the Drude-Lorentz bath we have truncated the expansion at $N_k = 2$ terms and ignore the remaining terms.

However, since the coupling to these higher order terms is comparatively weak, we may consider the interaction with them to be Markovian, and construct an additional Lindbladian term that captures their interaction with the system and the lower order terms in the expansion.

This additional term is called the `terminator` because it terminates the expansion.

The [DrudeLorentzBath](#) and [DrudeLorentzPadeBath](#) both provide a means of calculating the terminator for a given expansion:

```
# Matsubara expansion:
bath = DrudeLorentzBath(Q, lam, gamma, T, Nk)

# Padé expansion:
bath = DrudeLorentzPadeBath(Q, lam, gamma, T, Nk)

# Add terminator to the system Liouvillian:
delta, terminator = bath.terminator()
HL = liouvillian(H_sys) + terminator

# Construct solver:
solver = HEOMSolver(HL, bath, max_depth=max_depth, options=options)
```

This captures the Markovian effect of the remaining terms in the expansion without having to fully model many more terms.

The value `delta` is an approximation to the strength of the effect of the remaining terms in the expansion (i.e. how strongly the terminator is coupled to the rest of the system).

3.6.6 Matsubara expansion coefficients

So far we have relied on the built-in [DrudeLorentzBath](#) to construct the Drude-Lorentz bath expansion for us. Now we will calculate the coefficients ourselves and construct a [BosonicBath](#) directly. A similar procedure can be used to apply [HEOMSolver](#) to any bosonic bath for which we can calculate the expansion coefficients.

The real and imaginary parts of the correlation function, $C(t)$, for the bosonic bath is expanded in an exponential series:

$$C(t) = C_{real}(t) + iC_{imag}(t)$$

$$C_{real}(t) = \sum_{k=0}^{\infty} c_{k,real} e^{-\nu_{k,real}t}$$

$$C_{imag}(t) = \sum_{k=0}^{\infty} c_{k,imag} e^{-\nu_{k,imag}t}$$

In the specific case of Matsubara expansion for the Drude-Lorentz bath, the coefficients of this expansion are, for the real part, $C_{real}(t)$:

$$\nu_{k,real} = \begin{cases} \gamma & k = 0 \\ 2\pi k / \beta & k \geq 1 \end{cases}$$

$$C_{k,real} = \begin{cases} \lambda \gamma [\cot(\beta \gamma / 2) - i] & k = 0 \\ \frac{4\lambda \gamma \nu_k}{(\nu_k^2 - \gamma^2) \beta} & k \geq 1 \end{cases}$$

and the imaginary part, $C_{imag}(t)$:

$$\nu_{k,imag} = \begin{cases} \gamma & k = 0 \\ 0 & k \geq 1 \end{cases}$$

$$C_{k,imag} = \begin{cases} -\lambda \gamma & k = 0 \\ 0 & k \geq 1 \end{cases}$$

And now the same numbers calculated in Python:

```
# Convenience functions and parameters:

def cot(x):
    return 1. / np.tan(x)

beta = 1. / T

# Number of expansion terms to calculate:
Nk = 2

# C_real expansion terms:
ck_real = [lam * gamma / np.tan(gamma / (2 * T))]
ck_real.extend([
    (8 * lam * gamma * T * np.pi * k * T /
     ((2 * np.pi * k * T)**2 - gamma**2))
    for k in range(1, Nk + 1)
])
vk_real = [gamma]
vk_real.extend([2 * np.pi * k * T for k in range(1, Nk + 1)])

# C_imag expansion terms (this is the full expansion):
ck_imag = [lam * gamma * (-1.0)]
vk_imag = [gamma]
```

After all that, constructing the bath is very straight forward:

```
from qutip.solver.heom import BosonicBath

bath = BosonicBath(Q, ck_real, vk_real, ck_imag, vk_imag)
```

And we're done!

The *BosonicBath* can be used with the *HEOMSolver* in exactly the same way as the baths we constructed previously using the built-in Drude-Lorentz bath expansions.

3.6.7 Multiple baths

The *HEOMSolver* supports having a system interact with multiple environments. All that is needed is to supply a list of baths instead of a single bath.

In the example below we calculate the evolution of a small system where each basis state of the system interacts with a separate bath. Such an arrangement can model, for example, the Fenna–Matthews–Olson (FMO) pigment-protein complex which plays an important role in photosynthesis (for a full FMO example see the notebook <https://github.com/tehruhn/bofin/blob/main/examples/example-2-FMO-example.ipynb>).

For each bath expansion, we also include the terminator in the system Liouvillian.

At the end, we plot the populations of the system states as a function of time, and show the long-time beating of quantum state coherence that occurs:

```
# The size of the system:
N_sys = 3

def proj(i, j):
    """ A helper function for creating an interaction operator. """
    return basis(N_sys, i) * basis(N_sys, j).dag()


# Construct one bath for each system state:
baths = []
for i in range(N_sys):
    Q = proj(i, i)
    baths.append(DrudeLorentzBath(Q, lam, gamma, T, Nk))

# Construct the system Liouvillian from the system Hamiltonian and
# bath expansion terminators:
H_sys = sum((i + 0.5) * eps * proj(i, i) for i in range(N_sys))
H_sys += sum(
    (i + j + 0.5) * Del * proj(i, j)
    for i in range(N_sys) for j in range(N_sys)
    if i != j
)
HL = liouvillian(H_sys) + sum(bath.terminator()[1] for bath in baths)

# Construct the solver (pass a list of baths):
solver = HEOMSolver(HL, baths, max_depth=max_depth, options=options)

# Run the solver:
rho0 = basis(N_sys, 0) * basis(N_sys, 0).dag()
tlist = np.linspace(0, 5, 200)
e_ops = {
    f"P{i}": proj(i, i)
    for i in range(N_sys)
}
result = solver.run(rho0, tlist, e_ops=e_ops)

# Plot populations:
fig, axes = plt.subplots(1, 1, sharex=True, figsize=(8,8))
for label, values in result.e_data.items():
    axes.plot(result.times, values, label=label)
axes.set_xlabel(r't', fontsize=28)
axes.set_ylabel(r"Population", fontsize=28)
axes.legend(loc=0, fontsize=12)
```



3.6.8 Fermionic Environments

Here we model a single fermion coupled to two electronic leads or reservoirs (e.g., this can describe a single quantum dot, a molecular transistor, etc). The system hamiltonian, H_{sys} , and bath spectral density, J_D , are

$$H_{sys} = c^\dagger c$$

$$J_D = \frac{\Gamma W^2}{(w - \mu)^2 + W^2},$$

We will demonstrate how to describe the bath using two different expansions of the spectral density correlation function (Matsubara's expansion and a Padé expansion), how to evolve the system in time, and how to calculate the steady state.

Since our fermion is coupled to two reservoirs, we will construct two baths – one for each reservoir or lead – and call them the left (L) and right (R) baths for convenience. Each bath will have a different chemical potential μ which we will label μ_L and μ_R .

First we will do this using the built-in implementations of the bath expansions, `LorentzianBath` and `LorentzianPadéBath`.

Afterwards, we will show how to calculate the bath expansion coefficients and to use those coefficients to construct your own bath description so that you can implement your own fermionic baths.

Our implementation of fermionic baths primarily follows the definitions used by Christian Schinabeck in his dissertation (<https://opus4.kobv.de/opus4-fau/files/10984/DissertationChristianSchinabeck.pdf>) and related publications.

A notebook containing a complete example similar to this one implemented in BoFiN can be found in [example notebook 4b](#).

Describing the system and bath

First, let us construct the system Hamiltonian, H_{sys} , and the initial system state, ρ_0 :

```
from qutip import basis, destroy

# The system Hamiltonian:
e1 = 1. # site energy
H_sys = e1 * destroy(2).dag() * destroy(2)

# Initial state of the system:
rho0 = basis(2,0) * basis(2,0).dag()
```

Now let us describe the bath properties:

```
# Shared bath properties:
gamma = 0.01 # coupling strength
W = 1.0 # cut-off
T = 0.025851991 # temperature
beta = 1. / T

# Chemical potentials for the two baths:
mu_L = 1.
mu_R = -1.

# System-bath coupling operator:
Q = destroy(2)
```

where Γ (gamma), W and T are the parameters of an Lorentzian bath, μ_L (mu_L) and μ_R (mu_R) are the chemical potentials of the left and right baths, and Q is the coupling operator between the system and the baths.

We may pass these parameters to either `LorentzianBath` or `LorentzianPadeBath` to construct an expansion of the bath correlations:

```
from qutip.solver.heom import LorentzianBath
from qutip.solver.heom import LorentzianPadeBath

# Number of expansion terms to retain:
Nk = 2

# Matsubara expansion:
bath_L = LorentzianBath(Q, gamma, W, mu_L, T, Nk, tag="L")
bath_R = LorentzianBath(Q, gamma, W, mu_R, T, Nk, tag="R")

# Padé expansion:
bath_L = LorentzianPadeBath(Q, gamma, W, mu_L, T, Nk, tag="L")
bath_R = LorentzianPadeBath(Q, gamma, W, mu_R, T, Nk, tag="R")
```

Where N_k is the number of terms to retain within the expansion of the bath.

Note that we have labelled each bath with a tag (either “L” or “R”) so that we can identify the exponents from individual baths later when calculating the currents between the system and the bath.

System and bath dynamics

Now we are ready to construct a solver:

```
from qutip.solver.heom import HEOMSolver

max_depth = 5 # maximum hierarchy depth to retain
options = {"nsteps": 15_000}
baths = [bath_L, bath_R]

solver = HEOMSolver(H_sys, baths, max_depth=max_depth, options=options)
```

and to calculate the system evolution as a function of time:

```
tlist = [0, 10, 20] # times to evaluate the system state at
result = solver.run(rho0, tlist)
```

As in the bosonic case, the `max_depth` parameter determines how many levels of the hierarchy to retain.


As in the bosonic case, we can specify `e_ops` in order to retrieve the expectation values of operators at each given time. See [System and bath dynamics](#) for a fuller description of the returned `result` object.

Below we run the solver again, but use `e_ops` to store the expectation values of the population of the system states:

```
# Define the operators that measure the populations of the two
# system states:
P11p = basis(2,0) * basis(2,0).dag()
P22p = basis(2,1) * basis(2,1).dag()

# Run the solver:
tlist = np.linspace(0, 500, 101)
result = solver.run(rho0, tlist, e_ops={"11": P11p, "22": P22p})

# Plot the results:
fig, axes = plt.subplots(1, 1, sharex=True, figsize=(8,8))
axes.plot(result.times, result.e_data["11"], 'b', linewidth=2, label="P11")
axes.plot(result.times, result.e_data["22"], 'r', linewidth=2, label="P22")
axes.set_xlabel(r't', fontsize=28)
axes.legend(loc=0, fontsize=12)
```



The plot above is not very exciting. What we would really like to see in this case are the currents between the system and the two baths. We will plot these in the next section using the auxiliary density operators (ADOs) returned by the solver.

Determining currents

The currents between the system and a fermionic bath may be calculated from the first level auxiliary density operators (ADOs) associated with the exponents of that bath.

The contribution to the current into a given bath from each exponent in that bath is:

$$\text{Contribution from Exponent} = \pm i \text{Tr}(Q^\pm \cdot A)$$

where the \pm sign is the sign of the exponent (see the description later in *Padé expansion coefficients*) and Q^\pm is Q for + exponents and Q^\dagger for - exponents.

The first-level exponents for the left bath are retrieved by calling `.filter(tags=["L"])` on `ado_state` which is an instance of `HierarchyADOsState` and also provides access to the methods of `HierarchyADOs` which describes the structure of the hierarchy for a given problem.

Here the tag “L” matches the tag passed when constructing `bath_L` earlier in this example.

Similarly, we may calculate the current to the right bath from the exponents tagged with “R”.

```
def exp_current(aux, exp):
    """ Calculate the current for a single exponent. """
    sign = 1 if exp.type == exp.types["+"] else -1
    op = exp.Q if exp.type == exp.types["+"] else exp.Q.dag()
    return 1j * sign * (op * aux).tr()


def heom_current(tag, ado_state):
    """ Calculate the current between the system and the given bath. """
    level_1_ados = [
        (ado_state.extract(label), ado_state.exps(label)[0])
        for label in ado_state.filter(tags=[tag])
    ]
    return np.real(sum(exp_current(aux, exp) for aux, exp in level_1_ados))

heom_left_current = lambda t, ado_state: heom_current("L", ado_state)
heom_right_current = lambda t, ado_state: heom_current("R", ado_state)
```

Once we have defined functions for retrieving the currents for the baths, we can pass them to `e_ops` and plot the results:

```
# Run the solver (returning ADO states):
tlist = np.linspace(0, 100, 201)
result = solver.run(rho0, tlist, e_ops={
    "left_currents": heom_left_current,
    "right_currents": heom_right_current,
})

# Plot the results:
fig, axes = plt.subplots(1, 1, sharex=True, figsize=(8,8))
axes.plot(
    result.times, result.e_data["left_currents"], 'b',
    linewidth=2, label=r"Bath L",
)
axes.plot(
    result.times, result.e_data["right_currents"], 'r',
    linewidth=2, label="Bath R",
)
axes.set_xlabel(r't', fontsize=28)
axes.set_ylabel(r'Current', fontsize=20)
axes.set_title(r'System to Bath Currents', fontsize=20)
axes.legend(loc=0, fontsize=12)
```



And now we have a more interesting plot that shows the currents to the left and right baths decaying towards their steady states!

In the next section, we will calculate the steady state currents directly.

Steady state currents

Using the same solver, we can also determine the steady state of the combined system and bath using:


```
steady_state, steady_ados = solver.steady_state()
```

and calculate the steady state currents to the two baths from `steady_ados` using the same `heom_current` function we defined previously:

```
steady_state_current_left = heom_current("L", steady_ados)
steady_state_current_right = heom_current("R", steady_ados)
```

Now we can add the steady state currents to the previous plot:

```
# Plot the results and steady state currents:
fig, axes = plt.subplots(1, 1, sharex=True, figsize=(8,8))
axes.plot(
    result.times, result.e_data["left_currents"], 'b',
    linewidth=2, label=r"Bath L",
)
axes.plot(
    result.times, [steady_state_current_left] * len(result.times), 'b:',
    linewidth=2, label=r"Bath L (steady state)",
)
axes.plot(
    result.times, result.e_data["right_currents"], 'r',
    linewidth=2, label="Bath R",
)
axes.plot(
    result.times, [steady_state_current_right] * len(result.times), 'r:',
    linewidth=2, label=r"Bath R (steady state)",
)
axes.set_xlabel(r't', fontsize=28)
axes.set_ylabel(r'Current', fontsize=20)
axes.set_title(r'System to Bath Currents (with steady states)', fontsize=20)
axes.legend(loc=0, fontsize=12)
```



As you can see, there is still some way to go beyond $t = 100$ before the steady state is reached!

Padé expansion coefficients

We now look at how to calculate the correlation expansion coefficients for the Lorentzian spectral density ourselves. Once we have calculated the coefficients we can construct a *FermionicBath* directly from them. A similar procedure can be used to apply *HEOMSolver* to any fermionic bath for which we can calculate the expansion coefficients.

In the fermionic case we must discriminate between the order in which excitations are created within the bath, so we define two different correlation functions, $C_+(t)$, and $C_-(t)$:

$$C^\sigma(t) = \frac{1}{2\pi} \int_{-\infty}^{\infty} d\omega e^{i\omega t} J(\omega) f_F[\sigma\beta(\omega - \mu)]$$

where σ is either $+$ or $-$ and, f_F is the Fermi distribution function, and $J(\omega)$ is the Lorentzian spectral density we defined at the start.

The Fermi distribution function is:

$$f_F(x) = (\exp(x) + 1)^{-1}$$

As in the bosonic case we can approximate this integral with a Matsubara or Padé expansion. For the Lorentzian bath the Padé expansion converges much more quickly, so we will calculate the Padé expansion coefficients here.

The Padé decomposition approximates the Fermi distribution as:

$$f_F(x) \approx f_F^{\text{approx}}(x) = \frac{1}{2} - \sum_{l=0}^{Nk} \frac{2k_l x}{x^2 + \epsilon_l^2}$$

where k_l and ϵ_l are coefficients defined in J. Chem Phys 133, “Efficient on the fly calculation of time correlation functions in computer simulations”, and Nk specifies the cut-off in the expansion.

Evaluating the integral for the correlation functions gives:

$$C^\sigma(t) \approx \sum_{l=0}^{Nk} \eta^{\sigma,l} e^{-\gamma_{\sigma,l} t}$$

where:

$$\eta_{\sigma,l} = \begin{cases} \frac{\Gamma W}{2} f_F^{\text{approx}}(i\beta W) & l = 0 \\ -i \cdot \frac{k_l}{\beta} \cdot \frac{\Gamma W^2}{-\frac{\epsilon_l^2}{\beta^2} + W^2} & l \neq 0 \end{cases}$$

$$\gamma_{\sigma,l} = \begin{cases} W - \sigma i\mu & l = 0 \\ \frac{\epsilon_l}{\beta} - \sigma i\mu & l \neq 0 \end{cases}$$

and $\beta = \frac{1}{T}$.

And now we calculate the same numbers in Python:

```
# Imports
from numpy.linalg import eigvalsh

# Convenience functions and parameters:
def deltafun(j, k):
    """ Kronecker delta function. """
    return 1.0 if j == k else 0.

def f_approx(x, Nk):
    """ Padé approximation to Fermi distribution. """
    f = 0.5
    for ll in range(1, Nk + 1):
        # kappa and epsilon are calculated further down
        f = f - 2 * kappa[ll] * x / (x**2 + epsilon[ll]**2)
    return f

def kappa_epsilon(Nk):
    """ Calculate kappa and epsilon coefficients. """

    alpha = np.zeros((2 * Nk, 2 * Nk))
    for j in range(2 * Nk):
        for k in range(2 * Nk):
            alpha[j][k] = (
                (deltafun(j, k + 1) + deltafun(j, k - 1))
                / np.sqrt((2 * (j + 1) - 1) * (2 * (k + 1) - 1))
            )

    eps = [-2. / val for val in eigvalsh(alpha)[:Nk]]

    alpha_p = np.zeros((2 * Nk - 1, 2 * Nk - 1))
    for j in range(2 * Nk - 1):
        for k in range(2 * Nk - 1):
            alpha_p[j][k] = (
```

(continues on next page)

(continued from previous page)

```

        (deltafun(j, k + 1) + deltafun(j, k - 1))
        / np.sqrt((2 * (j + 1) + 1) * (2 * (k + 1) + 1))
    )

chi = [-2. / val for val in eigvalsh(alpha_p)[:Nk - 1]]

eta_list = [
    0.5 * Nk * (2 * (Nk + 1) - 1) * (
        np.prod([chi[k]**2 - eps[j]**2 for k in range(Nk - 1)]) /
        np.prod([
            eps[k]**2 - eps[j]**2 + deltafun(j, k) for k in range(Nk)
        ])
    )
    for j in range(Nk)
]

kappa = [0] + eta_list
epsilon = [0] + eps

return kappa, epsilon

kappa, epsilon = kappa_epsilon(Nk)

# Phew, we made it to function that calculates the coefficients for the
# correlation function expansions:

def C(sigma, mu, Nk):
    """ Calculate the expansion coefficients for C_\sigma. """
    beta = 1. / T
    ck = [0.5 * gamma * W * f_approx(1.0j * beta * W, Nk)]
    vk = [W - sigma * 1.0j * mu]
    for ll in range(1, Nk + 1):
        ck.append(
            -1.0j * (kappa[ll] / beta) * gamma * W**2
            / (-(epsilon[ll]**2 / beta**2) + W**2)
        )
        vk.append(epsilon[ll] / beta - sigma * 1.0j * mu)
    return ck, vk

ck_plus_L, vk_plus_L = C(1.0, mu_L, Nk) # C_+, left bath
ck_minus_L, vk_minus_L = C(-1.0, mu_L, Nk) # C_-, left bath

ck_plus_R, vk_plus_R = C(1.0, mu_R, Nk) # C_+, right bath
ck_minus_R, vk_minus_R = C(-1.0, mu_R, Nk) # C_-, right bath

```

Finally we are ready to construct the *FermionicBath*:

```

from qutip.solver.heom import FermionicBath

# Pad  expansion:
bath_L = FermionicBath(Q, ck_plus_L, vk_plus_L, ck_minus_L, vk_minus_L)
bath_R = FermionicBath(Q, ck_plus_R, vk_plus_R, ck_minus_R, vk_minus_R)

```

And we're done!

The *FermionicBath* can be used with the *HEOMSolver* in exactly the same way as the baths we constructed previously using the built-in Lorentzian bath expansions.

3.6.9 Previous implementations

The current HEOM implementation in QuTiP is the latest in a succession of HEOM implementations by various contributors:

HSolverDL

The original HEOM solver was implemented by Neill Lambert, Anubhav Vardhan, and Alexander Pitchford. In QuTiP 4.7 it was still available as `qutip.solve.nonmarkov.dlheom_solver.HSolverDL` but the legacy implementation was removed in QuTiP 5.

It only directly provided support for the Drude-Lorentz bath although there was the possibility of sub-classing the solver to implement other baths.

A compatible interface using the current implementation is still available under the same name in `qutip.solver.heom.HSolverDL`.

BoFiN-HEOM

BoFiN-HEOM (the bosonic and fermionic HEOM solver) was a much more flexible re-write of the original QuTiP `HSolverDL` that added support for both bosonic and fermionic baths and for baths to be specified directly via their correlation function expansion coefficients. Its authors were Neill Lambert, Tarun Raheja, Shahnawaz Ahmed, and Alexander Pitchford.

BoFiN was written outside of QuTiP and is can still be found in its original repository at <https://github.com/tehruhn/bofin>.

The construction of the right-hand side matrix for BoFiN was slow, so BoFiN-fast, a hybrid C++ and Python implementation, was written that performed the right-hand side construction in C++. It was otherwise identical to the pure Python version. BoFiN-fast can be found at https://github.com/tehruhn/bofin_fast.

BoFiN also came with an extensive set of example notebooks that are available at <https://github.com/tehruhn/bofin/tree/main/examples>.

Current implementation

The current implementation is a rewrite of BoFiN in pure Python. It's right-hand side construction has similar speed to BoFiN-fast, but is written in pure Python. Built-in implementations of a variety of different baths are provided, and a single solver is used for both fermionic and bosonic baths. Multiple baths of the same kind (either fermionic or bosonic) may be specified in a single problem, and there is good support for working with the auxiliary density operator (ADO) state and extracting information from it.

The code was written by Neill Lambert and Simon Cross.

3.6.10 References

3.7 Solving for Steady-State Solutions

3.7.1 Introduction

For time-independent open quantum systems with decay rates larger than the corresponding excitation rates, the system will tend toward a steady state as $t \rightarrow \infty$ that satisfies the equation

$$\frac{d\hat{\rho}_{ss}}{dt} = \mathcal{L}\hat{\rho}_{ss} = 0.$$

Although the requirement for time-independence seems quite restrictive, one can often employ a transformation to the interaction picture that yields a time-independent Hamiltonian. For many these systems, solving for the asymptotic density matrix $\hat{\rho}_{ss}$ can be achieved using direct or iterative solution methods faster than using master equation or Monte Carlo simulations. Although the steady state equation has a simple mathematical form, the properties of the Liouvillian operator are such that the solutions to this equation are anything but straightforward to find.

3.7.2 Steady State solvers in QuTiP

In QuTiP, the steady-state solution for a system Hamiltonian or Liouvillian is given by `qutip.steadystate.steadystate`. This function implements a number of different methods for finding the steady state, each with their own pros and cons, where the method used can be chosen using the `method` keyword argument.

Method	Keyword	Description
Direct (default)	'direct'	Direct solution solving $Ax = b$.
Eigenvalue	'eigen'	Iteratively find the zero eigenvalue of \mathcal{L} .
Inverse-Power	'power'	Solve using the inverse-power method.
SVD	'svd'	Steady-state solution via the dense SVD of the Liouvillian.

The function `qutip.steadystate` can take either a Hamiltonian and a list of collapse operators as input, generating internally the corresponding Liouvillian super operator in Lindblad form, or alternatively, a Liouvillian passed by the user.

Both the "direct" and "power" method need to solve a linear equation system. To do so, there are multiple solvers available: ``

Solver	Original function	Description
"solve"	<code>numpy.linalg.solve</code>	Dense solver from numpy.
"lstsq"	<code>numpy.linalg.lstsq</code>	Dense least-squares solver.
"spsolve"	<code>scipy.sparse.linalg.spsolve</code>	Sparse solver from scipy.
"gmres"	<code>scipy.sparse.linalg.gmres</code>	Generalized Minimal RESidual iterative solver.
"lgmres"	<code>scipy.sparse.linalg.lgmres</code>	LGMRES iterative solver.
"bicgstab"	<code>scipy.sparse.linalg.bicgstab</code>	BIConjugate Gradient STABilized iterative solver.
"mkl_spsolve"	<code>pardiso</code>	Intel Pardiso LU solver from MKL

QuTiP can take advantage of the Intel Pardiso LU solver in the Intel Math Kernel library that comes with the Anaconda (2.5+) and Intel Python distributions. This gives a substantial increase in performance compared with the standard SuperLU method used by SciPy. To verify that QuTiP can find the necessary libraries, one can check for INTEL MKL Ext: `True` in the QuTiP about box ([qutip.about](#)).

3.7.3 Using the Steadystate Solver

Solving for the steady state solution to the Lindblad master equation for a general system with `qutip.steadystate` can be accomplished using:

```
>>> rho_ss = steadystate(H, c_ops)
```

where `H` is a quantum object representing the system Hamiltonian, and `c_ops` is a list of quantum objects for the system collapse operators. The output, labelled as `rho_ss`, is the steady-state solution for the systems. If no other keywords are passed to the solver, the default 'direct' method is used with `numpy.linalg.solve`, generating a solution that is exact to machine precision at the expense of a large memory requirement. However Liouvillians are often quite sparse and using a sparse solver may be preferred:

```
rho_ss = steadystate(H, c_ops, method="power", solver="spsolve")
```

where `method='power'` indicates that we are using the inverse-power solution method, and `solver="spsolve"` indicate to use the sparse solver.

Sparse solvers may still use quite a large amount of memory when they factorize the matrix since the Liouvillian usually has a large bandwidth. To address this, `qutip.steadystate` allows one to use the bandwidth minimization algorithms listed in [Additional Solver Arguments](#). For example:

```
rho_ss = steadystate(H, c_ops, solver="spsolve", use_rcm=True)
```

where `use_rcm=True` turns on a bandwidth minimization routine.

Although it is not obvious, the 'direct', 'eigen', and 'power' methods all use an LU decomposition internally and thus can have a large memory overhead. In contrast, iterative solvers such as the 'gmres', 'lgmres', and 'bicgstab' do not factor the matrix and thus take less memory than the LU methods and allow, in principle, for extremely large system sizes. The downside is that these methods can take much longer than the direct method as the condition number of the Liouvillian matrix is large, indicating that these iterative methods require a large number of iterations for convergence. To overcome this, one can use a preconditioner M that solves for an approximate inverse for the (modified) Liouvillian, thus better conditioning the problem, leading to faster convergence. The use of a preconditioner can actually make these iterative methods faster than the other solution methods. The problem with preconditioning is that it is only well defined for Hermitian matrices. Since the Liouvillian is non-Hermitian, the ability to find a good preconditioner is not guaranteed. And moreover, if a preconditioner is found, it is not guaranteed to have a good condition number. QuTiP can make use of an incomplete LU preconditioner when using the iterative 'gmres', 'lgmres', and 'bicgstab' solvers by setting `use_precond=True`. The preconditioner optionally makes use of a combination of symmetric and anti-symmetric matrix permutations that attempt to improve the preconditioning process. These features are discussed in the [Additional Solver Arguments](#) section. Even with these state-of-the-art permutations, the generation of a successful preconditioner for non-symmetric matrices is currently a trial-and-error process due to the lack of mathematical work done in this area. It is always recommended to begin with the direct solver with no additional arguments before selecting a different method.

Finding the steady-state solution is not limited to the Lindblad form of the master equation. Any time-independent Liouvillian constructed from a Hamiltonian and collapse operators can be used as an input:

```
>>> rho_ss = steadystate(L)
```

where `L` is the Liouvillian. All of the additional arguments can also be used in this case.

3.7.4 Additional Solver Arguments

The following additional solver arguments are available for the steady-state solver:

Key-word	Default	Description
weight	None	Set the weighting factor used in the 'direct' method.
use_precond	False	Generate a preconditioner when using the 'gmres' and 'lgmres' methods.
use_rcm	False	Use a Reverse Cuthill-McKee reordering to minimize the bandwidth of the modified Liouvillian used in the LU decomposition.
use_wbm	False	Use a Weighted Bipartite Matching algorithm to attempt to make the modified Liouvillian more diagonally dominant, and thus for favorable for preconditioning.
power_tol	1e-12	Tolerance for the solution when using the 'power' method.
power_maxiter	10	Maximum number of iterations of the power method.
power_eps	1e-15	Small weight used in the "power" method.
**kwargs	{}	Options to pass through the linalg solvers. See the corresponding documentation from scipy for a full list.

Further information can be found in the `qutip.steadystate` docstrings.

3.7.5 Example: Harmonic Oscillator in Thermal Bath

A simple example of a system that reaches a steady state is a harmonic oscillator coupled to a thermal environment. Below we consider a harmonic oscillator, initially in the $|10\rangle$ number state, and weakly coupled to a thermal environment characterized by an average particle expectation value of $\langle n \rangle = 2$. We calculate the evolution via master equation and Monte Carlo methods, and see that they converge to the steady-state solution. Here we choose to perform only a few Monte Carlo trajectories so we can distinguish this evolution from the master-equation solution.

```
import numpy as np
import matplotlib.pyplot as plt

import qutip

# Define paramters
N = 20 # number of basis states to consider
a = qutip.destroy(N)
H = a.dag() * a
psi0 = qutip.basis(N, 10) # initial state
kappa = 0.1 # coupling to oscillator

# collapse operators
c_op_list = []
n_th_a = 2 # temperature with average of 2 excitations
rate = kappa * (1 + n_th_a)
if rate > 0.0:
    c_op_list.append(np.sqrt(rate) * a) # decay operators
rate = kappa * n_th_a
if rate > 0.0:
    c_op_list.append(np.sqrt(rate) * a.dag()) # excitation operators

# find steady-state solution
final_state = qutip.steadystate(H, c_op_list)
# find expectation value for particle number in steady state
fexpt = qutip.expect(a.dag() * a, final_state)
```

(continues on next page)


(continued from previous page)

```

tlist = np.linspace(0, 50, 100)
# monte-carlo
mcdata = qutip.mcsolve(H, psi0, tlist, c_op_list, [a.dag() * a], ntraj=100)
# master eq.
medata = qutip.mesolve(H, psi0, tlist, c_op_list, [a.dag() * a])

plt.plot(tlist, mcdata.expect[0], tlist, medata.expect[0], lw=2)
# plot steady-state expt. value as horizontal line (should be = 2)
plt.axhline(y=fexpt, color='r', lw=1.5)
plt.ylim([0, 10])
plt.xlabel('Time', fontsize=14)
plt.ylabel('Number of excitations', fontsize=14)
plt.legend(('Monte-Carlo', 'Master Equation', 'Steady State'))
plt.title(
    r'Decay of Fock state  $|\left|10\right\rangle$  in a thermal environment with  $\langle n \rangle = 2$ '
)
plt.show()

```



3.8 Two-time correlation functions

With the QuTiP time-evolution functions (for example `qutip.mesolve` and `qutip.mcsolve`), a state vector or density matrix can be evolved from an initial state at t_0 to an arbitrary time t , $\rho(t) = V(t, t_0) \{\rho(t_0)\}$, where $V(t, t_0)$ is the propagator defined by the equation of motion. The resulting density matrix can then be used to evaluate the expectation values of arbitrary combinations of *same-time* operators.

To calculate *two-time* correlation functions on the form $\langle A(t + \tau)B(t) \rangle$, we can use the quantum regression theorem (see, e.g., [Gar03]) to write

$$\langle A(t + \tau)B(t) \rangle = \text{Tr}[AV(t + \tau, t) \{B\rho(t)\}] = \text{Tr}[AV(t + \tau, t) \{BV(t, 0) \{\rho(0)\}\}]$$

We therefore first calculate $\rho(t) = V(t, 0) \{\rho(0)\}$ using one of the QuTiP evolution solvers with $\rho(0)$ as initial state, and then again use the same solver to calculate $V(t + \tau, t) \{B\rho(t)\}$ using $B\rho(t)$ as initial state.

Note that if the initial state is the steady state, then $\rho(t) = V(t, 0) \{\rho_{ss}\} = \rho_{ss}$ and

$$\langle A(t + \tau)B(t) \rangle = \text{Tr}[AV(t + \tau, t) \{B\rho_{ss}\}] = \text{Tr}[AV(\tau, 0) \{B\rho_{ss}\}] = \langle A(\tau)B(0) \rangle,$$

which is independent of t , so that we only have one time coordinate τ .

QuTiP provides a family of functions that assists in the process of calculating two-time correlation functions. The available functions and their usage is shown in the table below. Each of these functions can use one of the following evolution solvers: Master-equation, Exponential series and the Monte-Carlo. The choice of solver is defined by the optional argument `solver`.

QuTiP function	Correlation function
<code>qutip.correlation_2op_2t</code>	$\langle A(t + \tau)B(t) \rangle$ or $\langle A(t)B(t + \tau) \rangle$.
<code>qutip.correlation_2op_1t</code>	$\langle A(\tau)B(0) \rangle$ or $\langle A(0)B(\tau) \rangle$.
<code>qutip.correlation_3op_1t</code>	$\langle A(0)B(\tau)C(0) \rangle$.
<code>qutip.correlation_3op_2t</code>	$\langle A(t)B(t + \tau)C(t) \rangle$.
<code>qutip.correlation_3op</code>	$\langle A(t)B(t + \tau)C(t) \rangle$.

The most common use-case is to calculate the two time correlation function $\langle A(\tau)B(0) \rangle$. `qutip.correlation_2op_1t` performs this task with sensible default values, but only allows using the `mesolve` solver. From QuTiP 5.0 we added `qutip.correlation_3op`. This function can also calculate correlation functions with two or three operators and with one or two times. Most importantly, this function accepts alternative solvers such as `brmesolve`.


3.8.1 Steadystate correlation function


The following code demonstrates how to calculate the $\langle x(t)x(0) \rangle$ correlation for a leaky cavity with three different relaxation rates.

```
times = np.linspace(0, 10.0, 200)
a = destroy(10)
x = a.dag() + a
H = a.dag() * a

corr1 = correlation_2op_1t(H, None, times, [np.sqrt(0.5) * a], x, x)
corr2 = correlation_2op_1t(H, None, times, [np.sqrt(1.0) * a], x, x)
corr3 = correlation_2op_1t(H, None, times, [np.sqrt(2.0) * a], x, x)

plt.figure()
plt.plot(times, np.real(corr1), times, np.real(corr2), times, np.real(corr3))
plt.legend(['0.5', '1.0', '2.0'])
plt.xlabel(r'Time $t$')
plt.ylabel(r'Correlation $\langle x(t)x(0) \rangle$')
plt.show()
```





3.8.2 Emission spectrum

Given a correlation function $\langle A(\tau)B(0) \rangle$ we can define the corresponding power spectrum as

$$S(\omega) = \int_{-\infty}^{\infty} \langle A(\tau)B(0) \rangle e^{-i\omega\tau} d\tau.$$

In QuTiP, we can calculate $S(\omega)$ using either `qutip.correlation.spectrum_ss`, which first calculates the correlation function using one of the time-dependent solvers and then performs the Fourier transform semi-analytically, or we can use the function `qutip.correlation.spectrum_correlation_fft` to numerically calculate the Fourier transform of a given correlation data using FFT.

The following example demonstrates how these two functions can be used to obtain the emission power spectrum.

```
import numpy as np
from matplotlib import pyplot
import qutip

N = 4                                # number of cavity fock states
wc = wa = 1.0 * 2 * np.pi          # cavity and atom frequency
g = 0.1 * 2 * np.pi                 # coupling strength
kappa = 0.75                         # cavity dissipation rate
gamma = 0.25                         # atom dissipation rate

# Jaynes-Cummings Hamiltonian
a = qutip.tensor(qutip.destroy(N), qutip.qeye(2))
sm = qutip.tensor(qutip.qeye(N), qutip.destroy(2))
H = wc*a.dag()*a + wa*sm.dag()*sm + g*(a.dag()*sm + a*sm.dag())

# collapse operators
```

(continues on next page)

(continued from previous page)


```

n_th = 0.25
c_ops = [
    np.sqrt(kappa * (1 + n_th)) * a,
    np.sqrt(kappa * n_th) * a.dag(),
    np.sqrt(gamma) * sm,
]

# calculate the correlation function using the mesolve solver, and then fft to
# obtain the spectrum. Here we need to make sure to evaluate the correlation
# function for a sufficient long time and sufficiently high sampling rate so
# that the discrete Fourier transform (FFT) captures all the features in the
# resulting spectrum.
tlist = np.linspace(0, 100, 5000)
corr = qutip.correlation_2op_1t(H, None, tlist, c_ops, a.dag(), a)
wlist1, spec1 = qutip.spectrum_correlation_fft(tlist, corr)

# calculate the power spectrum using spectrum, which internally uses essolve
# to solve for the dynamics (by default)
wlist2 = np.linspace(0.25, 1.75, 200) * 2 * np.pi
spec2 = qutip.spectrum(H, wlist2, c_ops, a.dag(), a)

# plot the spectra
fig, ax = pyplot.subplots(1, 1)
ax.plot(wlist1 / (2 * np.pi), spec1, 'b', lw=2, label='eseries method')
ax.plot(wlist2 / (2 * np.pi), spec2, 'r--', lw=2, label='me+fft method')
ax.legend()
ax.set_xlabel('Frequency')
ax.set_ylabel('Power spectrum')
ax.set_title('Vacuum Rabi splitting')
ax.set_xlim(wlist2[0] / (2 * np.pi), wlist2[-1] / (2 * np.pi))
plt.show()
    
```




3.8.3 Non-steadystate correlation function

More generally, we can also calculate correlation functions of the kind $\langle A(t_1 + t_2)B(t_1) \rangle$, i.e., the correlation function of a system that is not in its steady state. In QuTiP, we can evaluate such correlation functions using the function `qutip.correlation.correlation_2op_2t`. The default behavior of this function is to return a matrix with the correlations as a function of the two time coordinates (t_1 and t_2).

```
import numpy as np
import matplotlib.pyplot as plt
import qutip

times = np.linspace(0, 10.0, 200)
a = qutip.destroy(10)
x = a.dag() + a
H = a.dag() * a
alpha = 2.5
rho0 = qutip.coherent_dm(10, alpha)
corr = qutip.correlation_2op_2t(H, rho0, times, times, [np.sqrt(0.25) * a], x, x)

plt.pcolor(np.real(corr))
plt.xlabel(r'Time  $t_2$ ')
plt.ylabel(r'Time  $t_1$ ')
plt.title(r'Correlation  $\langle x(t)x(0) \rangle$ ')
plt.show()
```



However, in some cases we might be interested in the correlation functions on the form $\langle A(t_1 + t_2)B(t_1) \rangle$, but only as a function of time coordinate t_2 . In this case we can also use the `qutip.correlation.correlation_2op_2t` function, if we pass the density matrix at time t_1 as second argument, and `None` as third argument. The `qutip.correlation.correlation_2op_2t` function then returns a vector with the correlation values corresponding to the times in *taulist* (the fourth argument).

Example: first-order optical coherence function

This example demonstrates how to calculate a correlation function on the form $\langle A(\tau)B(0) \rangle$ for a non-steady initial state. Consider an oscillator that is interacting with a thermal environment. If the oscillator initially is in a coherent state, it will gradually decay to a thermal (incoherent) state. The amount of coherence can be quantified using the first-order optical coherence function $g^{(1)}(\tau) = \frac{\langle a^\dagger(\tau)a(0) \rangle}{\sqrt{\langle a^\dagger(\tau)a(\tau) \rangle \langle a^\dagger(0)a(0) \rangle}}$. For a coherent state $|g^{(1)}(\tau)| = 1$, and for a completely incoherent (thermal) state $g^{(1)}(\tau) = 0$. The following code calculates and plots $g^{(1)}(\tau)$ as a function of τ .

```
import numpy as np
import matplotlib.pyplot as plt
import qutip

N = 15
taus = np.linspace(0, 10.0, 200)
a = qutip.destroy(N)
H = 2 * np.pi * a.dag() * a


# collapse operator
G1 = 0.75
n_th = 2.00 # bath temperature in terms of excitation number
c_ops = [np.sqrt(G1 * (1 + n_th)) * a, np.sqrt(G1 * n_th) * a.dag()]

# start with a coherent state
rho0 = qutip.coherent_dm(N, 2.0)

# first calculate the occupation number as a function of time
n = qutip.mesolve(H, rho0, taus, c_ops, [a.dag() * a]).expect[0]

# calculate the correlation function G1 and normalize with n to obtain g1
G1 = qutip.correlation_2op_1t(H, rho0, taus, c_ops, a.dag(), a)
g1 = np.array(G1) / np.sqrt(n[0] * np.array(n))

plt.plot(taus, np.real(g1), 'b', lw=2)
plt.plot(taus, n, 'r', lw=2)
plt.title('Decay of a coherent state to an incoherent (thermal) state')
plt.xlabel(r'$\tau$')
plt.legend([
    r'First-order coherence function $g^{(1)}(\tau)$',
    r'Occupation number $n(\tau)$',
])
plt.show()
```



For convenience, the steps for calculating the first-order coherence function have been collected in the function `qutip.correlation.coherence_function_g1`.

Example: second-order optical coherence function

The second-order optical coherence function, with time-delay τ , is defined as

$$g^{(2)}(\tau) = \frac{\langle a^\dagger(0)a^\dagger(\tau)a(\tau)a(0) \rangle}{\langle a^\dagger(0)a(0) \rangle^2}$$

For a coherent state $g^{(2)}(\tau) = 1$, for a thermal state $g^{(2)}(\tau = 0) = 2$ and it decreases as a function of time (bunched photons, they tend to appear together), and for a Fock state with n photons $g^{(2)}(\tau = 0) = n(n-1)/n^2 < 1$ and it increases with time (anti-bunched photons, more likely to arrive separated in time).

To calculate this type of correlation function with QuTiP, we can use `qutip.correlation.correlation_3op_1t`, which computes a correlation function on the form $\langle A(0)B(\tau)C(0) \rangle$ (three operators, one delay-time vector). We first have to combine the central two operators into one single one as they are evaluated at the same time, e.g. here we do $a^\dagger(\tau)a(\tau) = (a^\dagger a)(\tau)$.

The following code calculates and plots $g^{(2)}(\tau)$ as a function of τ for a coherent, thermal and Fock state.

```
import numpy as np
import matplotlib.pyplot as plt
import qutip

N = 25
taus = np.linspace(0, 25.0, 200)
a = qutip.destroy(N)
H = 2 * np.pi * a.dag() * a

kappa = 0.25
n_th = 2.0 # bath temperature in terms of excitation number
c_ops = [np.sqrt(kappa * (1 + n_th)) * a, np.sqrt(kappa * n_th) * a.dag()]

states = [
```

(continues on next page)

(continued from previous page)

```

    {'state': qutip.coherent_dm(N, np.sqrt(2)), 'label': "coherent state"},
    {'state': qutip.thermal_dm(N, 2), 'label': "thermal state"},
    {'state': qutip.fock_dm(N, 2), 'label': "Fock state"},
]

fig, ax = plt.subplots(1, 1)

for state in states:
    rho0 = state['state']


    # first calculate the occupation number as a function of time
    n = qutip.mesolve(H, rho0, taus, c_ops, [a.dag() * a]).expect[0]

    # calculate the correlation function G2 and normalize with n(0)n(t) to
    # obtain g2
    G2 = qutip.correlation_3op_1t(H, rho0, taus, c_ops, a.dag(), a.dag()*a, a)
    g2 = np.array(G2) / (n[0] * np.array(n))

    ax.plot(taus, np.real(g2), label=state['label'], lw=2)

ax.legend(loc=0)
ax.set_xlabel(r'$\tau$')
ax.set_ylabel(r'$g^{(2)}(\tau)$')
plt.show()

```



For convenience, the steps for calculating the second-order coherence function have been collected in the function `qutip.correlation.coherence_function_g2`.

3.9 Quantum Optimal Control

3.9.1 Introduction

In quantum control we look to prepare some specific state, effect some state-to-state transfer, or effect some transformation (or gate) on a quantum system. For a given quantum system there will always be factors that effect the dynamics that are outside of our control. As examples, the interactions between elements of the system or a magnetic field required to trap the system. However, there may be methods of affecting the dynamics in a controlled way, such as the time varying amplitude of the electric component of an interacting laser field. And so this leads to some questions; given a specific quantum system with known time-independent dynamics generator (referred to as the *drift* dynamics generators) and set of externally controllable fields for which the interaction can be described by *control* dynamics generators:

1. What states or transformations can we achieve (if any)?
2. What is the shape of the control pulse required to achieve this?

These questions are addressed as *controllability* and *quantum optimal control* [dAless08]. The answer to question of *controllability* is determined by the commutability of the dynamics generators and is formalised as the *Lie Algebra Rank Criterion* and is discussed in detail in [dAless08]. The solutions to the second question can be determined through optimal control algorithms, or control pulse optimisation.




Fig. 3: Schematic showing the principle of quantum control.

Quantum Control has many applications including NMR, *quantum metrology*, *control of chemical reactions*, and *quantum information processing*.

To explain the physics behind these algorithms we will first consider only finite-dimensional, closed quantum systems.

3.9.2 Closed Quantum Systems

In closed quantum systems the states can be represented by kets, and the transformations on these states are unitary operators. The dynamics generators are Hamiltonians. The combined Hamiltonian for the system is given by

$$H(t) = H_0 + \sum_{j=1} u_j(t) H_j$$

where H_0 is the drift Hamiltonian and the H_j are the control Hamiltonians. The u_j are time varying amplitude functions for the specific control.

The dynamics of the system are governed by *Schrödinger's equation*.

$$\frac{d}{dt} |\psi\rangle = -iH(t) |\psi\rangle$$

Note we use units where $\hbar = 1$ throughout. The solutions to Schrödinger's equation are of the form:

$$|\psi(t)\rangle = U(t) |\psi_0\rangle$$

where ψ_0 is the state of the system at $t = 0$ and $U(t)$ is a unitary operator on the Hilbert space containing the states. $U(t)$ is a solution to the *Schrödinger operator equation*

$$\frac{d}{dt}U = -iH(t)U, \quad U(0) = \mathbb{I}$$

We can use optimal control algorithms to determine a set of u_j that will drive our system from $|\psi_0\rangle$ to $|\psi_1\rangle$, this is state-to-state transfer, or drive the system from some arbitrary state to a given state $|\psi_1\rangle$, which is state preparation, or effect some unitary transformation U_{target} , called gate synthesis. The latter of these is most important in quantum computation.

3.9.3 The GRAPE algorithm

The **GR**radient **A**scent **P**ulse **E**ngineering was first proposed in [NKanej]. Solutions to Schrödinger's equation for a time-dependent Hamiltonian are not generally possible to obtain analytically. Therefore, a piecewise constant approximation to the pulse amplitudes is made. Time allowed for the system to evolve T is split into M timeslots (typically these are of equal duration), during which the control amplitude is assumed to remain constant. The combined Hamiltonian can then be approximated as:

$$H(t) \approx H(t_k) = H_0 + \sum_{j=1}^N u_{jk} H_j$$

where k is a timeslot index, j is the control index, and N is the number of controls. Hence t_k is the evolution time at the start of the timeslot, and u_{jk} is the amplitude of control j throughout timeslot k . The time evolution operator, or propagator, within the timeslot can then be calculated as:

$$X_k := e^{-iH(t_k)\Delta t_k}$$

where Δt_k is the duration of the timeslot. The evolution up to (and including) any timeslot k (including the full evolution $k = M$) can be calculated as

$$X(t_k) := X_k X_{k-1} \cdots X_1 X_0$$

If the objective is state-to-state transfer then $X_0 = |\psi_0\rangle$ and the target $X_{target} = |\psi_1\rangle$, for gate synthesis $X_0 = U(0) = \mathbb{I}$ and the target $X_{target} = U_{target}$.

A *figure of merit* or *fidelity* is some measure of how close the evolution is to the target, based on the control amplitudes in the timeslots. The typical figure of merit for unitary systems is the normalised overlap of the evolution and the target.

$$f_{PSU} = \frac{1}{d} |\text{tr}\{X_{target}^\dagger X(T)\}|$$

where d is the system dimension. In this figure of merit the absolute value is taken to ignore any differences in global phase, and $0 \leq f \leq 1$. Typically the fidelity error (or *infidelity*) is more useful, in this case defined as $\varepsilon = 1 - f_{PSU}$. There are many other possible objectives, and hence figures of merit.

As there are now $N \times M$ variables (the u_{jk}) and one parameter to minimise ε , then the problem becomes a finite multi-variable optimisation problem, for which there are many established methods, often referred to as 'hill-climbing' methods. The simplest of these to understand is that of steepest ascent (or descent). The gradient of the fidelity with respect to all the variables is calculated (or approximated) and a step is made in the variable space in the direction of steepest ascent (or descent). This method is a first order gradient method. In two dimensions this describes a method of climbing a hill by heading in the direction where the ground rises fastest. This analogy also clearly illustrates one of the main challenges in multi-variable optimisation, which is that all methods have a tendency to get stuck in local maxima. It is hard to determine whether one has found a global maximum or not - a local peak is likely not to be the highest mountain in the region. In quantum optimal control we can typically define an infidelity that has a lower bound of zero. We can then look to minimise the infidelity (from here on we will

only consider optimising for infidelity minima). This means that we can terminate any pulse optimisation when the infidelity reaches zero (to a sufficient precision). This is however only possible for fully controllable systems; otherwise it is hard (if not impossible) to know that the minimum possible infidelity has been achieved. In the hill walking analogy the step size is roughly fixed to a stride, however, in computations the step size must be chosen. Clearly there is a trade-off here between the number of steps (or iterations) required to reach the minima and the possibility that we might step over a minima. In practice it is difficult to determine an efficient and effective step size.

The second order differentials of the infidelity with respect to the variables can be used to approximate the local landscape to a parabola. This way a step (or jump) can be made to where the minima would be if it were parabolic. This typically vastly reduces the number of iterations, and removes the need to guess a step size. The method where all the second differentials are calculated explicitly is called the *Newton-Raphson* method. However, calculating the second-order differentials (the Hessian matrix) can be computationally expensive, and so there are a class of methods known as *quasi-Newton* that approximate the Hessian based on successive iterations. The most popular of these (in quantum optimal control) is the Broyden–Fletcher–Goldfarb–Shanno algorithm (BFGS). The default method in the QuTiP Qtrl GRAPE implementation is the L-BFGS-B method in Scipy, which is a wrapper to the implementation described in [Byrd95]. This limited memory and bounded method does not need to store the entire Hessian, which reduces the computer memory required, and allows bounds to be set for variable values, which considering these are field amplitudes is often physical.

The pulse optimisation is typically far more efficient if the gradients can be calculated exactly, rather than approximated. For simple fidelity measures such as f_{PSU} this is possible. Firstly the propagator gradient for each timeslot with respect to the control amplitudes is calculated. For closed systems, with unitary dynamics, a method using the eigendecomposition is used, which is efficient as it is also used in the propagator calculation (to exponentiate the combined Hamiltonian). More generally (for example open systems and symplectic dynamics) the Frechet derivative (or augmented matrix) method is used, which is described in [Flo12]. For other optimisation goals it may not be possible to calculate analytic gradients. In these cases it is necessary to approximate the gradients, but this can be very expensive, and can lead to other algorithms out-performing GRAPE.

3.9.4 The CRAB Algorithm

It has been shown [Lloyd14], the dimension of a quantum optimal control problem is a polynomial function of the dimension of the manifold of the time-polynomial reachable states, when allowing for a finite control precision and evolution time. You can think of this as the information content of the pulse (as being the only effective input) being very limited e.g. the pulse is compressible to a few bytes without losing the target.

This is where the **Chopped RAndom Basis** (CRAB) algorithm [Doria11], [Caneva11] comes into play: Since the pulse complexity is usually very low, it is sufficient to transform the optimal control problem to a few parameter search by introducing a physically motivated function basis that builds up the pulse. Compared to the number of time slices needed to accurately simulate quantum dynamics (often equals basis dimension for Gradient based algorithms), this number is lower by orders of magnitude, allowing CRAB to efficiently optimize smooth pulses with realistic experimental constraints. It is important to point out, that CRAB does not make any suggestion on the basis function to be used. The basis must be chosen carefully considered, taking into account a priori knowledge of the system (such as symmetries, magnitudes of scales,...) and solution (e.g. sign, smoothness, bang-bang behavior, singularities, maximum excursion or rate of change,...). By doing so, this algorithm allows for native integration of experimental constraints such as maximum frequencies allowed, maximum amplitude, smooth ramping up and down of the pulse and many more. Moreover initial guesses, if they are available, can (however not have to) be included to speed up convergence.

As mentioned in the GRAPE paragraph, for CRAB local minima arising from algorithmic design can occur, too. However, for CRAB a ‘dressed’ version has recently been introduced [Rach15] that allows to escape local minima.

For some control objectives and/or dynamical quantum descriptions, it is either not possible to derive the gradient for the cost functional with respect to each time slice or it is computationally expensive to do so. The same can apply for the necessary (reverse) propagation of the co-state. All this trouble does not occur within CRAB as those elements are not in use here. CRAB, instead, takes the time evolution as a black-box where the pulse goes as an input and the cost (e.g. infidelity) value will be returned as an output. This concept, on top, allows for direct integration in a closed loop experimental environment where both the preliminarily open loop optimization, as well as the final adoption, and integration to the lab (to account for modeling errors, experimental systematic noise, ...) can be done all in one, using this algorithm.

3.9.5 Optimal Quantum Control in QuTiP

There are two separate implementations of optimal control inside QuTiP. The first is an implementation of first order GRAPE, and is not further described here, but there are the example notebooks. The second is referred to as Qtrl (when a distinction needs to be made) as this was its name before it was integrated into QuTiP. Qtrl uses the Scipy optimize functions to perform the multi-variable optimisation, typically the L-BFGS-B method for GRAPE and Nelder-Mead for CRAB. The GRAPE implementation in Qtrl was initially based on the open-source package DYNAMO, which is a MATLAB implementation, and is described in [DYNAMO]. It has since been restructured and extended for flexibility and compatibility within QuTiP.

The rest of this section describes the Qtrl implementation and how to use it.

Object Model The Qtrl code is organised in a hierarchical object model in order to try and maximise configurability whilst maintaining some clarity. It is not necessary to understand the model in order to use the pulse optimisation functions, but it is the most flexible method of using Qtrl. If you just want to use a simple single function call interface, then jump to [Using the pulseoptim functions](#)




Fig. 4: Qtrl code object model.

The object's properties and methods are described in detail in the documentation, so that will not be repeated here.

OptimConfig The OptimConfig object is used simply to hold configuration parameters used by all the objects. Typically this is the subclass types for the other objects and parameters for the users specific requirements. The `loadparams` module can be used read parameter values from a configuration file.

Optimizer This acts as a wrapper to the `Scipy.optimize` functions that perform the work of the pulse optimisation algorithms. Using the main classes the user can specify which of the optimisation methods are to be used. There are subclasses specifically for the BFGS and L-BFGS-B methods. There is another subclass for using the CRAB algorithm.

Dynamics This is mainly a container for the lists that hold the dynamics generators, propagators, and time evolution operators in each timeslot. The combining of dynamics generators is also complete by this object. Different subclasses support a range of types of quantum systems, including closed systems with unitary dynamics, systems with quadratic Hamiltonians that have Gaussian states and symplectic transforms, and a general subclass that can be used for open system dynamics with Lindbladian operators.

PulseGen There are many subclasses of pulse generators that generate different types of pulses as the initial amplitudes for the optimisation. Often the goal cannot be achieved from all starting conditions, and then typically some kind of random pulse is used and repeated optimisations are performed until the desired infidelity is reached or the minimum infidelity found is reported. There is a specific subclass that is used by the CRAB algorithm to generate the pulses based on the basis coefficients that are being optimised.

TerminationConditions This is simply a convenient place to hold all the properties that will determine when the single optimisation run terminates. Limits can be set for number of iterations, time, and of course the target infidelity.

Stats Performance data are optionally collected during the optimisation. This object is shared to a single location to store, calculate and report run statistics.

FidelityComputer The subclass of the fidelity computer determines the type of fidelity measure. These are closely linked to the type of dynamics in use. These are also the most commonly user customised subclasses.

PropagatorComputer This object computes propagators from one timeslot to the next and also the propagator gradient. The options are using the spectral decomposition or Frechet derivative, as discussed above.

TimeslotComputer Here the time evolution is computed by calling the methods of the other computer objects.

OptimResult The result of a pulse optimisation run is returned as an object with properties for the outcome in terms of the infidelity, reason for termination, performance statistics, final evolution, and more.

3.9.6 Using the pulseoptim functions

The simplest method for optimising a control pulse is to call one of the functions in the `pulseoptim` module. This automates the creation and configuration of the necessary objects, generation of initial pulses, running the optimisation and returning the result. There are functions specifically for unitary dynamics, and also specifically for the CRAB algorithm (GRAPE is the default). The `optimise_pulse` function can in fact be used for unitary dynamics and / or the CRAB algorithm, the more specific functions simply have parameter names that are more familiar in that application.

A semi-automated method is to use the `create_optimizer_objects` function to generate and configure all the objects, then manually set the initial pulse and call the optimisation. This would be more efficient when repeating runs with different starting conditions.

3.10 Plotting on the Bloch Sphere


3.10.1 Introduction

When studying the dynamics of a two-level system, it is often convenient to visualize the state of the system by plotting the state-vector or density matrix on the Bloch sphere. In QuTiP, we have created two different classes to allow for easy creation and manipulation of data sets, both vectors and data points, on the Bloch sphere. The `qutip.bloch.Bloch` class, uses Matplotlib to render the Bloch sphere, where as `qutip.bloch3d.Bloch3d` uses the Mayavi rendering engine to generate a more faithful 3D reconstruction of the Bloch sphere.

3.10.2 The Bloch and Bloch3d Classes

In QuTiP, creating a Bloch sphere is accomplished by calling either:

```
b = qutip.Bloch()
```





which will load an instance of the `qutip.bloch.Bloch` class, or using

```
>>> b3d = qutip.Bloch3d()
```


that loads the `qutip.bloch3d.Bloch3d` version. Before getting into the details of these objects, we can simply plot the blank Bloch sphere associated with these instances via:

```
b.make_sphere()
```






or




In addition to the `show` command, see the API documentation for *Bloch* for a full list of other available functions. As an example, we can add a single data point:

```
pnt = [1/np.sqrt(3), 1/np.sqrt(3), 1/np.sqrt(3)]
b.add_points(pnt)
b.render()
```




and then a single vector:

```
b.fig.clf()
vec = [0, 1, 0]
b.add_vectors(vec)
b.render()
```



and then add another vector corresponding to the $|\text{up}\rangle$ state:


```
up = qutip.basis(2, 0)
b.add_states(up)
b.render()
```




Notice that when we add more than a single vector (or data point), a different color will automatically be applied to the later data set (mod 4). In total, the code for constructing our Bloch sphere with one vector, one state, and a single data point is:

```
b = qutip.Bloch()

pnt = [1./np.sqrt(3), 1./np.sqrt(3), 1./np.sqrt(3)]
b.add_points(pnt)
vec = [0, 1, 0]
b.add_vectors(vec)
up = qutip.basis(2, 0)
b.add_states(up)
b.render()
```




where we have removed the extra `show()` commands. Replacing `b=Bloch()` with `b=Bloch3d()` in the above code generates the following 3D Bloch sphere.



We can also plot multiple points, vectors, and states at the same time by passing list or arrays instead of individual elements. Before giving an example, we can use the `clear()` command to remove the current data from our Bloch sphere instead of creating a new instance:


```
b.clear()
b.render()
```



Now on the same Bloch sphere, we can plot the three states associated with the x, y, and z directions:


```
x = (qutip.basis(2, 0) + (1+0j)*qutip.basis(2, 1)).unit()
y = (qutip.basis(2, 0) + (0+1j)*qutip.basis(2, 1)).unit()
z = (qutip.basis(2, 0) + (0+0j)*qutip.basis(2, 1)).unit()

b.add_states([x, y, z])
b.render()
```

a similar method works for adding vectors:

```
b.clear()
vec = [[1, 0, 0], [0, 1, 0], [0, 0, 1]]
b.add_vectors(vec)
b.render()
```




Adding multiple points to the Bloch sphere works slightly differently than adding multiple states or vectors. For example, let's add a set of 20 points around the equator (after calling `clear()`):

```
b.clear()


th = np.linspace(0, 2*np.pi, 20)
xp = np.cos(th)
yp = np.sin(th)
zp = np.zeros(20)

pnts = [xp, yp, zp]
b.add_points(pnts)
b.render()
```



Notice that, in contrast to states or vectors, each point remains the same color as the initial point. This is because adding multiple data points using the `add_points` function is interpreted, by default, to correspond to a single data point (single qubit state) plotted at different times. This is very useful when visualizing the dynamics of a qubit. An example of this is given in the example . If we want to plot additional qubit states we can call additional `add_points` functions:

```
xz = np.zeros(20)
yz = np.sin(th)
zz = np.cos(th)
b.add_points([xz, yz, zz])
b.render()
```




The color and shape of the data points is varied automatically by the Bloch class. Notice how the color and point markers change for each set of data. Again, we have had to call `add_points` twice because adding more than one set of multiple data points is *not* supported by the `add_points` function.

What if we want to vary the color of our points. We can tell the `qutip.bloch.Bloch` class to vary the color of each point according to the colors listed in the `b.point_color` list (see [Configuring the Bloch sphere](#) below). Again after `clear()`:

```
b.clear()


xp = np.cos(th)
yp = np.sin(th)
zp = np.zeros(20)
pnts = [xp, yp, zp]
b.add_points(pnts, 'm') # <-- add a 'm' string to signify 'multi' colored points
b.render()
```




Now, the data points cycle through a variety of predefined colors. Now lets add another set of points, but this time we want the set to be a single color, representing say a qubit going from the $|up\rangle$ state to the $|down\rangle$ state in the y - z plane:

```
xz = np.zeros(20)
yz = np.sin(th)
zz = np.cos(th)

b.add_points([xz, yz, zz]) # no 'm'
b.render()
```



Again, the same plot can be generated using the `qutip.bloch3d.Bloch3d` class by replacing `Bloch` with `Bloch3d`:



A more slick way of using this ‘multi’ color feature is also given in the example, where we set the color of the markers as a function of time.

Differences Between Bloch and Bloch3d

While in general the `Bloch` and `Bloch3d` classes are interchangeable, there are some important differences to consider when choosing between them.

- The `Bloch` class uses Matplotlib to generate figures. As such, the data plotted on the sphere is in reality just a 2D object. In contrast the `Bloch3d` class uses the 3D rendering engine from VTK via mayavi to generate the sphere and the included data. In this sense the `Bloch3d` class is much more advanced, as objects are rendered in 3D leading to a higher quality figure.
- Only the `Bloch` class can be embedded in a Matplotlib figure window. Thus if you want to combine a Bloch sphere with another figure generated in QuTiP, you can not use `Bloch3d`. Of course you can always post-process your figures using other software to get the desired result.
- Due to limitations in the rendering engine, the `Bloch3d` class does not support LaTeX for text. Again, you can get around this by post-processing.
- The user customizable attributes for the `Bloch` and `Bloch3d` classes are not identical. Therefore, if you change the properties of one of the classes, these changes will cause an exception if the class is switched.

3.10.3 Configuring the Bloch sphere

Bloch Class Options

At the end of the last section we saw that the colors and marker shapes of the data plotted on the Bloch sphere are automatically varied according to the number of points and vectors added. But what if you want a different choice of color, or you want your sphere to be purple with different axes labels? Well then you are in luck as the `Bloch` class has 22 attributes which one can control. Assuming `b=Bloch()`:

Attribute	Function	Default Setting
<code>b.axes</code>	Matplotlib axes instance for animations. Set by <code>axes</code> keyword arg.	None
<code>b.fig</code>	User supplied Matplotlib Figure instance. Set by <code>fig</code> keyword arg.	None
<code>b.font_color</code>	Color of fonts	'black'
<code>b.font_size</code>	Size of fonts	20
<code>b.frame_alpha</code>	Transparency of wireframe	0.1
<code>b.frame_color</code>	Color of wireframe	'gray'
<code>b.frame_width</code>	Width of wireframe	1
<code>b.point_color</code>	List of colors for Bloch point markers to cycle through	['b', 'r', 'g', '#CC6600']
<code>b.point_marker</code>	List of point marker shapes to cycle through	['o', 's', 'd', '^']
<code>b.point_size</code>	List of point marker sizes (not all markers look the same size when plotted)	[55, 62, 65, 75]
<code>b.sphere_alpha</code>	Transparency of Bloch sphere	0.2
<code>b.sphere_color</code>	Color of Bloch sphere	'#FFDDDD'
<code>b.size</code>	Sets size of figure window	[7, 7] (700x700 pixels)
<code>b.vector_color</code>	List of colors for Bloch vectors to cycle through	['g', '#CC6600', 'b', 'r']
<code>b.vector_width</code>	Width of Bloch vectors	4
<code>b.view</code>	Azimuthal and Elevation viewing angles	[-60, 30]
<code>b.xlabel</code>	Labels for x-axis	[' x ', ''] +x and -x (labels use LaTeX)
<code>b.xlpos</code>	Position of x-axis labels	[1.1, -1.1]
<code>b.ylabel</code>	Labels for y-axis	[' y ', ''] +y and -y (labels use LaTeX)
<code>b.ylpos</code>	Position of y-axis labels	[1.2, -1.2]
<code>b.zlabel</code>	Labels for z-axis	[' z ', ''] +z and -z (labels use LaTeX)
<code>b.zlpos</code>	Position of z-axis labels	[1.2, -1.2]

Bloch3d Class Options

The Bloch3d sphere is also customizable. Note however that the attributes for the `Bloch3d` class are not in one-to-one correspondence to those of the `Bloch` class due to the different underlying rendering engines. Assuming `b=Bloch3d()`:

Attribute	Function	Default Setting
<code>b.fig</code>	User supplied Mayavi Figure instance. Set by <code>fig</code> keyword arg.	None
<code>b.font_color</code>	Color of fonts	'black'
<code>b.font_scale</code>	Scale of fonts	0.08
<code>b.frame</code>	Draw wireframe for sphere?	True
<code>b.frame_alpha</code>	Transparency of wireframe	0.05
<code>b.frame_color</code>	Color of wireframe	'gray'
<code>b.frame_num</code>	Number of wireframe elements to draw	8
<code>b.frame_radius</code>	Radius of wireframe lines	0.005
<code>b.point_color</code>	List of colors for Bloch point markers to cycle through	['r', 'g', 'b', 'y']
<code>b.point_mode</code>	Type of point markers to draw	'sphere'
<code>b.point_size</code>	Size of points	0.075
<code>b.sphere_alpha</code>	Transparency of Bloch sphere	0.1
<code>b.sphere_color</code>	Color of Bloch sphere	'#808080'
<code>b.size</code>	Sets size of figure window	[500, 500] (500x500 pixels)
<code>b.vector_color</code>	List of colors for Bloch vectors to cycle through	['r', 'g', 'b', 'y']
<code>b.vector_width</code>	Width of Bloch vectors	3
<code>b.view</code>	Azimuthal and Elevation viewing angles	[45, 65]
<code>b.xlabel</code>	Labels for x-axis	[' x>', ''] +x and -x
<code>b.xlpos</code>	Position of x-axis labels	[1.07, -1.07]
<code>b.ylabel</code>	Labels for y-axis	['\$y\$', ''] +y and -y
<code>b.ylpos</code>	Position of y-axis labels	[1.07, -1.07]
<code>b.zlabel</code>	Labels for z-axis	[' 0>', ' 1>'] +z and -z
<code>b.zlpos</code>	Position of z-axis labels	[1.07, -1.07]

These properties can also be accessed via the print command:

```
>>> b = qutip.Bloch()

>>> print(b)
Bloch data:
-----
Number of points: 0
Number of vectors: 0

Bloch sphere properties:
-----
font_color:      black
font_size:       20
frame_alpha:     0.2
frame_color:     gray
frame_width:     1
point_color:     ['b', 'r', 'g', '#CC6600']
point_marker:    ['o', 's', 'd', '^']
point_size:      [25, 32, 35, 45]
sphere_alpha:    0.2
sphere_color:    #FFDDDD
figsize:         [5, 5]
vector_color:    ['g', '#CC6600', 'b', 'r']
vector_width:    3
```

(continues on next page)

(continued from previous page)

```
vector_style:    -|>
vector_mutation: 20
view:           [-60, 30]
xlabel:         ['$x$', '']
xlpos:          [1.2, -1.2]
ylabel:         ['$y$', '']
ylpos:          [1.2, -1.2]
zlabel:         ['$\\left|0\\right>$', '$\\left|1\\right>$']
zlpos:          [1.2, -1.2]
```

3.10.4 Animating with the Bloch sphere

The Bloch class was designed from the outset to generate animations. To animate a set of vectors or data points the basic idea is: plot the data at time t_1 , save the sphere, clear the sphere, plot data at t_2, \dots . The Bloch sphere will automatically number the output file based on how many times the object has been saved (this is stored in `b.savenum`). The easiest way to animate data on the Bloch sphere is to use the `save()` method and generate a series of images to convert into an animation. However, as of Matplotlib version 1.1, creating animations is built-in. We will demonstrate both methods by looking at the decay of a qubit on the bloch sphere.

Example: Qubit Decay

The code for calculating the expectation values for the Pauli spin operators of a qubit decay is given below. This code is common to both animation examples.

```
import numpy as np
import qutip

def qubit_integrate(w, theta, gammal, gamma2, psi0, tlist):
    # operators and the hamiltonian
    sx = qutip.sigmax()
    sy = qutip.sigmay()
    sz = qutip.sigmaz()
    sm = qutip.sigmam()
    H = w * (np.cos(theta) * sz + np.sin(theta) * sx)
    # collapse operators
    c_op_list = []
    n_th = 0.5 # temperature
    rate = gammal * (n_th + 1)
    if rate > 0.0: c_op_list.append(np.sqrt(rate) * sm)
    rate = gammal * n_th
    if rate > 0.0: c_op_list.append(np.sqrt(rate) * sm.dag())
    rate = gamma2
    if rate > 0.0: c_op_list.append(np.sqrt(rate) * sz)
    # evolve and calculate expectation values
    output = qutip.mesolve(H, psi0, tlist, c_op_list, [sx, sy, sz])
    return output.expect[0], output.expect[1], output.expect[2]

## calculate the dynamics
w      = 1.0 * 2 * np.pi # qubit angular frequency
theta  = 0.2 * np.pi     # qubit angle from sigma_z axis (toward sigma_x axis)
gammal = 0.5              # qubit relaxation rate
gamma2  = 0.2             # qubit dephasing rate
# initial state
a = 1.0
psi0 = (a*qutip.basis(2, 0) + (1-a)*qutip.basis(2, 1))/np.sqrt(a**2 + (1-a)**2)
tlist = np.linspace(0, 4, 250)
#expectation values for plotting
sx, sy, sz = qubit_integrate(w, theta, gammal, gamma2, psi0, tlist)
```

Generating Images for Animation

An example of generating images for generating an animation outside of Python is given below:

```
import numpy as np
b = qutip.Bloch()
b.vector_color = ['r']
b.view = [-40, 30]
for i in range(len(sx)):
    b.clear()
    b.add_vectors([np.sin(theta), 0, np.cos(theta)])
    b.add_points([sx[:i+1], sy[:i+1], sz[:i+1]])
    b.save(dirc='temp') # saving images to temp directory in current working_
                        ↪directory
```

Generating an animation using FFmpeg (for example) is fairly simple:

```
ffmpeg -i temp/bloch_%01d.png bloch.mp4
```

Directly Generating an Animation

Important: Generating animations directly from Matplotlib requires installing either MEncoder or FFmpeg. While either choice works on linux, it is best to choose FFmpeg when running on the Mac. If using macports just do: `sudo port install ffmpeg`.

The code to directly generate an mp4 movie of the Qubit decay is as follows

```
from matplotlib import pyplot, animation
from mpl_toolkits.mplot3d import Axes3D

fig = pyplot.figure()
ax = Axes3D(fig, azim=-40, elev=30)
sphere = qutip.Bloch(axes=ax)

def animate(i):
    sphere.clear()
    sphere.add_vectors([np.sin(theta), 0, np.cos(theta)])
    sphere.add_points([sx[:i+1], sy[:i+1], sz[:i+1]])
    sphere.make_sphere()
    return ax

def init():
    sphere.vector_color = ['r']
    return ax

ani = animation.FuncAnimation(fig, animate, np.arange(len(sx)),
                             init_func=init, blit=False, repeat=False)
ani.save('bloch_sphere.mp4', fps=20)
```

The resulting movie may be viewed here: [bloch_decay.mp4](#)

3.11 Visualization of quantum states and processes

Visualization is often an important complement to a simulation of a quantum mechanical system. The first method of visualization that come to mind might be to plot the expectation values of a few selected operators. But on top of that, it can often be instructive to visualize for example the state vectors or density matrices that describe the state of the system, or how the state is transformed as a function of time (see process tomography below). In this section we demonstrate how QuTiP and matplotlib can be used to perform a few types of visualizations that often can provide additional understanding of quantum system.

3.11.1 Fock-basis probability distribution

In quantum mechanics probability distributions plays an important role, and as in statistics, the expectation values computed from a probability distribution does not reveal the full story. For example, consider an quantum harmonic oscillator mode with Hamiltonian $H = \hbar\omega a^\dagger a$, which is in a state described by its density matrix ρ , and which on average is occupied by two photons, $\text{Tr}[\rho a^\dagger a] = 2$. Given this information we cannot say whether the oscillator is in a Fock state, a thermal state, a coherent state, etc. By visualizing the photon distribution in the Fock state basis important clues about the underlying state can be obtained.

One convenient way to visualize a probability distribution is to use histograms. Consider the following histogram visualization of the number-basis probability distribution, which can be obtained from the diagonal of the density matrix, for a few possible oscillator states with on average occupation of two photons.

First we generate the density matrices for the coherent, thermal and fock states.

```
N = 20

rho_coherent = coherent_dm(N, np.sqrt(2))

rho_thermal = thermal_dm(N, 2)

rho_fock = fock_dm(N, 2)
```

Next, we plot histograms of the diagonals of the density matrices:

```
fig, axes = plt.subplots(1, 3, figsize=(12,3))

bar0 = axes[0].bar(np.arange(0, N)-.5, rho_coherent.diag())

lb10 = axes[0].set_title("Coherent state")

lim0 = axes[0].set_xlim([-0.5, N])

bar1 = axes[1].bar(np.arange(0, N)-.5, rho_thermal.diag())

lb11 = axes[1].set_title("Thermal state")


lim1 = axes[1].set_xlim([-0.5, N])

bar2 = axes[2].bar(np.arange(0, N)-.5, rho_fock.diag())

lb12 = axes[2].set_title("Fock state")

lim2 = axes[2].set_xlim([-0.5, N])

plt.show()
```



All these states correspond to an average of two photons, but by visualizing the photon distribution in Fock basis the differences between these states are easily appreciated.


One frequently need to visualize the Fock-distribution in the way described above, so QuTiP provides a convenience function for doing this, see `qutip.visualization.plot_fock_distribution`, and the following example:

```
fig, axes = plt.subplots(1, 3, figsize=(12,3))

plot_fock_distribution(rho_coherent, fig=fig, ax=axes[0], title="Coherent state");
plot_fock_distribution(rho_thermal, fig=fig, ax=axes[1], title="Thermal state");
plot_fock_distribution(rho_fock, fig=fig, ax=axes[2], title="Fock state");

fig.tight_layout()

plt.show()
```



3.11.2 Quasi-probability distributions

The probability distribution in the number (Fock) basis only describes the occupation probabilities for a discrete set of states. A more complete phase-space probability-distribution-like function for harmonic modes are the Wigner and Husimi Q-functions, which are full descriptions of the quantum state (equivalent to the density matrix). These are called quasi-distribution functions because unlike real probability distribution functions they can for example be negative. In addition to being more complete descriptions of a state (compared to only the occupation probabilities plotted above), these distributions are also great for demonstrating if a quantum state is quantum mechanical, since for example a negative Wigner function is a definite indicator that a state is distinctly nonclassical.

Wigner function

In QuTiP, the Wigner function for a harmonic mode can be calculated with the function `qutip.wigner.wigner`. It takes a ket or a density matrix as input, together with arrays that define the ranges of the phase-space coordinates (in the x-y plane). In the following example the Wigner functions are calculated and plotted for the same three states as in the previous section.

```
xvec = np.linspace(-5,5,200)

W_coherent = wigner(rho_coherent, xvec, xvec)

W_thermal = wigner(rho_thermal, xvec, xvec)

W_fock = wigner(rho_fock, xvec, xvec)

# plot the results

fig, axes = plt.subplots(1, 3, figsize=(12,3))

cont0 = axes[0].contourf(xvec, xvec, W_coherent, 100)

lbl0 = axes[0].set_title("Coherent state")


cont1 = axes[1].contourf(xvec, xvec, W_thermal, 100)

lbl1 = axes[1].set_title("Thermal state")

cont0 = axes[2].contourf(xvec, xvec, W_fock, 100)

lbl2 = axes[2].set_title("Fock state")

plt.show()
```



Custom Color Maps

The main objective when plotting a Wigner function is to demonstrate that the underlying state is nonclassical, as indicated by negative values in the Wigner function. Therefore, making these negative values stand out in a figure is helpful for both analysis and publication purposes. Unfortunately, all of the color schemes used in Matplotlib (or any other plotting software) are linear colormaps where small negative values tend to be near the same color as the zero values, and are thus hidden. To fix this dilemma, QuTiP includes a nonlinear colormap function `qutip.matplotlib_utilities.wigner_cmap` that colors all negative values differently than positive or zero values. Below is a demonstration of how to use this function in your Wigner figures:

```
import matplotlib as mpl

from matplotlib import cm

psi = (basis(10, 0) + basis(10, 3) + basis(10, 9)).unit()
```

(continues on next page)

(continued from previous page)

```
xvec = np.linspace(-5, 5, 500)
W = wigner(psi, xvec, xvec)

wmap = wigner_cmap(W) # Generate Wigner colormap

nrm = mpl.colors.Normalize(-W.max(), W.max())

fig, axes = plt.subplots(1, 2, figsize=(10, 4))

plt1 = axes[0].contourf(xvec, xvec, W, 100, cmap=cm.RdBu, norm=nrm)

axes[0].set_title("Standard Colormap");

cb1 = fig.colorbar(plt1, ax=axes[0])


plt2 = axes[1].contourf(xvec, xvec, W, 100, cmap=wmap) # Apply Wigner colormap

axes[1].set_title("Wigner Colormap");

cb2 = fig.colorbar(plt2, ax=axes[1])

fig.tight_layout()

plt.show()
```



Husimi Q-function

The Husimi Q function is, like the Wigner function, a quasiprobability distribution for harmonic modes. It is defined as

$$Q(\alpha) = \frac{1}{\pi} \langle \alpha | \rho | \alpha \rangle$$

where $|\alpha\rangle$ is a coherent state and $\alpha = x + iy$. In QuTiP, the Husimi Q function can be computed given a state ket or density matrix using the function `qfunc`, as demonstrated below.

```
Q_coherent = qfunc(rho_coherent, xvec, xvec)
Q_thermal = qfunc(rho_thermal, xvec, xvec)
Q_fock = qfunc(rho_fock, xvec, xvec)
fig, axes = plt.subplots(1, 3, figsize=(12, 3))
cont0 = axes[0].contourf(xvec, xvec, Q_coherent, 100)
```


(continues on next page)

(continued from previous page)

```

lbl0 = axes[0].set_title("Coherent state")
cont1 = axes[1].contourf(xvec, xvec, Q_thermal, 100)
lbl1 = axes[1].set_title("Thermal state")
cont0 = axes[2].contourf(xvec, xvec, Q_fock, 100)
lbl2 = axes[2].set_title("Fock state")
plt.show()

```



If you need to calculate the Q function for many states with the same phase-space coordinates, it is more efficient to use the `QFunc` class. This stores various intermediary results to achieve an order-of-magnitude improvement compared to calling `qfunc` in a loop.

```

xs = np.linspace(-1, 1, 101)
qfunc_calculator = qutip.QFunc(xs, xs)
q_state1 = qfunc_calculator(qutip.rand_dm(5))
q_state2 = qfunc_calculator(qutip.rand_ket(100))

```

3.11.3 Visualizing operators

Sometimes, it may also be useful to directly visualizing the underlying matrix representation of an operator. The density matrix, for example, is an operator whose elements can give insights about the state it represents, but one might also be interesting in plotting the matrix of an Hamiltonian to inspect the structure and relative importance of various elements.

QuTiP offers a few functions for quickly visualizing matrix data in the form of histograms, `qutip.visualization.matrix_histogram` and `qutip.visualization.matrix_histogram_complex`, and as Hinton diagram of weighted squares, `qutip.visualization.hinton`. These functions takes a `qutip.Qobj` as first argument, and optional arguments to, for example, set the axis labels and figure title (see the function's documentation for details).

For example, to illustrate the use of `qutip.visualization.matrix_histogram`, let's visualize of the Jaynes-Cummings Hamiltonian:

```

N = 5

a = tensor(destroy(N), qeye(2))
b = tensor(qeye(N), destroy(2))
sx = tensor(qeye(N), sigmax())

H = a.dag() * a + sx - 0.5 * (a * b.dag() + a.dag() * b)

# visualize H

lbls_list = [[str(d) for d in range(N)], ["u", "d"]]

xlabels = []

```

(continues on next page)


(continued from previous page)

```
for inds in tomography._index_permutations([len(lbls) for lbls in lbls_list]):
    xlabels.append("".join([lbls_list[k][inds[k]] for k in range(len(lbls_list))]))

fig, ax = matrix_histogram(H, xlabels, xlabels, limits=[-4,4])

ax.view_init(azim=-55, elev=45)

plt.show()
```




Similarly, we can use the function `qutip.visualization.hinton`, which is used below to visualize the corresponding steadystate density matrix:

```
rho_ss = steadystate(H, [np.sqrt(0.1) * a, np.sqrt(0.4) * b.dag()])

hinton(rho_ss)

plt.show()
```

3.11.4 Quantum process tomography

Quantum process tomography (QPT) is a useful technique for characterizing experimental implementations of quantum gates involving a small number of qubits. It can also be a useful theoretical tool that can give insight in how a process transforms states, and it can be used for example to study how noise or other imperfections deteriorate a gate. Whereas a fidelity or distance measure can give a single number that indicates how far from ideal a gate is, a quantum process tomography analysis can give detailed information about exactly what kind of errors various imperfections introduce.

The idea is to construct a transformation matrix for a quantum process (for example a quantum gate) that describes how the density matrix of a system is transformed by the process. We can then decompose the transformation in some operator basis that represent well-defined and easily interpreted transformations of the input states.

To see how this works (see e.g. [Moh08] for more details), consider a process that is described by quantum map $\epsilon(\rho_{\text{in}}) = \rho_{\text{out}}$, which can be written

$$\epsilon(\rho_{\text{in}}) = \rho_{\text{out}} = \sum_i^{N^2} A_i \rho_{\text{in}} A_i^\dagger, \quad (3.40)$$

where N is the number of states of the system (that is, ρ is represented by an $[N \times N]$ matrix). Given an orthogonal operator basis of our choice $\{B_i\}_i^{N^2}$, which satisfies $\text{Tr}[B_i^\dagger B_j] = N \delta_{ij}$, we can write the map as

$$\epsilon(\rho_{\text{in}}) = \rho_{\text{out}} = \sum_{mn} \chi_{mn} B_m \rho_{\text{in}} B_n^\dagger. \quad (3.41)$$

where $\chi_{mn} = \sum_{ij} b_{im} b_{jn}^*$ and $A_i = \sum_m b_{im} B_m$. Here, matrix χ is the transformation matrix we are after, since it describes how much $B_m \rho_{\text{in}} B_n^\dagger$ contributes to ρ_{out} .

In a numerical simulation of a quantum process we usually do not have access to the quantum map in the form Eq. (3.40). Instead, what we usually can do is to calculate the propagator U for the density matrix in superoperator

form, using for example the QuTiP function `qutip.propagator.propagator`. We can then write

$$\epsilon(\tilde{\rho}_{\text{in}}) = U\tilde{\rho}_{\text{in}} = \tilde{\rho}_{\text{out}}$$

where $\tilde{\rho}$ is the vector representation of the density matrix ρ . If we write Eq. (3.41) in superoperator form as well we obtain

$$\tilde{\rho}_{\text{out}} = \sum_{mn} \chi_{mn} \tilde{B}_m \tilde{B}_n^\dagger \tilde{\rho}_{\text{in}} = U \tilde{\rho}_{\text{in}}.$$

so we can identify

$$U = \sum_{mn} \chi_{mn} \tilde{B}_m \tilde{B}_n^\dagger.$$

Now this is a linear equation systems for the $N^2 \times N^2$ elements in χ . We can solve it by writing χ and the superoperator propagator as $[N^4]$ vectors, and likewise write the superoperator product $\tilde{B}_m \tilde{B}_n^\dagger$ as a $[N^4 \times N^4]$ matrix M :

$$U_I = \sum_J M_{IJ} \chi_J$$

with the solution

$$\chi = M^{-1}U.$$

Note that to obtain χ with this method we have to construct a matrix M with a size that is the square of the size of the superoperator for the system. Obviously, this scales very badly with increasing system size, but this method can still be a very useful for small systems (such as system comprised of a small number of coupled qubits).

Implementation in QuTiP

In QuTiP, the procedure described above is implemented in the function `qutip.tomography.qpt`, which returns the χ matrix given a density matrix propagator. To illustrate how to use this function, let's consider the SWAP gate for two qubits. In QuTiP the function `qutip.core.operators.swap` generates the unitary transformation for the state kets:

```
from qutip.core.gates import swap

U_psi = swap()
```

To be able to use this unitary transformation matrix as input to the function `qutip.tomography.qpt`, we first need to convert it to a transformation matrix for the corresponding density matrix:

```
U_rho = spre(U_psi) * spost(U_psi.dag())
```

Next, we construct a list of operators that define the basis $\{B_i\}$ in the form of a list of operators for each composite system. At the same time, we also construct a list of corresponding labels that will be used when plotting the χ matrix.


```
op_basis = [[qeye(2), sigmax(), sigmay(), sigmaz()]] * 2
op_label = [["i", "x", "y", "z"]] * 2
```

We are now ready to compute χ using `qutip.tomography.qpt`, and to plot it using `qutip.tomography.qpt_plot_combined`.

```
chi = qpt(U_rho, op_basis)

fig = qpt_plot_combined(chi, op_label, r'SWAP')

plt.show()
```



For a slightly more advanced example, where the density matrix propagator is calculated from the dynamics of a system defined by its Hamiltonian and collapse operators using the function `qutip.propagator.propagator`, see notebook “Time-dependent master equation: Landau-Zener transitions” on the tutorials section on the QuTiP web site.

3.12 Parallel computation

3.12.1 Parallel map and parallel for-loop

Often one is interested in the output of a given function as a single-parameter is varied. For instance, we can calculate the steady-state response of our system as the driving frequency is varied. In cases such as this, where each iteration is independent of the others, we can speedup the calculation by performing the iterations in parallel. In QuTiP, parallel computations may be performed using the `qutip.solver.parallel.parallel_map` function.

To use the this function we need to define a function of one or more variables, and the range over which one of these variables are to be evaluated. For example:

```
>>> result = parallel_map(func1, range(10))

>>> result_array = np.array(result)

>>> print(result_array[:, 0]) # == a
[0 1 2 3 4 5 6 7 8 9]

>>> print(result_array[:, 1]) # == b
[ 0  1  4  9 16 25 36 49 64 81]
```

(continues on next page)

(continued from previous page)

```
>>> print(result_array[:, 2]) # == c
[ 0  1  8 27 64 125 216 343 512 729]

>>> print(result)
[(0, 0, 0), (1, 1, 1), (2, 4, 8), (3, 9, 27), (4, 16, 64)]
```

The `qutip.solver.parallel.parallel_map` function is not limited to just numbers, but also works for a variety of outputs:

```
>>> def func2(x): return x, Qobj(x), 'a' * x

>>> results = parallel_map(func2, range(5))

>>> print([result[0] for result in results])
[0 1 2 3 4]

>>> print([result[1] for result in results])
[Quantum object: dims = [[1], [1]], shape = (1, 1), type = bra
Qobj data =
[[0.]]
Quantum object: dims = [[1], [1]], shape = (1, 1), type = bra
Qobj data =
[[1.]]
Quantum object: dims = [[1], [1]], shape = (1, 1), type = bra
Qobj data =
[[2.]]
Quantum object: dims = [[1], [1]], shape = (1, 1), type = bra
Qobj data =
[[3.]]
Quantum object: dims = [[1], [1]], shape = (1, 1), type = bra
Qobj data =
[[4.]]]

>>> print([result[2] for result in results])
['' 'a' 'aa' 'aaa' 'aaaa']
```

One can also define functions with **multiple** input arguments and keyword arguments.

```
>>> def sum_diff(x, y, z=0): return x + y, x - y, z

>>> parallel_map(sum_diff, [1, 2, 3], task_args=(np.array([4, 5, 6])), task_
↳kwargs=dict(z=5.0))
[(array([5, 6, 7]), array([-3, -4, -5]), 5.0),
 (array([6, 7, 8]), array([-2, -3, -4]), 5.0),
 (array([7, 8, 9]), array([-1, -2, -3]), 5.0)]
```

The `qutip.solver.parallel.parallel_map` function supports progressbar by setting the keyword argument `progress_bar` to `True`. The number of cpu used can also be controlled using the `map_kw` keyword, per default, all available cpus are used.

```
>>> import time

>>> def func(x): time.sleep(1)

>>> result = parallel_map(func, range(50), progress_bar=True, map_kw={"num_cpus": 2})
↳2})

10.0%. Run time: 3.10s. Est. time left: 00:00:00:27
20.0%. Run time: 5.11s. Est. time left: 00:00:00:20
30.0%. Run time: 8.11s. Est. time left: 00:00:00:18
```

(continues on next page)

(continued from previous page)

```
40.0%. Run time: 10.15s. Est. time left: 00:00:00:15
50.0%. Run time: 13.15s. Est. time left: 00:00:00:13
60.0%. Run time: 15.15s. Est. time left: 00:00:00:10
70.0%. Run time: 18.15s. Est. time left: 00:00:00:07
80.0%. Run time: 20.15s. Est. time left: 00:00:00:05
90.0%. Run time: 23.15s. Est. time left: 00:00:00:02
100.0%. Run time: 25.15s. Est. time left: 00:00:00:00
Total run time: 28.91s
```

There is a function called `qutip.solver.parallel.serial_map` that works as a non-parallel drop-in replacement for `qutip.solver.parallel.parallel_map`, which allows easy switching between serial and parallel computation. Qutip also has the function `qutip.solver.parallel.loky_map` as another drop-in replacement. It use the *loky* module instead of *multiprocessing* to run in parallel. Parallel processing is useful for repeated tasks such as generating plots corresponding to the dynamical evolution of your system, or simultaneously simulating different parameter configurations.

3.12.2 IPython-based parallel_map

When QuTiP is used with IPython interpreter, there is an alternative parallel for-loop implementation in the QuTiP module `qutip.ipynbtools`, see `qutip.ipynbtools.parallel_map`. The advantage of this `parallel_map` implementation is based on IPython's powerful framework for parallelization, so the compute processes are not confined to run on the same host as the main process.

3.13 Saving QuTiP Objects and Data Sets

With time-consuming calculations it is often necessary to store the results to files on disk, so it can be post-processed and archived. In QuTiP there are two facilities for storing data: Quantum objects can be stored to files and later read back as python pickles, and numerical data (vectors and matrices) can be exported as plain text files in for example CSV (comma-separated values), TSV (tab-separated values), etc. The former method is preferred when further calculations will be performed with the data, and the latter when the calculations are completed and data is to be imported into a post-processing tool (e.g. for generating figures).

3.13.1 Storing and loading QuTiP objects

To store and load arbitrary QuTiP related objects (`qutip.Qobj`, `qutip.solve.solver.Result`, etc.) there are two functions: `qutip.fileio.qsave` and `qutip.fileio.qload`. The function `qutip.fileio.qsave` takes an arbitrary object as first parameter and an optional filename as second parameter (default filename is `qutip_data.qu`). The filename extension is always `.qu`. The function `qutip.fileio.qload` takes a mandatory filename as first argument and loads and returns the objects in the file.

To illustrate how these functions can be used, consider a simple calculation of the steadystate of the harmonic oscillator

```
>>> a = destroy(10); H = a.dag() * a
>>> c_ops = [np.sqrt(0.5) * a, np.sqrt(0.25) * a.dag()]
>>> rho_ss = steadystate(H, c_ops)
```

The steadystate density matrix `rho_ss` is an instance of `qutip.Qobj`. It can be stored to a file `steadystate.qu` using

```
>>> qsave(rho_ss, 'steadystate')
>>> !ls *.qu
density_matrix_vs_time.qu  steadystate.qu
```

and it can later be loaded again, and used in further calculations

```
>>> rho_ss_loaded = qload('steadystate')
Loaded Qobj object:
Quantum object: dims = [[10], [10]], shape = (10, 10), type = oper, isHerm = True
>>> a = destroy(10)
>>> np.testing.assert_almost_equal(expect(a.dag() * a, rho_ss_loaded), 0.
↪9902248289345061)
```

The nice thing about the `qutip.fileio.qsave` and `qutip.fileio.qload` functions is that almost any object can be stored and load again later on. We can for example store a list of density matrices as returned by `qutip.mesolve`

```
>>> a = destroy(10); H = a.dag() * a ; c_ops = [np.sqrt(0.5) * a, np.sqrt(0.25) *
↪a.dag()]
>>> psi0 = rand_ket(10)
>>> times = np.linspace(0, 10, 10)
>>> dm_list = mesolve(H, psi0, times, c_ops, [])
>>> qsave(dm_list, 'density_matrix_vs_time')
```

And it can then be loaded and used again, for example in an other program

```
>>> dm_list_loaded = qload('density_matrix_vs_time')
Loaded Result object:
Result object with mesolve data.
-----
states = True
num_collapse = 0
>>> a = destroy(10)
>>> expect(a.dag() * a, dm_list_loaded.states)
array([4.63317086, 3.59150315, 2.90590183, 2.41306641, 2.05120716,
       1.78312503, 1.58357995, 1.4346382 , 1.32327398, 1.23991233])
```

3.13.2 Storing and loading datasets

The `qutip.fileio.qsave` and `qutip.fileio.qload` are great, but the file format used is only understood by QuTiP (python) programs. When data must be exported to other programs the preferred method is to store the data in the commonly used plain-text file formats. With the QuTiP functions `qutip.fileio.file_data_store` and `qutip.fileio.file_data_read` we can store and load **numpy** arrays and matrices to files on disk using a delimiter-separated value format (for example comma-separated values CSV). Almost any program can handle this file format.

The `qutip.fileio.file_data_store` takes two mandatory and three optional arguments:

```
>>> file_data_store(filename, data, numtype="complex", numformat="decimal", sep=",
↪")
```

where *filename* is the name of the file, *data* is the data to be written to the file (must be a *numpy* array), *numtype* (optional) is a flag indicating numerical type that can take values *complex* or *real*, *numformat* (optional) specifies the numerical format that can take the values *exp* for the format *1.0e1* and *decimal* for the format *10.0*, and *sep* (optional) is an arbitrary single-character field separator (usually a tab, space, comma, semicolon, etc.).

A common use for the `qutip.fileio.file_data_store` function is to store the expectation values of a set of operators for a sequence of times, e.g., as returned by the `qutip.mesolve` function, which is what the following example does

```
>>> a = destroy(10); H = a.dag() * a ; c_ops = [np.sqrt(0.5) * a, np.sqrt(0.25) *
↪a.dag()]
>>> psi0 = rand_ket(10)
>>> times = np.linspace(0, 100, 100)
>>> medata = mesolve(H, psi0, times, c_ops, [a.dag() * a, a + a.dag(), -1j * (a -
↪a.dag())])
```

(continues on next page)

(continued from previous page)

```
>>> np.shape(metadata.expect)
(3, 100)
>>> times.shape
(100,)
>>> output_data = np.vstack((times, metadata.expect)) # join time and expt data
>>> file_data_store('expect.dat', output_data.T) # Note the .T for transpose!
>>> with open("expect.dat", "r") as f:
...     print('\n'.join(f.readlines()[:10]))
# Generated by QuTiP: 100x4 complex matrix in decimal format [',' separated_
↪values].
0.0000000000+0.0000000000j,3.2109553666+0.0000000000j,0.3689771549+0.0000000000j,0.
↪0185002867+0.0000000000j
1.0101010101+0.0000000000j,2.6754598872+0.0000000000j,0.1298251132+0.0000000000j,-
↪0.3303672956+0.0000000000j
2.0202020202+0.0000000000j,2.2743186810+0.0000000000j,-0.2106241300+0.0000000000j,-
↪0.2623894277+0.0000000000j
3.0303030303+0.0000000000j,1.9726633457+0.0000000000j,-0.3037311621+0.0000000000j,
↪0.0397330921+0.0000000000j
4.0404040404+0.0000000000j,1.7435892209+0.0000000000j,-0.1126550232+0.0000000000j,
↪0.2497182058+0.0000000000j
5.0505050505+0.0000000000j,1.5687324121+0.0000000000j,0.1351622725+0.0000000000j,0.
↪2018398581+0.0000000000j
6.0606060606+0.0000000000j,1.4348632045+0.0000000000j,0.2143080535+0.0000000000j,-
↪0.0067820038+0.0000000000j
7.0707070707+0.0000000000j,1.3321818015+0.0000000000j,0.0950352763+0.0000000000j,-
↪0.1630920429+0.0000000000j
8.0808080808+0.0000000000j,1.2533244850+0.0000000000j,-0.0771210981+0.0000000000j,-
↪0.1468923919+0.0000000000j
```

In this case we didn't really need to store both the real and imaginary parts, so instead we could use the `numtype="real"` option


```
>>> file_data_store('expect.dat', output_data.T, numtype="real")
>>> with open("expect.dat", "r") as f:
...     print('\n'.join(f.readlines()[:5]))
# Generated by QuTiP: 100x4 real matrix in decimal format [',' separated values].
0.0000000000,3.2109553666,0.3689771549,0.0185002867
1.0101010101,2.6754598872,0.1298251132,-0.3303672956
2.0202020202,2.2743186810,-0.2106241300,-0.2623894277
3.0303030303,1.9726633457,-0.3037311621,0.0397330921
```

and if we prefer scientific notation we can request that using the `numformat="exp"` option

```
>>> file_data_store('expect.dat', output_data.T, numtype="real", numformat="exp")
```

Loading data previously stored using `qutip.fileio.file_data_store` (or some other software) is a even easier. Regardless of which delimiter was used, if data was stored as complex or real numbers, if it is in decimal or exponential form, the data can be loaded using the `qutip.fileio.file_data_read`, which only takes the filename as mandatory argument.

```
input_data = file_data_read('expect.dat')
plt.plot(input_data[:,0], input_data[:,1]); # plot the data
```



(If a particularly obscure choice of delimiter was used it might be necessary to use the optional second argument, for example `sep="_"` if `_` is the delimiter).

3.14 Generating Random Quantum States & Operators

QuTiP includes a collection of random state, unitary and channel generators for simulations, Monte Carlo evaluation, theorem evaluation, and code testing. Each of these objects can be sampled from one of several different distributions.

For example, a random Hermitian operator can be sampled by calling `rand_herm` function:

```
>>> rand_herm(5)
Quantum object: dims = [[5], [5]], shape = (5, 5), type = oper, isherm = True
Qobj data =
[[-0.25091976+0.j          0.          +0.j          0.          +0.j
 -0.21793701+0.47037633j -0.23212846-0.61607187j]
 [ 0.          +0.j          -0.88383278+0.j          0.836086   -0.23956218j
 -0.09464275+0.45370863j -0.15243356+0.65392096j]
 [ 0.          +0.j          0.836086   +0.23956218j  0.66488528+0.j
 -0.26290446+0.64984451j -0.52603038-0.07991553j]
 [-0.21793701-0.47037633j -0.09464275-0.45370863j -0.26290446-0.64984451j
 -0.13610996+0.j          -0.34240902-0.2879303j ]
 [-0.23212846+0.61607187j -0.15243356-0.65392096j -0.52603038+0.07991553j
 -0.34240902+0.2879303j  0.          +0.j          ]]
```


Random Variable Type	Sampling Functions	Dimensions
State vector (ket)	<code>rand_ket</code> ,	$N \times 1$
Hermitian operator (oper)	<code>rand_herm</code>	$N \times N$
Density operator (oper)	<code>rand_dm</code> ,	$N \times N$
Unitary operator (oper)	<code>rand_unitary</code> ,	$N \times N$
stochastic matrix (oper)	<code>rand_stochastic</code> ,	$N \times N$
CPTP channel (super)	<code>rand_super</code> , <code>rand_super_bcsz</code>	$(N \times N) \times (N \times N)$
CPTP map (list of oper)	<code>rand_kraus_map</code>	$N \times N$ (N^2 operators)

In all cases, these functions can be called with a single parameter *dimensions* that can be the size of the relevant Hilbert space or the dimensions of a random state, unitary or channel.

```
>>> rand_super_bcsz(7).dims
[[[7], [7]], [[7], [7]]]
>>> rand_super_bcsz([[2, 3], [2, 3]]).dims
[[[2, 3], [2, 3]], [[2, 3], [2, 3]]]
```

Several of the random *Qobj* function in QuTiP support additional parameters as well, namely *density* and *distribution*. `rand_dm`, `rand_herm`, `rand_unitary` and `rand_ket` can be created using multiple method controlled by *distribution*. The `rand_ket`, `rand_herm` and `rand_unitary` functions can return quantum objects such that a fraction of the elements are identically equal to zero. The ratio of nonzero elements is passed as the `density` keyword argument. By contrast, `rand_super_bcsz` take as an argument the rank of the generated object, such that passing `rank=1` returns a random pure state or unitary channel, respectively. Passing `rank=None` specifies that the generated object should be full-rank for the given dimension. `rand_dm` can support *density* or *rank* depending on the chosen distribution.

For example,

```
>>> rand_dm(5, density=0.5, distribution="herm")
Quantum object: dims = [[5], [5]], shape = (5, 5), type = oper, isherm = True
Qobj data =
[[ 0.298+0.j , 0. +0.j , -0.095+0.1j , 0. +0.j , -0.105+0.122j],
 [ 0. +0.j , 0.088+0.j , 0. +0.j , -0.018-0.001j, 0. +0.j ],
 [-0.095-0.1j , 0. +0.j , 0.328+0.j , 0. +0.j , -0.077-0.033j],
 [ 0. +0.j , -0.018+0.001j, 0. +0.j , 0.084+0.j , 0. +0.j ],
 [-0.105-0.122j, 0. +0.j , -0.077+0.033j, 0. +0.j , 0.201+0.j ]]

>>> rand_dm_ginibre(5, rank=2)
Quantum object: dims = [[5], [5]], shape = (5, 5), type = oper, isherm = True
Qobj data =
[[ 0.307+0.j , -0.258+0.039j, -0.039+0.184j, 0.041-0.054j, 0.016+0.045j],
 [-0.258-0.039j, 0.239+0.j , 0.075-0.15j , -0.053+0.008j, -0.057-0.078j],
 [-0.039-0.184j, 0.075+0.15j , 0.136+0.j , -0.05 -0.052j, -0.028-0.058j],
 [ 0.041+0.054j, -0.053-0.008j, -0.05 +0.052j, 0.083+0.j , 0.101-0.056j],
 [ 0.016-0.045j, -0.057+0.078j, -0.028+0.058j, 0.101+0.056j, 0.236+0.j ]]
```

See the API documentation: [Quantum Objects](#) for details.

Warning: When using the `density` keyword argument, setting the density too low may result in not enough diagonal elements to satisfy trace constraints.

3.14.1 Random objects with a given eigen spectrum

It is also possible to generate random Hamiltonian (`rand_herm`) and density matrices (`rand_dm`) with a given eigen spectrum. This is done by passing an array to `eigenvalues` argument to either function and choosing the “eigen” distribution. For example,

```
>>> eigs = np.arange(5)

>>> H = rand_herm(5, density=0.5, eigenvalues=eigs, distribution="eigen")

>>> H
Quantum object: dims = [[5], [5]], shape = (5, 5), type = oper, isherm = True
Qobj data =
[[ 0.5 +0.j , 0.228+0.27j, 0. +0.j , 0. +0.j , -0.228-0.27j],
 [ 0.228-0.27j, 1.75 +0.j , 0.456+0.54j, 0. +0.j , 1.25 +0.j ],
 [ 0. +0.j , 0.456-0.54j, 3. +0.j , 0. +0.j , 0.456-0.54j],
 [ 0. +0.j , 0. +0.j , 0. +0.j , 3. +0.j , 0. +0.j ],
 [-0.228+0.27j, 1.25 +0.j , 0.456+0.54j, 0. +0.j , 1.75 +0.j ]]

>>> H.eigenenergies()
array([7.70647994e-17, 1.00000000e+00, 2.00000000e+00, 3.00000000e+00,
       4.00000000e+00])
```

In order to generate a random object with a given spectrum QuTiP applies a series of random complex Jacobi rotations. This technique requires many steps to build the desired quantum object, and is thus suitable only for objects with Hilbert dimensionality $\lesssim 1000$.

3.14.2 Composite random objects

In many cases, one is interested in generating random quantum objects that correspond to composite systems generated using the `qutip.tensor.tensor` function. Specifying the tensor structure of a quantum object is done passing a list for the first argument. The resulting quantum objects size will be the product of the elements in the list and the resulting `qutip.Qobj` dimensions will be `[dims, dims]`:

```
>>> rand_unitary([2, 2], density=0.5)
Quantum object: dims = [[2, 2], [2, 2]], shape = (4, 4), type = oper, isherm = True
Qobj data =
[[ 0.887+0.061j, 0. +0.j , 0. +0.j , -0.191-0.416j],
 [ 0. +0.j , 0.604+0.116j, -0.32 -0.721j, 0. +0.j ],
 [ 0. +0.j , 0.768+0.178j, 0.227+0.572j, 0. +0.j ],
 [ 0.412-0.2j , 0. +0.j , 0. +0.j , 0.724+0.516j]]
```

3.14.3 Controlling the random number generator

Qutip uses numpy random number generator to create random quantum objects. To control the random number, a seed as an *int* or *numpy.random.SeedSequence* or a *numpy.random.Generator* can be passed to the *seed* keyword argument:

```
>>> rng = np.random.default_rng(12345)
>>> rand_ket(2, seed=rng)
Quantum object: dims=[[2], [1]], shape=(2, 1), type='ket'
Qobj data =
[[-0.697+0.618j],
 [-0.326-0.163j]]
```

3.14.4 Internal matrix format

The internal storage type of the generated random quantum objects can be set with the *dtype* keyword.

```
>>> rand_ket(2, dtype="dense").data
Dense(shape=(2, 1), fortran=True)

>>> rand_ket(2, dtype="CSR").data
CSR(shape=(2, 1), nnz=2)
```

3.15 Modifying Internal QuTiP Settings

3.15.1 User Accessible Parameters

In this section we show how to modify a few of the internal parameters used by QuTiP. The settings that can be modified are given in the following table:

Setting	Description	Options
<i>auto_tidyup</i>	Automatically tidyup sparse quantum objects.	True / False
<i>auto_tidyup_atol</i>	Tolerance used by tidyup. (sparse only)	float {1e-14}
<i>atol</i>	General absolute tolerance.	float {1e-12}
<i>rtol</i>	General relative tolerance.	float {1e-12}
<i>function_coefficient_style</i>	Signature expected by function coefficients.	{"auto", "pythonic", "dict"}

3.15.2 Example: Changing Settings

The two most important settings are *auto_tidyup* and *auto_tidyup_atol* as they control whether the small elements of a quantum object should be removed, and what number should be considered as the cut-off tolerance. Modifying these, or any other parameters, is quite simple:

```
>>> qutip.settings.core["auto_tidyup"] = False
```

The settings can also be changed for a code block:

```
>>> with qutip.CoreOptions(atol=1e-5):
>>>     assert qutip.qeye(2) * 1e-9 == qutip.qzero(2)
```

3.16 Measurement of Quantum Objects

Note: New in QuTiP 4.6

3.16.1 Introduction

Measurement is a fundamental part of the standard formulation of quantum mechanics and is the process by which classical readings are obtained from a quantum object. Although the interpretation of the procedure is at times contentious, the procedure itself is mathematically straightforward and is described in many good introductory texts.

Here we will show you how to perform simple measurement operations on QuTiP objects. The same functions `measure` and `measurement_statistics` can be used to handle both observable-style measurements and projective style measurements.

3.16.2 Performing a basic measurement (Observable)

First we need to select some states to measure. For now, let us create an *up* state and a *down* state:

```
up = basis(2, 0)
down = basis(2, 1)
```

which represent spin-1/2 particles with their spin pointing either up or down along the z-axis.

We choose what to measure (in this case) by selecting a **measurement operator**. For example, we could select `sigmaz` which measures the z-component of the spin of a spin-1/2 particle, or `sigmax` which measures the x-component:

```
spin_z = sigmaz()
spin_x = sigmax()
```

How do we know what these operators measure? The answer lies in the measurement procedure itself:

- A quantum measurement transforms the state being measured by projecting it into one of the eigenvectors of the measurement operator.
- Which eigenvector to project onto is chosen probabilistically according to the square of the amplitude of the state in the direction of the eigenvector.
- The value returned by the measurement is the eigenvalue corresponding to the chosen eigenvector.

Note: How to interpret this “random choosing” is the famous “quantum measurement problem”.

The eigenvectors of `spin_z` are the states with their spin pointing either up or down, so it measures the component of the spin along the z-axis.

The eigenvectors of `spin_x` are the states with their spin pointing either left or right, so it measures the component of the spin along the x-axis.

When we measure our *up* and *down* states using the operator `spin_z`, we always obtain:

```
from qutip.measurement import measure, measurement_statistics

measure(up, spin_z) == (1.0, up)

measure(down, spin_z) == (-1.0, down)
```

because *up* is the eigenvector of *spin_z* with eigenvalue *1.0* and *down* is the eigenvector with eigenvalue *-1.0*. The minus signs are just an arbitrary global phase – *up* and *-up* represent the same quantum state.

Neither eigenvector has any component in the direction of the other (they are orthogonal), so *measure(spin_z, up)* returns the state *up* 100% percent of the time and *measure(spin_z, down)* returns the state *down* 100% of the time.

Note how *measure* returns a pair of values. The first is the measured value, i.e. an eigenvalue of the operator (e.g. *1.0*), and the second is the state of the quantum system after the measurement, i.e. an eigenvector of the operator (e.g. *up*).

Now let us consider what happens if we measure the x-component of the spin of *up*:

```
measure(up, spin_x)
```

The *up* state is not an eigenvector of *spin_x*. *spin_x* has two eigenvectors which we will call *left* and *right*. The *up* state has equal components in the direction of these two vectors, so measurement will select each of them 50% of the time.

These *left* and *right* states are:

```
left = (up - down).unit()
right = (up + down).unit()
```

When *left* is chosen, the result of the measurement will be *(-1.0, -left)*.

When *right* is chosen, the result of measurement will be *(1.0, right)*.

Note: When *measure* is invoked with the second argument being an observable, it acts as an alias to *measure_observable*.

3.16.3 Performing a basic measurement (Projective)

We can also choose what to measure by specifying a *list of projection operators*. For example, we could select the projection operators $|0\rangle\langle 0|$ and $|1\rangle\langle 1|$ which measure the state in the $|0\rangle, |1\rangle$ basis. Note that these projection operators are simply the projectors determined by the eigenstates of the *sigmaz* operator.

```
Z0, Z1 = ket2dm(basis(2, 0)), ket2dm(basis(2, 1))
```

The probabilities and respective output state are calculated for each projection operator.

```
measure(up, [Z0, Z1]) == (0, up)
measure(down, [Z0, Z1]) == (1, down)
```

In this case, the projection operators are conveniently eigenstates corresponding to subspaces of dimension 1. However, this might not be the case, in which case it is not possible to have unique eigenvalues for each eigenstate. Suppose we want to measure only the first qubit in a two-qubit system. Consider the two qubit state $|0+\rangle$

```
state_0 = basis(2, 0)
state_plus = (basis(2, 0) + basis(2, 1)).unit()
state_0plus = tensor(state_0, state_plus)
```

Now, suppose we want to measure only the first qubit in the computational basis. We can do that by measuring with the projection operators $|0\rangle\langle 0| \otimes I$ and $|1\rangle\langle 1| \otimes I$.

```
PZ1 = [tensor(Z0, identity(2)), tensor(Z1, identity(2))]
PZ2 = [tensor(identity(2), Z0), tensor(identity(2), Z1)]
```

Now, as in the previous example, we can measure by supplying a list of projection operators and the state.

```
measure(state_0plus, PZ1) == (0, state_0plus)
```

The output of the measurement is the index of the measurement outcome as well as the output state on the full Hilbert space of the input state. It is crucial to note that we do not discard the measured qubit after measurement (as opposed to when measuring on quantum hardware).

Note: When `measure` is invoked with the second argument being a list of projectors, it acts as an alias to `measure_povm`.

The `measure` function can perform measurements on density matrices too. You can read about these and other details at `measure_povm` and `measure_observable`.

Now you know how to measure quantum states in QuTiP!

3.16.4 Obtaining measurement statistics(Observable)

You've just learned how to perform measurements in QuTiP, but you've also learned that measurements are probabilistic. What if instead of just making a single measurement, we want to determine the probability distribution of a large number of measurements?

One way would be to repeat the measurement many times – and this is what happens in many quantum experiments. In QuTiP one could simulate this using:

```
results = {1.0: 0, -1.0: 0} # 1 and -1 are the possible outcomes
for _ in range(1000):
    value, new_state = measure(up, spin_x)
    results[round(value)] += 1
print(results)
```

Output:

```
{1.0: 497, -1.0: 503}
```

which measures the x-component of the spin of the `up` state 1000 times and stores the results in a dictionary. Afterwards we expect to have seen the result `1.0` (i.e. left) roughly 500 times and the result `-1.0` (i.e. right) roughly 500 times, but, of course, the number of each will vary slightly each time we run it.

But what if we want to know the distribution of results precisely? In a physical system, we would have to perform the measurement many many times, but in QuTiP we can peak at the state itself and determine the probability distribution of the outcomes exactly in a single line:

```
>>> eigenvalues, eigenstates, probabilities = measurement_statistics(up, spin_x)

>>> eigenvalues
array([-1., 1.])

>>> eigenstates
array([Quantum object: dims = [[2], [1]], shape = (2, 1), type = ket
Qobj data =
[[ 0.70710678]
 [-0.70710678]],
      Quantum object: dims = [[2], [1]], shape = (2, 1), type = ket
Qobj data =
[[0.70710678]
 [0.70710678]]], dtype=object)

>>> probabilities
[0.5000000000000001, 0.4999999999999999]
```

The `measurement_statistics` function then returns three values when called with a single observable:

- *eigenvalues* is an array of eigenvalues of the measurement operator, i.e. a list of the possible measurement results. In our example the value is `array([-1., -1.])`.
- *eigenstates* is an array of the eigenstates of the measurement operator, i.e. a list of the possible final states after the measurement is complete. Each element of the array is a `Qobj`.
- *probabilities* is a list of the probabilities of each measurement result. In our example the value is `[0.5, 0.5]` since the *up* state has equal probability of being measured to be in the left (-1.0) or right (1.0) eigenstates.

All three lists are in the same order – i.e. the first eigenvalue is `eigenvalues[0]`, its corresponding eigenstate is `eigenstates[0]`, and its probability is `probabilities[0]`, and so on.

Note: When `measurement_statistics` is invoked with the second argument being an observable, it acts as an alias to `measurement_statistics_observable`.

3.16.5 Obtaining measurement statistics(Projective)

Similarly, when we want to obtain measurement statistics for projection operators, we can use the `measurement_statistics` function with the second argument being a list of projectors. Consider again, the state $|0+\rangle$. Suppose, now we want to obtain the measurement outcomes for the second qubit. We must use the projectors specified earlier by *PZ2* which allow us to measure only on the second qubit. Since the second qubit has the state $|+\rangle$, we get the following result.

```
collapsed_states, probabilities = measurement_statistics(state_0plus, PZ2)

print(collapsed_states)
```

Output:

```
[Quantum object: dims = [[2, 2], [1, 1]], shape = (4, 1), type = ket
Qobj data =
[[1.]
 [0.]
 [0.]
 [0.]], Quantum object: dims = [[2, 2], [1, 1]], shape = (4, 1), type = ket
Qobj data =
[[0.]
 [1.]
 [0.]
 [0.]]]
```

```
print(probabilities)
```

Output:

```
[0.49999999999999999, 0.49999999999999999]
```

The function `measurement_statistics` then returns two values:

- *collapsed_states* is an array of the possible final states after the measurement is complete. Each element of the array is a `Qobj`.
- *probabilities* is a list of the probabilities of each measurement outcome.

Note that the collapsed_states are exactly $|00\rangle$ and $|01\rangle$ with equal probability, as expected. The two lists are in the same order.

Note: When `measurement_statistics` is invoked with the second argument being a list of projectors, it acts as an alias to `measurement_statistics_povm`.

The `measurement_statistics` function can provide statistics for measurements of density matrices too. You can read about these and other details at `measurement_statistics_observable` and `measurement_statistics_povm`.

Furthermore, the `measure_povm` and `measurement_statistics_povm` functions can handle POVM measurements which are more general than projective measurements.

Chapter 4

Gallery

This is the gallery for QuTiP examples, you can click on the image to see the source code.

Chapter 5

API documentation

This chapter contains automatically generated API documentation, including a complete list of QuTiP's public classes and functions.

5.1 Classes

5.1.1 Qobj

class Qobj (*arg=None, dims=None, type=None, copy=True, superrep=None, isherm=None, isunitary=None*)

A class for representing quantum objects, such as quantum operators and states.

The Qobj class is the QuTiP representation of quantum operators and state vectors. This class also implements math operations $+$, $-$, $*$ between Qobj instances (and $/$ by a C-number), as well as a collection of common operator/state operations. The Qobj constructor optionally takes a dimension `list` and/or shape `list` as arguments.

Parameters

inpt: array_like Data for vector/matrix representation of the quantum object.

dims: list Dimensions of object used for tensor products.

type: {'bra', 'ket', 'oper', 'operator-ket', 'operator-bra', 'super'} The type of quantum object to be represented.

shape: list Shape of underlying data structure (matrix shape).

copy: bool Flag specifying whether Qobj should get a copy of the input data, or use the original.

Attributes

data [array_like] Sparse matrix characterizing the quantum object.

dims [list] List of dimensions keeping track of the tensor structure.

shape [list] Shape of the underlying *data* array.

type [str] Type of quantum object: 'bra', 'ket', 'oper', 'operator-ket', 'operator-bra', or 'super'.

superrep [str] Representation used if *type* is 'super'. One of 'super' (Liouville form) or 'choi' (Choi matrix with $\text{tr} = \text{dimension}$).

isherm [bool] Indicates if quantum object represents Hermitian operator.

isunitary [bool] Indicates if quantum object represents unitary operator.

iscp [bool] Indicates if the quantum object represents a map, and if that map is completely positive (CP).

ishp [bool] Indicates if the quantum object represents a map, and if that map is hermicity preserving (HP).

istp [bool] Indicates if the quantum object represents a map, and if that map is trace preserving (TP).

iscptp [bool] Indicates if the quantum object represents a map that is completely positive and trace preserving (CPTP).

isket [bool] Indicates if the quantum object represents a ket.

isbra [bool] Indicates if the quantum object represents a bra.

isoper [bool] Indicates if the quantum object represents an operator.

issuper [bool] Indicates if the quantum object represents a superoperator.

isoperket [bool] Indicates if the quantum object represents an operator in column vector form.

isoperbra [bool] Indicates if the quantum object represents an operator in row vector form.

Methods

copy()	Create copy of Qobj
conj()	Conjugate of quantum object.
cosm()	Cosine of quantum object.
dag()	Adjoint (dagger) of quantum object.
dnorm()	Diamond norm of quantum operator.
dual_chan()	Dual channel of quantum object representing a CP map.
eigenenergies(sparse=False, sort='low', eigvals=0, tol=0, maxiter=100000)	Returns eigenenergies (eigenvalues) of a quantum object.
eigenstates(sparse=False, sort='low', eigvals=0, tol=0, maxiter=100000)	Returns eigenenergies and eigenstates of quantum object.
expm()	Matrix exponential of quantum object.
full(order='C')	Returns dense array of quantum object <i>data</i> attribute.
groundstate(sparse=False, tol=0, max-iter=100000)	Returns eigenvalue and eigenket for the groundstate of a quantum object.
inv()	Return a Qobj corresponding to the matrix inverse of the operator.
matrix_element(bra, ket)	Returns the matrix element of operator between <i>bra</i> and <i>ket</i> vectors.
norm(norm='tr', sparse=False, tol=0, max-iter=100000)	Returns norm of a ket or an operator.
permute(order)	Returns composite qobj with indices reordered.
proj()	Computes the projector for a ket or bra vector.
ptrace(sel)	Returns quantum object for selected dimensions after performing partial trace.
sinm()	Sine of quantum object.
sqrtn()	Matrix square root of quantum object.
tidyup(atol=1e-12)	Removes small elements from quantum object.
tr()	Trace of quantum object.
trans()	Transpose of quantum object.
transform(inpt, inverse=False)	Performs a basis transformation defined by <i>inpt</i> matrix.
trunc_neg(method='clip')	Removes negative eigenvalues and returns a new Qobj that is a valid density operator.
unit(norm='tr', sparse=False, tol=0, max-iter=100000)	Returns normalized quantum object.

check_herm()

Check if the quantum object is hermitian.

Returns

isherm [bool] Returns the new value of isherm property.

conj()

Get the element-wise conjugation of the quantum object.

contract(inplace=False)

Contract subspaces of the tensor structure which are 1D. Not defined on superoperators. If all dimensions are scalar, a Qobj of dimension $[[1], [1]]$ is returned, i.e. `_multiple_` scalar dimensions are contracted, but one is left.

Parameters

inplace: bool, optional If `True`, modify the dimensions in place. If `False`, return a copied object.

Returns

out: *Qobj* Quantum object with dimensions contracted. Will be `self` if `inplace` is `True`.

copy()
Create identical copy

cosm()
Cosine of a quantum operator.
Operator must be square.

Returns

oper [*qutip.Qobj*] Matrix cosine of operator.

Raises

TypeError Quantum object is not square.

Notes

Uses the `Q.expm()` method.

dag()
Get the Hermitian adjoint of the quantum object.

diag()
Diagonal elements of quantum object.

Returns

diags [array] Returns array of `real` values if operators is Hermitian, otherwise `complex` values are returned.

dnorm(*B=None*)
Calculates the diamond norm, or the diamond distance to another operator.

Parameters

B [*qutip.Qobj* or `None`] If `B` is not `None`, the diamond distance $d(A, B) = \text{dnorm}(A - B)$ between this operator and `B` is returned instead of the diamond norm.

Returns

d [float] Either the diamond norm of this operator, or the diamond distance from this operator to `B`.

dual_chan()
Dual channel of quantum object representing a completely positive map.

eigenenergies (*sparse=False, sort='low', eigvals=0, tol=0, maxiter=100000*)
Eigenenergies of a quantum object.

Eigenenergies (eigenvalues) are defined for operators or superoperators only.

Parameters

sparse [bool] Use sparse Eigensolver

sort [str] Sort eigenvalues 'low' to high, or 'high' to low.

eigvals [int] Number of requested eigenvalues. Default is all eigenvalues.

tol [float] Tolerance used by sparse Eigensolver (0=machine precision). The sparse solver may not converge if the tolerance is set too low.

maxiter [int] Maximum number of iterations performed by sparse solver (if used).

Returns

eigvals [array] Array of eigenvalues for operator.

Notes

The sparse eigensolver is much slower than the dense version. Use sparse only if memory requirements demand it.

eigenstates (*sparse=False, sort='low', eigvals=0, tol=0, maxiter=100000, phase_fix=None*)
Eigenstates and eigenenergies.

Eigenstates and eigenenergies are defined for operators and superoperators only.

Parameters

- sparse** [bool] Use sparse Eigensolver
- sort** [str] Sort eigenvalues (and vectors) 'low' to high, or 'high' to low.
- eigvals** [int] Number of requested eigenvalues. Default is all eigenvalues.
- tol** [float] Tolerance used by sparse Eigensolver (0 = machine precision). The sparse solver may not converge if the tolerance is set too low.
- maxiter** [int] Maximum number of iterations performed by sparse solver (if used).
- phase_fix** [int, None] If not None, set the phase of each kets so that ket[phase_fix,0] is real positive.

Returns

- eigvals** [array] Array of eigenvalues for operator.
- eigvecs** [array] Array of quantum operators representing the operator eigenkets. Order of eigenkets is determined by order of eigenvalues.

Notes

The sparse eigensolver is much slower than the dense version. Use sparse only if memory requirements demand it.

expm (*dtype=<class 'qutip.core.data.dense.Dense'>*)
Matrix exponential of quantum operator.

Input operator must be square.

Parameters

- dtype** [type] The data-layer type that should be output. As the matrix exponential is almost dense, this defaults to outputting dense matrices.

Returns

- oper** [qutip.Qobj] Exponentiated quantum operator.

Raises

- TypeError** Quantum operator is not square.

full (*order='C', squeeze=False*)
Dense array from quantum object.

Parameters

- order** [str {'C', 'F'}] Return array in C (default) or Fortran ordering.
- squeeze** [bool {False, True}] Squeeze output array.

Returns

- data** [array] Array of complex data from quantum objects *data* attribute.

groundstate (*sparse=False, tol=0, maxiter=100000, safe=True*)

Ground state Eigenvalue and Eigenvector.

Defined for quantum operators or superoperators only.

Parameters

sparse [bool] Use sparse Eigensolver

tol [float] Tolerance used by sparse Eigensolver (0 = machine precision). The sparse solver may not converge if the tolerance is set too low.

maxiter [int] Maximum number of iterations performed by sparse solver (if used).

safe [bool (default=True)] Check for degenerate ground state

Returns

eigval [float] Eigenvalue for the ground state of quantum operator.

eigvec [qutip.Qobj] Eigenket for the ground state of quantum operator.

Notes

The sparse eigensolver is much slower than the dense version. Use sparse only if memory requirements demand it.

inv (*sparse=False*)

Matrix inverse of a quantum operator

Operator must be square.

Returns

oper [qutip.Qobj] Matrix inverse of operator.

Raises

TypeError Quantum object is not square.

logm ()

Matrix logarithm of quantum operator.

Input operator must be square.

Returns

oper [qutip.Qobj] Logarithm of the quantum operator.

Raises

TypeError Quantum operator is not square.

matrix_element (*bra, ket*)

Calculates a matrix element.

Gives the matrix element for the quantum object sandwiched between a *bra* and *ket* vector.

Parameters

bra [qutip.Qobj] Quantum object of type 'bra' or 'ket'

ket [qutip.Qobj] Quantum object of type 'ket'.

Returns

elem [complex] Complex valued matrix element.

Notes

It is slightly more computationally efficient to use a ket vector for the 'bra' input.

norm (*norm=None, kwargs=None*)

Norm of a quantum object.

Default norm is L2-norm for kets and trace-norm for operators. Other ket and operator norms may be specified using the *norm* parameter.

Parameters

norm [str] Which type of norm to use. Allowed values for vectors are 'l2' and 'max'. Allowed values for matrices are 'tr' for the trace norm, 'fro' for the Frobenius norm, 'one' and 'max'.

kwargs [dict] Additional keyword arguments to pass on to the relevant norm solver. See details for each norm function in `data.norm`.

Returns

norm [float] The requested norm of the operator or state quantum object.

overlap (*other*)

Overlap between two state vectors or two operators.

Gives the overlap (inner product) between the current bra or ket Qobj and another bra or ket Qobj. It gives the Hilbert-Schmidt overlap when one of the Qobj is an operator/density matrix.

Parameters

other [qutip.Qobj] Quantum object for a state vector of type 'ket', 'bra' or density matrix.

Returns

overlap [complex] Complex valued overlap.

Raises

TypeError Can only calculate overlap between a bra, ket and density matrix quantum objects.

permute (*order*)

Permute the tensor structure of a quantum object. For example, `qutip.tensor(x, y).permute([1, 0])` will give the same result as `qutip.tensor(y, x)` and `qutip.tensor(a, b, c).permute([1, 2, 0])` will be the same as `qutip.tensor(b, c, a)`

For regular objects (bras, kets and operators) we expect *order* to be a flat list of integers, which specifies the new order of the tensor product.

For superoperators, we expect *order* to be something like `[[0, 2], [1, 3]]` which tells us to permute according to `[0, 2, 1, 3]`, and then group indices according to the length of each sub-list. As another example, permuting a superoperator with dimensions of `[[[1, 2, 3], [1, 2, 3]], [[1, 2, 3], [1, 2, 3]]]` by an order `[[0, 3], [1, 4], [2, 5]]` should give a new object with dimensions `[[[1, 1], [2, 2], [3, 3]], [[1, 1], [2, 2], [3, 3]]]`.

Parameters

order [list] List of indices specifying the new tensor order.

Returns

P [qutip.Qobj] Permuted quantum object.

proj ()

Form the projector from a given ket or bra vector.

Parameters

Q [qutip.Qobj] Input bra or ket vector

Returns

P [qutip.Qobj] Projection operator.

ptrace (*sel*, *dtype=None*)

Take the partial trace of the quantum object leaving the selected subspaces. In other words, trace out all subspaces which are `_not_` passed.

This is typically a function which acts on operators; bras and kets will be promoted to density matrices before the operation takes place since the partial trace is inherently undefined on pure states.

For operators which are currently being represented as states in the superoperator formalism (i.e. the object has type *operator-ket* or *operator-bra*), the partial trace is applied as if the operator were in the conventional form. This means that for any operator *x*, `operator_to_vector(x).ptrace(0) == operator_to_vector(x.ptrace(0))` and similar for *operator-bra*.

The story is different for full superoperators. In the formalism that QuTiP uses, if an operator has dimensions (*dims*) of `[[2, 3], [2, 3]]` then it can be represented as a state on a Hilbert space of dimensions `[2, 3, 2, 3]`, and a superoperator would be an operator which acts on this joint space. This function performs the partial trace on superoperators by letting the selected components refer to elements of the `_joint_space_`, and then returns a regular operator (of type *oper*).

Parameters

sel [int or iterable of int] An `int` or `list` of components to keep after partial trace. The selected subspaces will `_not_` be reordered, no matter order they are supplied to *ptrace*.

Returns

oper [qutip.Qobj] Quantum object representing partial trace with selected components remaining.

purity ()

Calculate purity of a quantum object.

Returns

state_purity [float] Returns the purity of a quantum object. For a pure state, the purity is 1. For a mixed state of dimension *d*, $1/d \leq \text{purity} < 1$.

sinm ()

Sine of a quantum operator.

Operator must be square.

Returns

oper [qutip.Qobj] Matrix sine of operator.

Raises

TypeError Quantum object is not square.

Notes

Uses the `Q.expm()` method.

sqrtn (*sparse=False, tol=0, maxiter=100000*)

Sqrt of a quantum operator. Operator must be square.

Parameters

sparse [bool] Use sparse eigenvalue/vector solver.

tol [float] Tolerance used by sparse solver (0 = machine precision).

maxiter [int] Maximum number of iterations used by sparse solver.

Returns

oper [qutip.Qobj] Matrix square root of operator.

Raises

TypeError Quantum object is not square.

Notes

The sparse eigensolver is much slower than the dense version. Use sparse only if memory requirements demand it.

tidyup (*atol=None*)

Removes small elements from the quantum object.

Parameters

atol [float] Absolute tolerance used by tidyup. Default is set via qutip global settings parameters.

Returns

oper [qutip.Qobj] Quantum object with small elements removed.

to (*data_type*)

Convert the underlying data store of this *Qobj* into a different storage representation.

The different storage representations available are the “data-layer types” which are known to *qutip.data.to*. By default, these are *qutip.data.Dense* and *qutip.data.CSR*, which respectively construct a dense matrix store and a compressed sparse row one. Certain algorithms and operations may be faster or more accurate when using a more appropriate data store.

If the data store is already in the format requested, the function returns *self*. Otherwise, it returns a copy of itself with the data store in the new type.

Parameters

data_type [type] The data-layer type that the data of this *Qobj* should be converted to.

Returns

Qobj A new *Qobj* if a type conversion took place with the data stored in the requested format, or *self* if not.

tr ()

Trace of a quantum object.

Returns

trace [float] Returns the trace of the quantum object.

trans ()

Get the matrix transpose of the quantum operator.

Returns

oper [*Qobj*] Transpose of input operator.

transform (*inpt*, *inverse=False*)

Basis transform defined by input array.

Input array can be a *matrix* defining the transformation, or a *list* of kets that defines the new basis.

Parameters

inpt [*array_like*] A *matrix* or *list* of kets defining the transformation.

inverse [*bool*] Whether to return inverse transformation.

Returns

oper [*qutip.Qobj*] Operator in new basis.

Notes

This function is still in development.

trunc_neg (*method='clip'*)

Truncates negative eigenvalues and renormalizes.

Returns a new *Qobj* by removing the negative eigenvalues of this instance, then renormalizing to obtain a valid density operator.

Parameters

method [*str*] Algorithm to use to remove negative eigenvalues. “clip” simply discards negative eigenvalues, then renormalizes. “sgs” uses the SGS algorithm (doi:10/bb76) to find the positive operator that is nearest in the Schatten 2-norm.

Returns

oper [*qutip.Qobj*] A valid density operator.

unit (*inplace=False*, *norm=None*, *kwargs=None*)

Operator or state normalized to unity. Uses norm from *Qobj.norm()*.

Parameters

inplace [*bool*] Do an in-place normalization

norm [*str*] Requested norm for states / operators.

kwargs [*dict*] Additional key-word arguments to be passed on to the relevant norm function (see *norm* for more details).

Returns

obj [*qutip.Qobj*] Normalized quantum object. Will be the *self* object if in place.

5.1.2 QobjEvo

class QobjEvo

A class for representing time-dependent quantum objects, such as quantum operators and states.

Importantly, *QobjEvo* instances are used to represent such time-dependent quantum objects when working with QuTiP solvers.

A *QobjEvo* instance may be constructed from one of the following:

- a callable *f*(*t*: *double*, *args*: *dict*) -> *Qobj* that returns the value of the quantum object at time *t*.

- a `[Qobj, Coefficient]` pair, where `Coefficient` may also be any item that can be used to construct a coefficient (e.g. a function, a numpy array of coefficient values, a string expression).
- a `Qobj` (which creates a constant *QobjEvo* term).
- a list of such callables, pairs or `Qobjs`.
- a *QobjEvo* (in which case a copy is created, all other arguments are ignored except `args` which, if passed, replaces the existing arguments).

Parameters

Q_object [callable, list or `Qobj`] A specification of the time-depended quantum object. See the paragraph above for a full description and the examples section below for examples.

args [dict, optional] A dictionary that contains the arguments for the coefficients. Arguments may be omitted if no function or string coefficients that require arguments are present.

tlist [array-like, optional] A list of times corresponding to the values of the coefficients supplied as numpy arrays. If no coefficients are supplied as numpy arrays, `tlist` may be omitted, otherwise it is required.

The times in `tlist` do not need to be equidistant, but must be sorted.

By default, a cubic spline interpolation will be used to interpolate the value of the (numpy array) coefficients at time `t`. If the coefficients are to be treated as step functions, pass the argument `order=0` (see below).

order [int, default=3] Order of the spline interpolation that is to be used to interpolate the value of the (numpy array) coefficients at time `t`. 0 use previous or left value.

copy [bool, default=True] Whether to make a copy of the `Qobj` instances supplied in the `Q_object` parameter.

compress [bool, default=True] Whether to compress the *QobjEvo* instance terms after the instance has been created.

This sums the constant terms in a single term and combines `[Qobj, coefficient]` pairs with the same `Qobj` into a single pair containing the sum of the coefficients.

See *compress*.

function_style [{None, "pythonic", "dict", "auto"}] The style of function signature used by callables in `Q_object`. If style is None, the value of `qutip.settings.core["function_coefficient_style"]` is used. Otherwise the supplied value overrides the global setting.

Examples

A *QobjEvo* constructed from a function:

```
def f(t, args):
    return qutip.qeye(N) * np.exp(args['w'] * t)

QobjEvo(f, args={'w': 1j})
```

For list based *QobjEvo*, the list must consist of `:obj`~Qobj`` or `[Qobj, Coefficient]` pairs:

```
QobjEvo([H0, [H1, coeff1], [H2, coeff2]], args=args)
```

The coefficients may be specified either using a `Coefficient` object or by a function, string, numpy array or any object that can be passed to the `coefficient` function. See the documentation of `coefficient` for a full description.

An example of a coefficient specified by a function:

```
def f1_t(t, args):
    return np.exp(-1j * t * args["w1"])

QobjEvo([[H1, f1_t]], args={"w1": 1.})
```

And of coefficients specified by string expressions:

```
H = QobjEvo(
    [H0, [H1, 'exp(-1j*w1*t)'], [H2, 'cos(w2*t)']],
    args={"w1": 1., "w2": 2.}
)
```

Coefficients maybe also be expressed as numpy arrays giving a list of the coefficient values:

```
tlist = np.logspace(-5, 0, 100)
H = QobjEvo(
    [H0, [H1, np.exp(-1j * tlist)], [H2, np.cos(2. * tlist)]],
    tlist=tlist
)
```

The coefficients array must have the same len as the tlist.

A *QobjEvo* may also be built using simple arithmetic operations combining *Qobj* with *Coefficient*, for example:

```
coeff = qutip.coefficient("exp(-1j*w1*t)", args={"w1": 1})
qevo = H0 + H1 * coeff
```

Attributes

dims [list] List of dimensions keeping track of the tensor structure.

shape [(int, int)] List of dimensions keeping track of the tensor structure.

type [str] Type of quantum object: 'bra', 'ket', 'oper', 'operator-ket', 'operator-bra', or 'super'.

superrep [str] Representation used if *type* is 'super'. One of 'super' (Liouville form) or 'choi' (Choi matrix with tr = dimension).

arguments()

Update the arguments.

Parameters

_args [dict [optional]] New arguments as a dict. Update args with arguments(new_args).

****kwargs**: New arguments as a keywords. Update args with arguments(**new_args).

.. note:: If both the positional *_args* and keywords are passed new values from both will be used. If a key is present with both, the *_args* dict value will take priority.

compress()

Look for redundance in the *QobjEvo* components:

Constant parts, (*Qobj* without *Coefficient*) will be summed. Pairs [*Qobj*, *Coefficient*] with the same *Qobj* are merged.

Example: `[[sigmax(), f1], [sigmax(), f2]] -> [[sigmax(), f1+f2]]`

The *QobjEvo* is transformed inplace.

Returns

None

conj()

Get the element-wise conjugation of the quantum object.

copy()

Return a copy of this *QobjEvo*

dag()

Get the Hermitian adjoint of the quantum object.

expect()

Expectation value of this operator at time t with the state.

Parameters

t [float] Time of the operator to apply.

state [Qobj] right matrix of the product

Returns

expect [float or complex] `state.adjoint() @ self @ state` if state is a ket. `trace(self @ matrix)` if state is an operator or operator-ket.

expect_data()

Expectation is defined as `state.adjoint() @ self @ state` if state is a vector, or state is an operator and self is a superoperator. If state is an operator and self is an operator, then expectation is `trace(self @ matrix)`.

isconstant

Does the system change depending on t

isoper

Indicates if the system represents an operator.

issuper

Indicates if the system represents a superoperator.

linear_map()

Apply mapping to each Qobj contribution.

Example: `QobjEvo([sigmax(), coeff]).linear_map(spre)` gives the same result as `QobjEvo([spre(sigmax()), coeff])`

Returns

QobjEvo Modified object

Notes

Does not modify the coefficients, thus `linear_map(conj)` would not give the the conjugate of the *QobjEvo*. It's only valid for linear transformations.

matmul()

Product of this operator at time t to the state. `self(t) @ state`

Parameters

t [float] Time of the operator to apply.

state [Qobj] right matrix of the product

Returns

product [Qobj] The result product as a Qobj

matmul_data()

Compute `out += self(t) @ state`

num_elements

Number of parts composing the system

tidyup()

Removes small elements from quantum object.

to()

Convert the underlying data store of all component into the desired storage representation.

The different storage representations available are the “data-layer types”. By default, these are *qutip.data.Dense* and *qutip.data.CSR*, which respectively construct a dense matrix store and a compressed sparse row one.

The *QobjEvo* is transformed inplace.

Parameters

data_type [type] The data-layer type that the data of this *Qobj* should be converted to.

Returns

None

trans()

Transpose of the quantum object

5.1.3 Bloch sphere

class Bloch (*fig=None, axes=None, view=None, figsize=None, background=False*)

Class for plotting data on the Bloch sphere. Valid data can be either points, vectors, or *Qobj* objects.

Attributes

axes [matplotlib.axes.Axes] User supplied Matplotlib axes for Bloch sphere animation.

fig [matplotlib.figure.Figure] User supplied Matplotlib Figure instance for plotting Bloch sphere.

font_color [str, default ‘black’] Color of font used for Bloch sphere labels.

font_size [int, default 20] Size of font used for Bloch sphere labels.

frame_alpha [float, default 0.1] Sets transparency of Bloch sphere frame.

frame_color [str, default ‘gray’] Color of sphere wireframe.

frame_width [int, default 1] Width of wireframe.

point_color [list, default [‘b’, ‘r’, ‘g’, ‘#CC6600’]] List of colors for Bloch sphere point markers to cycle through, i.e. by default, points 0 and 4 will both be blue (‘b’).

point_marker [list, default [‘o’, ‘s’, ‘d’, ‘^’]] List of point marker shapes to cycle through.

point_size [list, default [25, 32, 35, 45]] List of point marker sizes. Note, not all point markers look the same size when plotted!

sphere_alpha [float, default 0.2] Transparency of Bloch sphere itself.

sphere_color [str, default ‘#FFDDDD’] Color of Bloch sphere.

figsize [list, default [7, 7]] Figure size of Bloch sphere plot. Best to have both numbers the same; otherwise you will have a Bloch sphere that looks like a football.

vector_color [list, [‘g’, ‘#CC6600’, ‘b’, ‘r’]] List of vector colors to cycle through.

vector_width [int, default 5] Width of displayed vectors.

vector_style [str, default ‘->’] Vector arrowhead style (from matplotlib’s arrow style).

vector_mutation [int, default 20] Width of vectors arrowhead.

view [list, default [-60, 30]] Azimuthal and Elevation viewing angles.

xlabel [list, default ["\$x\$", ""]] List of strings corresponding to +x and -x axes labels, respectively.

xlpos [list, default [1.1, -1.1]] Positions of +x and -x labels respectively.

ylabel [list, default ["\$y\$", ""]] List of strings corresponding to +y and -y axes labels, respectively.

ylpos [list, default [1.2, -1.2]] Positions of +y and -y labels respectively.

zlabel [list, default ['\$\leftl0\right>\$', '\$\leftl1\right>\$']] List of strings corresponding to +z and -z axes labels, respectively.

zlpos [list, default [1.2, -1.2]] Positions of +z and -z labels respectively.

add_annotation (*state_or_vector*, *text*, ***kwargs*)

Add a text or LaTeX annotation to Bloch sphere, parametrized by a qubit state or a vector.

Parameters

state_or_vector [Qobj/array/list/tuple] Position for the annotaion. Qobj of a qubit or a vector of 3 elements.

text [str] Annotation text. You can use LaTeX, but remember to use raw string e.g. `r"$\angle x \angle $"` or escape backslashes e.g. `"$\angle x \angle $"`.

kwargs: Options as for `mplot3d.axes3d.text`, including: `fontsize`, `color`, `horizontalalignment`, `verticalalignment`.

add_arc (*start*, *end*, *fmt='b'*, *steps=None*, ***kwargs*)

Adds an arc between two points on a sphere. The arc is set to be blue solid curve by default.

The start and end points must be on the same sphere (i.e. have the same radius) but need not be on the unit sphere.

Parameters

start [Qobj or array-like] Array with cartesian coordinates of the first point, or a state vector or density matrix that can be mapped to a point on or within the Bloch sphere.

end [Qobj or array-like] Array with cartesian coordinates of the second point, or a state vector or density matrix that can be mapped to a point on or within the Bloch sphere.

fmt [str, default: "b"] A matplotlib format string for rendering the arc.

steps [int, default: None] The number of segments to use when rendering the arc. The default uses 100 steps times the distance between the start and end points, with a minimum of 2 steps.

****kwargs** [dict] Additional parameters to pass to the matplotlib `.plot` function when rendering this arc.

add_line (*start*, *end*, *fmt='k'*, ***kwargs*)

Adds a line segment connecting two points on the bloch sphere.

The line segment is set to be a black solid line by default.

Parameters

start [Qobj or array-like] Array with cartesian coordinates of the first point, or a state vector or density matrix that can be mapped to a point on or within the Bloch sphere.

end [Qobj or array-like] Array with cartesian coordinates of the second point, or a state vector or density matrix that can be mapped to a point on or within the Bloch sphere.

fmt [str, default: "k"] A matplotlib format string for rendering the line.

****kwargs** [dict] Additional parameters to pass to the matplotlib `.plot` function when rendering this line.

add_points (*points, meth='s', colors=None, alpha=1.0*)

Add a list of data points to Bloch sphere.

Parameters

points [array_like] Collection of data points.

meth [{ 's', 'm', 'l' }] Type of points to plot, use 'm' for multicolored, 'l' for points connected with a line.

colors [array_like] Optional array with colors for the points. A single color for meth 's', and list of colors for meth 'm'

alpha [float, default=1.] Transparency value for the vectors. Values between 0 and 1.

.. note:: When using `meth=l` in QuTiP 4.6, the line transparency defaulted to 0.75 and there was no way to alter it. When the `alpha` parameter was added in QuTiP 4.7, the default became `alpha=1.0` for values of `meth`.

add_states (*state, kind='vector', colors=None, alpha=1.0*)

Add a state vector Qobj to Bloch sphere.

Parameters

state [Qobj] Input state vector.

kind [{ 'vector', 'point' }] Type of object to plot.

colors [array_like] Optional array with colors for the states.

alpha [float, default=1.] Transparency value for the vectors. Values between 0 and 1.

add_vectors (*vectors, colors=None, alpha=1.0*)

Add a list of vectors to Bloch sphere.

Parameters

vectors [array_like] Array with vectors of unit length or smaller.

colors [array_like] Optional array with colors for the vectors.

alpha [float, default=1.] Transparency value for the vectors. Values between 0 and 1.

clear ()

Resets Bloch sphere data sets to empty.

make_sphere ()

Plots Bloch sphere and data sets.

render ()

Render the Bloch sphere and its data sets in on given figure and axes.

save (*name=None, format='png', dirc=None, dpin=None*)

Saves Bloch sphere to file of type `format` in directory `dirc`.

Parameters

name [str] Name of saved image. Must include path and format as well. i.e. `'/Users/Paul/Desktop/bloch.png'` This overrides the 'format' and 'dirc' arguments.

format [str] Format of output image.

dirc [str] Directory for output images. Defaults to current working directory.

dpin [int] Resolution in dots per inch.

Returns

File containing plot of Bloch sphere.

set_label_convention (*convention*)

Set x, y and z labels according to one of conventions.

Parameters

convention [string] One of the following:

- “original”
- “xyz”
- “sx sy sz”
- “01”
- “polarization jones”
- “polarization jones letters” see also: https://en.wikipedia.org/wiki/Jones_calculus
- “polarization stokes” see also: https://en.wikipedia.org/wiki/Stokes_parameters

show()

Display Bloch sphere and corresponding data sets.

Notes

When using inline plotting in Jupyter notebooks, any figure created in a notebook cell is displayed after the cell executes. Thus if you create a figure yourself and use it create a Bloch sphere with `b = Bloch(..., fig=fig)` and then call `b.show()` in the same cell, then the figure will be displayed twice. If you do create your own figure, the simplest solution to this is to not call `.show()` in the cell you create the figure in.

vector_mutation

Sets the width of the vectors arrowhead

vector_style

Style of Bloch vectors, default = ‘-|>’ (or ‘simple’)

vector_width

Width of Bloch vectors, default = 5

class Bloch3d (*fig=None*)

Class for plotting data on a 3D Bloch sphere using mayavi. Valid data can be either points, vectors, or qobj objects corresponding to state vectors or density matrices. for a two-state system (or subsystem).

Notes

The use of mayavi for 3D rendering of the Bloch sphere comes with a few limitations: I) You can not embed a Bloch3d figure into a matplotlib window. II) The use of LaTeX is not supported by the mayavi rendering engine. Therefore all labels must be defined using standard text. Of course you can post-process the generated figures later to add LaTeX using other software if needed.

Attributes

fig [instance {None}] User supplied Matplotlib Figure instance for plotting Bloch sphere.

font_color [str {‘black’}] Color of font used for Bloch sphere labels.

font_scale [float {0.08}] Scale for font used for Bloch sphere labels.

frame [bool {True}] Draw frame for Bloch sphere

frame_alpha [float {0.05}] Sets transparency of Bloch sphere frame.

frame_color [str {‘gray’}] Color of sphere wireframe.

frame_num [int {8}] Number of frame elements to draw.

frame_radius [floats {0.005}] Width of wireframe.

point_color [list {[‘r’, ‘g’, ‘b’, ‘y’]}] List of colors for Bloch sphere point markers to cycle through. i.e. By default, points 0 and 4 will both be blue (‘r’).

point_mode [string {‘sphere’, ‘cone’, ‘cube’, ‘cylinder’, ‘point’}] Point marker shapes.

point_size [float {0.075}] Size of points on Bloch sphere.

sphere_alpha [float {0.1}] Transparency of Bloch sphere itself.

sphere_color [str {‘#808080’}] Color of Bloch sphere.

size [list {[500,500]}] Size of Bloch sphere plot in pixels. Best to have both numbers the same otherwise you will have a Bloch sphere that looks like a football.

vector_color [list {[‘r’, ‘g’, ‘b’, ‘y’]}] List of vector colors to cycle through.

vector_width [int {3}] Width of displayed vectors.

view [list {[45,65]}] Azimuthal and Elevation viewing angles.

xlabel [list {[‘|x>’, ‘|’]}] List of strings corresponding to +x and -x axes labels, respectively.

xlpos [list {[1.07,-1.07]}] Positions of +x and -x labels respectively.

ylabel [list {[‘|y>’, ‘|’]}] List of strings corresponding to +y and -y axes labels, respectively.

ylpos [list {[1.07,-1.07]}] Positions of +y and -y labels respectively.

zlabel [list {[‘|0>’, ‘|1>’]}] List of strings corresponding to +z and -z axes labels, respectively.

zlpos [list {[1.07,-1.07]}] Positions of +z and -z labels respectively.

add_points (*points*, *meth*=‘s’, *alpha*=1.0)

Add a list of data points to bloch sphere.

Parameters

points [array/list] Collection of data points.

meth [str {‘s’, ‘m’}] Type of points to plot, use ‘m’ for multicolored.

alpha [float, default=1.] Transparency value for the vectors. Values between 0 and 1.

add_states (*state*, *kind*=‘vector’, *alpha*=1.0)

Add a state vector Qobj to Bloch sphere.

Parameters

state [qobj] Input state vector.

kind [str {‘vector’, ‘point’}] Type of object to plot.

alpha [float, default=1.] Transparency value for the vectors. Values between 0 and 1.

add_vectors (*vectors*, *alpha*=1.0)

Add a list of vectors to Bloch sphere.

Parameters

vectors [array/list] Array with vectors of unit length or smaller.

alpha [float, default=1.] Transparency value for the vectors. Values between 0 and 1.

clear ()

Resets the Bloch sphere data sets to empty.

make_sphere ()

Plots Bloch sphere and data sets.

plot_points ()

Plots points on the Bloch sphere.

plot_vectors()

Plots vectors on the Bloch sphere.

save (*name=None, format='png', dirc=None*)

Saves Bloch sphere to file of type *format* in directory *dirc*.

Parameters

name [str] Name of saved image. Must include path and format as well. i.e. `'/Users/Paul/Desktop/bloch.png'` This overrides the `'format'` and `'dirc'` arguments.

format [str] Format of output image. Default is `'png'`.

dirc [str] Directory for output images. Defaults to current working directory.

Returns

File containing plot of Bloch sphere.

show()

Display the Bloch sphere and corresponding data sets.

5.1.4 Distributions

class QFunc (*xvec, yvec, g: float = 1.4142135623730951, memory: float = 1024*)

Class-based method of calculating the Husimi-Q function of many different quantum states at fixed phase-space points $0.5 * g * (xvec + i * yvec)$. This class has slightly higher first-usage costs than `qfunc`, but subsequent operations will be several times faster. However, it can require quite a lot of memory. Call the created object as a function to retrieve the Husimi-Q function.

Parameters

xvec, yvec [array_like] x- and y-coordinates at which to calculate the Husimi-Q function.

g [float, default $\sqrt{2}$] Scaling factor for $a = 0.5 * g * (x + iy)$. The value of *g* is related to the value of \hbar in the commutation relation $[x, y] = i\hbar$ via $\hbar = 2/g^2$, so the default corresponds to $\hbar = 1$.

memory [real, default 1024] Size in MB that may be used internally as workspace. This class will raise `MemoryError` if subsequently passed a state of sufficiently large dimension that this bound would be exceeded. In those cases, use `qfunc` with `precompute_memory=None` instead to force using the slower, more memory-efficient algorithm.

See also:

`qfunc` a single function version, which will involve computing several quantities multiple times in order to use less memory.

Examples

Initialise the class for a square set of coordinates, with some states we want to investigate.

```
>>> xvec = np.linspace(-2, 2, 101)
>>> states = [qutip.rand_dm(10) for _ in range(10)]
>>> qfunc = qutip.QFunc(xvec, xvec)
```

Now we can calculate the Husimi-Q function over each of the states more efficiently with:

```
>>> husimiq = np.array([qfunc(state) for state in states])
```

5.1.5 Solver

class SESolver (*H*, *, *options=None*)

Schrodinger equation evolution of a state vector or unitary matrix for a given Hamiltonian.

Parameters

H [Qobj, QobjEvo] System Hamiltonian as a Qobj or QobjEvo for time-dependent Hamiltonians. List of [Qobj, Coefficient] or callable that can be made into QobjEvo are also accepted.

options [dict, optional] Options for the solver, see [SESolver.options](#) and [Integrator](#) for a list of all options.

Attributes

stats: dict Diverse diagnostic statistics of the evolution.

property options

Solver's options:

store_final_state: bool, default=False Whether or not to store the final state of the evolution in the result class.

store_states: bool, default=None Whether or not to store the state vectors or density matrices. On *None* the states will be saved if no expectation operators are given.

normalize_output: bool, default=True Normalize output state to hide ODE numerical errors.

progress_bar: str {'text', 'enhanced', 'tqdm', ''}, {} How to present the solver progress. 'tqdm' uses the python module of the same name and raise an error if not installed. Empty string or False will disable the bar.

progress_kwargs: dict, default={"chunk_size": 10} Arguments to pass to the progress_bar. Qutip's bars use *chunk_size*.

method: str, default="adams" Which ordinary differential equation integration method to use.

class MESolver (*H*, *c_ops=None*, *, *options=None*)

Master equation evolution of a density matrix for a given Hamiltonian and set of collapse operators, or a Liouvillian.

Evolve the density matrix (*rho0*) using a given Hamiltonian or Liouvillian (*H*) and an optional set of collapse operators (*c_ops*), by integrating the set of ordinary differential equations that define the system.

If either *H* or the Qobj elements in *c_ops* are superoperators, they will be treated as direct contributions to the total system Liouvillian. This allows the solution of master equations that are not in standard Lindblad form.

Parameters

H [Qobj, QobjEvo] Possibly time-dependent system Liouvillian or Hamiltonian as a Qobj or QobjEvo. List of [Qobj, Coefficient] or callable that can be made into QobjEvo are also accepted.

c_ops [list of Qobj, QobjEvo] Single collapse operator, or list of collapse operators, or a list of Liouvillian superoperators. None is equivalent to an empty list.

options [dict, optional] Options for the solver, see [SESolver.options](#) and [Integrator](#) for a list of all options.

Attributes

stats: dict Diverse diagnostic statistics of the evolution.

class BRSolver (*H*, *a_ops*, *c_ops=None*, *sec_cutoff=0.1*, *, *options=None*)

Bloch Redfield equation evolution of a density matrix for a given Hamiltonian and set of bath coupling operators.

Parameters

H [*Qobj*, *QobjEvo*] Possibly time-dependent system Liouvillian or Hamiltonian as a *Qobj* or *QobjEvo*. list of [*Qobj*, *Coefficient*] or callable that can be made into *QobjEvo* are also accepted.

a_ops [list of (*a_op*, *spectra*)] Nested list of system operators that couple to the environment, and the corresponding bath spectra.

a_op [*qutip.Qobj*, *qutip.QobjEvo*] The operator coupling to the environment. Must be hermitian.

spectra [*Coefficient*] The corresponding bath spectra. As a *Coefficient* using an ‘w’ args. Can depend on *t* only if *a_op* is a *qutip.QobjEvo*. *SpectraCoefficient* can be used to convert a coefficient depending on *t* to one depending on *w*.

Example:

```
a_ops = [
    (a+a.dag(), coefficient('w>0', args={'w':0})),
    (QobjEvo([b+b.dag(), lambda t: ...]),
     coefficient(lambda t, w: ...), args={"w": 0}),
    (c+c.dag(), SpectraCoefficient(coefficient(array,
    ↪tlist=ws))),
]
```

c_ops [list of *Qobj*, *QobjEvo*] Single collapse operator, or list of collapse operators, or a list of Lindblad dissipator. None is equivalent to an empty list.

options [dict, optional] Options for the solver, see *BRSolver.options* and *Integrator* for a list of all options.

sec_cutoff [float {0.1}] Cutoff for secular approximation. Use -1 if secular approximation is not used when evaluating bath-coupling terms.

Attributes

stats: dict Diverse diagnostic statistics of the evolution.

property options

Options for bloch redfield solver:

store_final_state: bool, default=False Whether or not to store the final state of the evolution in the result class.

store_states: bool, default=None Whether or not to store the state vectors or density matrices. On *None* the states will be saved if no expectation operators are given.

normalize_output: bool, default=False Normalize output state to hide ODE numerical errors.

progress_bar: str {'text', 'enhanced', 'tqdm', ''}, default="text" How to present the solver progress. ‘tqdm’ uses the python module of the same name and raise an error if not installed. Empty string or False will disable the bar.

progress_kwargs: dict, default={"chunk_size":10} Arguments to pass to the progress_bar. Qutip’s bars use *chunk_size*.

tensor_type: str ['sparse', 'dense', 'data'], default="sparse" Which data type to use when computing the brtensor. With a cutoff ‘sparse’ is usually the most efficient.

sparse_eigsolver: bool, default=False Whether to use the sparse eigensolver

method: str, default="adams" Which ODE integrator methods are supported.

5.1.6 Non-Markovian HEOM Solver

class HEOMSolver (*H, bath, max_depth, *, options=None*)

HEOM solver that supports multiple baths.

The baths must be all either bosonic or fermionic baths.

Parameters

H [*Qobj*, *QobjEvo*] Possibly time-dependent system Liouvillian or Hamiltonian as a *Qobj* or *QobjEvo*. list of [*Qobj*, *Coefficient*] or callable that can be made into *QobjEvo* are also accepted.

bath [*Bath* or list of *Bath*] A *Bath* containing the exponents of the expansion of the bath correlation function and their associated coefficients and coupling operators, or a list of baths.

If multiple baths are given, they must all be either fermionic or bosonic baths.

max_depth [int] The maximum depth of the heirarchy (i.e. the maximum number of bath exponent “excitations” to retain).

options [dict, optional] Generic solver options. If set to None the default options will be used. Keyword only. Default: None.

Attributes

ados [*HierarchyADOS*] The description of the hierarchy constructed from the given bath and maximum depth.

property options

Options for HEOMSolver:

store_final_state: bool, default=False Whether or not to store the final state of the evolution in the result class.

store_states: bool, default=None Whether or not to store the state vectors or density matrices. On *None* the states will be saved if no expectation operators are given.

normalize_output: bool, default=False Normalize output state to hide ODE numerical errors.

progress_bar: str {'text', 'enhanced', 'tqdm', ''}, default="text" How to present the solver progress. ‘tqdm’ uses the python module of the same name and raise an error if not installed. Empty string or False will disable the bar.

progress_kwargs: dict, default={"chunk_size": 10} Arguments to pass to the progress_bar. Qutip’s bars use *chunk_size*.

method: str, default="adams" Which ordinary differential equation integration method to use.

state_data_type: str, default="dense" Name of the data type of the state used during the ODE evolution. Use an empty string to keep the input state type. Many integrator can only work with *Dense*.

store_ados [bool, default=False] Whether or not to store the HEOM ADOs. Only relevant when using the HEOM solver.

resultclass

alias of `qutip.solver.heom.bofin_solvers.HEOMResult`

run (*state0, tlist, *, args=None, e_ops=None*)

Solve for the time evolution of the system.

Parameters

state0 [*Qobj* or *HierarchyADOSState* or array-like] If *rho0* is a *Qobj* the it is the initial state of the system (i.e. a *Qobj* density matrix).

If it is a *HierarchyADOSState* or array-like, then *rho0* gives the initial state of all ADOs.

Usually the state of the ADOs would be determined from a previous call to `.run(...)` with the solver results option `store_ados` set to `True`. For example, `result = solver.run(...)` could be followed by `solver.run(result.ado_states[-1], tlist)`.

If a numpy array-like is passed its shape must be `(number_of_ados, n, n)` where `(n, n)` is the system shape (i.e. shape of the system density matrix) and the ADOs must be in the same order as in `.ados.labels`.

tlist [list] An ordered list of times at which to return the value of the state.

args [dict, optional {None}] Change the `args` of the RHS for the evolution.

e_ops [Qobj / QobjEvo / callable / list / dict / None, optional] A list or dictionary of operators as `Qobj`, `QobjEvo` and/or callable functions (they can be mixed) or a single operator or callable function. For an operator `op`, the result will be computed using `(state * op).tr()` and the state at each time `t`. For callable functions, `f`, the result is computed using `f(t, ado_state)`. The values are stored in the `expect` and `e_data` attributes of the result (see the return section below).

Returns

HEOMResult The results of the simulation run, with the following important attributes:

- **times**: the times `t` (i.e. the `tlist`).
- **states**: the system state at each time `t` (only available if `e_ops` was `None` or if the solver option `store_states` was set to `True`).
- **ado_states**: the full ADO state at each time (only available if the results option `ado_return` was set to `True`). Each element is an instance of `HierarchyADOsState`. The state of a particular ADO may be extracted from `result.ado_states[i]` by calling `extract`.
- **expect**: a list containing the values of each `e_ops` at time `t`.
- **e_data**: a dictionary containing the values of each `e_ops` at time `t`. The keys are those given by `e_ops` if it was a dict, otherwise they are the indexes of the supplied `e_ops`.

See `HEOMResult` and `Result` for the complete list of attributes.

start (`state0`, `t0`)

Set the initial state and time for a step evolution.

Parameters

state0 [Qobj] Initial state of the evolution. This may provide either just the initial density matrix of the system, or the full set of ADOs for the hierarchy. See the documentation for `rho0` in the `.run(...)` method for details.

t0 [double] Initial time of the evolution.

steady_state (`use_mkl=True`, `mkl_max_iter_refine=100`, `mkl_weighted_matching=False`)

Compute the steady state of the system.

Parameters

use_mkl [bool, default=False] Whether to use mkl or not. If mkl is not installed or if this is false, use the scipy splu solver instead.

mkl_max_iter_refine [int] Specifies the the maximum number of iterative refinement steps that the MKL PARDISO solver performs.

For a complete description, see `iparm(8)` in <http://cali2.unilim.fr/intel-xe/mkl/mklman/GUID-264E311E-ACED-4D56-AC31-E9D3B11D1CBF.htm>.

mkl_weighted_matching [bool] MKL PARDISO can use a maximum weighted matching algorithm to permute large elements close the diagonal. This strategy adds an additional level of reliability to the factorization methods.

For a complete description, see `iparm(13)` in <http://cali2.unilim.fr/intel-xe/mkl/mklman/GUID-264E311E-ACED-4D56-AC31-E9D3B11D1CBF.htm>.

Returns

steady_state [Qobj] The steady state density matrix of the system.

steady_ados [*HierarchyADOsState*] The steady state of the full ADO hierarchy. A particular ADO may be extracted from the full state by calling *extract*.

property sys_dims

Dimensions of the space that the system use, excluding any environment:

`qutip.basis(sovler.dims)` will create a state with proper dimensions for this solver.

class HSolverDL(*H_sys*, *coup_op*, *coup_strength*, *temperature*, *N_cut*, *N_exp*, *cut_freq*, *, *bnd_cut_approx=False*, *options=None*, *combine=True*)

A helper class for creating an *HEOMSolver* that is backwards compatible with the *HSolverDL* provided in `qutip.nonmarkov.heom` in QuTiP 4.6 and below.

See *HEOMSolver* and *DrudeLorentzBath* for more descriptions of the underlying solver and bath construction.

An exact copy of the QuTiP 4.6 *HSolverDL* is provided in `qutip.nonmarkov.dlheom_solver` for cases where the functionality of the older solver is required. The older solver will be completely removed in QuTiP 5.

Note: Unlike the version of *HSolverDL* in QuTiP 4.6, this solver supports supplying a time-dependent or Liouvillian *H_sys*.

Note: For compatibility with *HSolverDL* in QuTiP 4.6 and below, the parameter *N_exp* specifying the number of exponents to keep in the expansion of the bath correlation function is one more than the equivalent *Nk* used in the *DrudeLorentzBath*. I.e., $Nk = N_exp - 1$. The *Nk* parameter in the *DrudeLorentzBath* does not count the zeroeth exponent in order to better match common usage in the literature.

Note: The *stats* and *renorm* arguments accepted in QuTiP 4.6 and below are no longer supported.

Parameters

H_sys [Qobj or QobjEvo or list] The system Hamiltonian or Liouvillian. See *HEOMSolver* for a complete description.

coup_op [Qobj] Operator describing the coupling between system and bath. See parameter *Q* in *BosonicBath* for a complete description.

coup_strength [float] Coupling strength. Referred to as *lam* in *DrudeLorentzBath*.

temperature [float] Bath temperature. Referred to as *T* in *DrudeLorentzBath*.

N_cut [int] The maximum depth of the hierarchy. See *max_depth* in *HEOMSolver* for a full description.

N_exp [int] Number of exponential terms used to approximate the bath correlation functions. The equivalent *Nk* in *DrudeLorentzBath* is one less than *N_exp* (see note above).

cut_freq [float] Bath spectral density cutoff frequency. Referred to as γ in *DrudeLorentzBath*.

bnd_cut_approx [bool] Use boundary cut off approximation. If true, the Matsubara terminator is added to the system Liouvillian (and H_{sys} is promoted to a Liouvillian if it was a Hamiltonian). Keyword only. Default: False.

options [dict, optional] Generic solver options. If set to None the default options will be used. Keyword only. Default: None.

combine [bool, default True] Whether to combine exponents with the same frequency (and coupling operator). See *BosonicBath.combine* for details. Keyword only. Default: True.

class BathExponent (*type, dim, Q, ck, vk, ck2=None, sigma_bar_k_offset=None, tag=None*)
Represents a single exponent (naively, an excitation mode) within the decomposition of the correlation functions of a bath.

Parameters

type [{“R”, “T”, “RI”, “+”, “-”} or BathExponent.ExponentType] The type of bath exponent.

“R” and “T” are bosonic bath exponents that appear in the real and imaginary parts of the correlation expansion.

“RI” is combined bosonic bath exponent that appears in both the real and imaginary parts of the correlation expansion. The combined exponent has a single νk . The ck is the coefficient in the real expansion and $ck2$ is the coefficient in the imaginary expansion.

“+” and “-” are fermionic bath exponents. These fermionic bath exponents must specify $\sigma_{\text{bar } k_offset}$ which specifies the amount to add to k (the exponent index within the bath of this exponent) to determine the k of the corresponding exponent with the opposite sign (i.e. “-” or “+”).

dim [int or None] The dimension (i.e. maximum number of excitations for this exponent). Usually 2 for fermionic exponents or None (i.e. unlimited) for bosonic exponents.

Q [Qobj] The coupling operator for this excitation mode.

vk [complex] The frequency of the exponent of the excitation term.

ck [complex] The coefficient of the excitation term.

ck2 [optional, complex] For exponents of type “RI” this is the coefficient of the term in the imaginary expansion (and ck is the coefficient in the real expansion).

sigma_bar_k_offset [optional, int] For exponents of type “+” this gives the offset (within the list of exponents within the bath) of the corresponding “-” bath exponent. For exponents of type “-” it gives the offset of the corresponding “+” exponent.

tag [optional, str, tuple or any other object] A label for the exponent (often the name of the bath). It defaults to None.

Attributes

All of the parameters are available as attributes.

types

alias of `qutip.solver.heom.bofin_baths.ExponentType`

class Bath (*exponents*)

Represents a list of bath expansion exponents.

Parameters

exponents [list of BathExponent] The exponents of the correlation function describing the bath.

Attributes

All of the parameters are available as attributes.

class BosonicBath (*Q, ck_real, vk_real, ck_imag, vk_imag, combine=True, tag=None*)

A helper class for constructing a bosonic bath from the expansion coefficients and frequencies for the real and imaginary parts of the bath correlation function.

If the correlation functions $C(t)$ is split into real and imaginary parts:

$$C(t) = C_{\text{real}}(t) + i * C_{\text{imag}}(t)$$

then:

```
C_real(t) = sum(ck_real * exp(- vk_real * t))
C_imag(t) = sum(ck_imag * exp(- vk_imag * t))
```

Defines the coefficients ck and the frequencies vk .

Note that the ck and vk may be complex, even though $C_{\text{real}}(t)$ and $C_{\text{imag}}(t)$ (i.e. the sum) is real.

Parameters

Q [Qobj] The coupling operator for the bath.

ck_real [list of complex] The coefficients of the expansion terms for the real part of the correlation function. The corresponding frequencies are passed as **vk_real**.

vk_real [list of complex] The frequencies (exponents) of the expansion terms for the real part of the correlation function. The corresponding coefficients are passed as **ck_real**.

ck_imag [list of complex] The coefficients of the expansion terms in the imaginary part of the correlation function. The corresponding frequencies are passed as **vk_imag**.

vk_imag [list of complex] The frequencies (exponents) of the expansion terms for the imaginary part of the correlation function. The corresponding coefficients are passed as **ck_imag**.

combine [bool, default True] Whether to combine exponents with the same frequency (and coupling operator). See [combine](#) for details.

tag [optional, str, tuple or any other object] A label for the bath exponents (for example, the name of the bath). It defaults to None but can be set to help identify which bath an exponent is from.

classmethod combine (*exponents, rtol=1e-05, atol=1e-07*)

Group bosonic exponents with the same frequency and return a single exponent for each frequency present.

Exponents with the same frequency are only combined if they share the same coupling operator Q .

Note that combined exponents take their tag from the first exponent in the group being combined (i.e. the one that occurs first in the given exponents list).

Parameters

exponents [list of BathExponent] The list of exponents to combine.

rtol [float, default 1e-5] The relative tolerance to use to when comparing frequencies and coupling operators.

atol [float, default 1e-7] The absolute tolerance to use to when comparing frequencies and coupling operators.

Returns

list of BathExponent The new reduced list of exponents.

class DrudeLorentzBath (*Q, lam, gamma, T, Nk, combine=True, tag=None*)

A helper class for constructing a Drude-Lorentz bosonic bath from the bath parameters (see parameters below).

Parameters

Q [Qobj] Operator describing the coupling between system and bath.

lam [float] Coupling strength.

gamma [float] Bath spectral density cutoff frequency.

T [float] Bath temperature.

Nk [int] Number of exponential terms used to approximate the bath correlation functions.

combine [bool, default True] Whether to combine exponents with the same frequency (and coupling operator). See *BosonicBath.combine* for details.

tag [optional, str, tuple or any other object] A label for the bath exponents (for example, the name of the bath). It defaults to None but can be set to help identify which bath an exponent is from.

terminator ()

Return the Matsubara terminator for the bath and the calculated approximation discrepancy.

Returns

delta: float The approximation discrepancy. That is, the difference between the true correlation function of the Drude-Lorentz bath and the sum of the N_k exponential terms is approximately $2 * \text{delta} * \text{dirac}(t)$, where $\text{dirac}(t)$ denotes the Dirac delta function.

terminator [Qobj] The Matsubara terminator – i.e. a liouvillian term representing the contribution to the system-bath dynamics of all exponential expansion terms beyond N_k . It should be used by adding it to the system liouvillian (i.e. `liouvillian(H_sys)`).

class DrudeLorentzPadeBath (*Q, lam, gamma, T, Nk, combine=True, tag=None*)

A helper class for constructing a Padé expansion for a Drude-Lorentz bosonic bath from the bath parameters (see parameters below).

A Padé approximant is a sum-over-poles expansion (see https://en.wikipedia.org/wiki/Pad%C3%A9_approximant).

The application of the Padé method to spectrum decompositions is described in “Padé spectrum decompositions of quantum distribution functions and optimal hierarchical equations of motion construction for quantum open systems” [1].

The implementation here follows the approach in the paper.

[1] J. Chem. Phys. 134, 244106 (2011); <https://doi.org/10.1063/1.3602466>

This is an alternative to the *DrudeLorentzBath* which constructs a simpler exponential expansion.

Parameters

Q [Qobj] Operator describing the coupling between system and bath.

lam [float] Coupling strength.

gamma [float] Bath spectral density cutoff frequency.

T [float] Bath temperature.

Nk [int] Number of Padé exponentials terms used to approximate the bath correlation functions.

combine [bool, default True] Whether to combine exponents with the same frequency (and coupling operator). See *BosonicBath.combine* for details.

tag [optional, str, tuple or any other object] A label for the bath exponents (for example, the name of the bath). It defaults to None but can be set to help identify which bath an exponent is from.

terminator ()

Return the Padé terminator for the bath and the calculated approximation discrepancy.

Returns

delta: float The approximation discrepancy. That is, the difference between the true correlation function of the Drude-Lorentz bath and the sum of the N_k exponential terms is approximately $2 * \text{delta} * \text{dirac}(t)$, where $\text{dirac}(t)$ denotes the Dirac delta function.

terminator [Qobj] The Padé terminator – i.e. a liouvillian term representing the contribution to the system-bath dynamics of all exponential expansion terms beyond N_k . It should be used by adding it to the system liouvillian (i.e. `liouvillian(H_sys)`).

class UnderDampedBath (*Q, lam, gamma, w0, T, Nk, combine=True, tag=None*)

A helper class for constructing an under-damped bosonic bath from the bath parameters (see parameters below).

Parameters

Q [Qobj] Operator describing the coupling between system and bath.

lam [float] Coupling strength.

gamma [float] Bath spectral density cutoff frequency.

w0 [float] Bath spectral density resonance frequency.

T [float] Bath temperature.

Nk [int] Number of exponential terms used to approximate the bath correlation functions.

combine [bool, default True] Whether to combine exponents with the same frequency (and coupling operator). See `BosonicBath.combine` for details.

tag [optional, str, tuple or any other object] A label for the bath exponents (for example, the name of the bath). It defaults to None but can be set to help identify which bath an exponent is from.

class FermionicBath (*Q, ck_plus, vk_plus, ck_minus, vk_minus, tag=None*)

A helper class for constructing a fermionic bath from the expansion coefficients and frequencies for the + and – modes of the bath correlation function.

There must be the same number of + and – modes and their coefficients must be specified in the same order so that `ck_plus[i]`, `vk_plus[i]` are the plus coefficient and frequency corresponding to the minus mode `ck_minus[i]`, `vk_minus[i]`.

In the fermionic case the order in which excitations are created or destroyed is important, resulting in two different correlation functions labelled `C_plus(t)` and `C_minus(t)`:

```
C_plus(t) = sum(ck_plus * exp(- vk_plus * t))
C_minus(t) = sum(ck_minus * exp(- vk_minus * t))
```

where the expansions above define the coefficients `ck` and the frequencies `vk`.

Parameters

Q [Qobj] The coupling operator for the bath.

ck_plus [list of complex] The coefficients of the expansion terms for the + part of the correlation function. The corresponding frequencies are passed as `vk_plus`.

vk_plus [list of complex] The frequencies (exponents) of the expansion terms for the + part of the correlation function. The corresponding coefficients are passed as `ck_plus`.

ck_minus [list of complex] The coefficients of the expansion terms for the $-$ part of the correlation function. The corresponding frequencies are passed as **vk_minus**.

vk_minus [list of complex] The frequencies (exponents) of the expansion terms for the $-$ part of the correlation function. The corresponding coefficients are passed as **ck_minus**.

tag [optional, str, tuple or any other object] A label for the bath exponents (for example, the name of the bath). It defaults to None but can be set to help identify which bath an exponent is from.

class LorentzianBath (*Q, gamma, w, mu, T, Nk, tag=None*)

A helper class for constructing a Lorentzian fermionic bath from the bath parameters (see parameters below).

Note: This Matsubara expansion used in this bath converges very slowly and $Nk > 20$ may be required to get good convergence. The Padé expansion used by `LorentzianPadeBath` converges much more quickly.

Parameters

Q [Qobj] Operator describing the coupling between system and bath.

gamma [float] The coupling strength between the system and the bath.

w [float] The width of the environment.

mu [float] The chemical potential of the bath.

T [float] Bath temperature.

Nk [int] Number of exponential terms used to approximate the bath correlation functions.

tag [optional, str, tuple or any other object] A label for the bath exponents (for example, the name of the bath). It defaults to None but can be set to help identify which bath an exponent is from.

class LorentzianPadeBath (*Q, gamma, w, mu, T, Nk, tag=None*)

A helper class for constructing a Padé expansion for Lorentzian fermionic bath from the bath parameters (see parameters below).

A Padé approximant is a sum-over-poles expansion (see https://en.wikipedia.org/wiki/Pad%C3%A9_approximant).

The application of the Padé method to spectrum decompositions is described in “Padé spectrum decompositions of quantum distribution functions and optimal hierarchical equations of motion construction for quantum open systems” [1].

The implementation here follows the approach in the paper.

[1] J. Chem. Phys. 134, 244106 (2011); <https://doi.org/10.1063/1.3602466>

This is an alternative to the `LorentzianBath` which constructs a simpler exponential expansion that converges much more slowly in this particular case.

Parameters

Q [Qobj] Operator describing the coupling between system and bath.

gamma [float] The coupling strength between the system and the bath.

w [float] The width of the environment.

mu [float] The chemical potential of the bath.

T [float] Bath temperature.

Nk [int] Number of exponential terms used to approximate the bath correlation functions.

tag [optional, str, tuple or any other object] A label for the bath exponents (for example, the name of the bath). It defaults to None but can be set to help identify which bath an exponent is from.

class HierarchyADOs (*exponents, max_depth*)

A description of ADOs (auxilliary density operators) with the hierarchical equations of motion.

The list of ADOs is constructed from a list of bath exponents (corresponding to one or more baths). Each ADO is referred to by a label that lists the number of “excitations” of each bath exponent. The level of a label within the hierarchy is the sum of the “excitations” within the label.

For example the label (0, 0, ..., 0) represents the density matrix of the system being solved and is the only 0th level label.

The labels with a single 1, i.e. (1, 0, ..., 0), (0, 1, 0, ... 0), etc. are the 1st level labels.

The second level labels all have either two 1s or a single 2, and so on for the third and higher levels of the hierarchy.

Parameters

exponents [list of BathExponent] The exponents of the correlation function describing the bath or baths.

max_depth [int] The maximum depth of the hierarchy (i.e. the maximum sum of “excitations” in the hierarchy ADO labels or maximum ADO level).

Attributes

exponents [list of BathExponent] The exponents of the correlation function describing the bath or baths.

max_depth [int] The maximum depth of the hierarchy (i.e. the maximum sum of “excitations” in the hierarchy ADO labels).

dims [list of int] The dimensions of each exponent within the bath(s).

vk [list of complex] The frequency of each exponent within the bath(s).

ck [list of complex] The coefficient of each exponent within the bath(s).

ck2: list of complex For exponents of type “RI”, the coefficient of the exponent within the imaginary expansion. For other exponent types, the entry is None.

sigma_bar_k_offset: list of int For exponents of type “+” or “-” the offset within the list of modes of the corresponding “-” or “+” exponent. For other exponent types, the entry is None.

labels: list of tuples A list of the ADO labels within the hierarchy.

exps (*label*)

Converts an ADO label into a tuple of exponents, with one exponent for each “excitation” within the label.

The number of exponents returned is always equal to the level of the label within the hierarchy (i.e. the sum of the indices within the label).

Parameters

label [tuple] The ADO label to convert to a list of exponents.

Returns

tuple of BathExponent A tuple of BathExponents.

Examples

`ados.exps((1, 0, 0))` would return `[ados.exponents[0]]`

`ados.exps((2, 0, 0))` would return `[ados.exponents[0], ados.exponents[0]].`

`ados.exps((1, 2, 1))` would return `[ados.exponents[0], ados.exponents[1], ados.exponents[1], ados.exponents[2]].`

filter (*level=None, tags=None, dims=None, types=None*)

Return a list of ADO labels for ADOs whose “excitations” match the given patterns.

Each of the filter parameters (*tags*, *dims*, *types*) may be either unspecified (*None*) or a list. Unspecified parameters are excluded from the filtering.

All specified filter parameters must be lists of the same length. Each position in the lists describes a particular excitation and any exponent that matches the filters may supply that excitation. The level of all labels returned is thus equal to the length of the filter parameter lists.

Within a filter parameter list, items that are *None* represent wildcards and match any value of that exponent attribute

Parameters

level [int] The hierarchy depth to return ADOs from.

tags [list of object or *None*] Filter parameter that matches the `.tag` attribute of exponents.

dims [list of int] Filter parameter that matches the `.dim` attribute of exponents.

types [list of *BathExponent* types or list of str] Filter parameter that matches the `.type` attribute of exponents. Types may be supplied by name (e.g. “R”, “I”, “+”) instead of by the actual type (e.g. `BathExponent.types.R`).

Returns

list of tuple The ADO label for each ADO whose exponent excitations (i.e. label) match the given filters or level.

idx (*label*)

Return the index of the ADO label within the list of labels, i.e. within `self.labels`.

Parameters

label [tuple] The label to look up.

Returns

int The index of the label within the list of ADO labels.

next (*label, k*)

Return the ADO label with one more excitation in the *k*’th exponent dimension or *None* if adding the excitation would exceed the dimension or maximum depth of the hierarchy.

Parameters

label [tuple] The ADO label to add an excitation to.

k [int] The exponent to add the excitation to.

Returns

tuple or None The next label.

prev (*label, k*)

Return the ADO label with one fewer excitation in the *k*’th exponent dimension or *None* if the label has no excitations in the *k*’th exponent.

Parameters

label [tuple] The ADO label to remove the excitation from.

k [int] The exponent to remove the excitation from.

Returns

tuple or None The previous label.

class HierarchyADOsState (*rho, ados, ado_state*)

Provides convenient access to the full hierarchy ADO state at a particular point in time, t .

Parameters

rho [Qobj] The current state of the system (i.e. the 0th component of the hierarchy).

ados [*HierarchyADOs*] The description of the hierarchy.

ado_state [numpy.array] The full state of the hierarchy.

Attributes

rho [Qobj] The system state.

In addition, all of the attributes of the hierarchy description,

i.e. ```HierarchyADOs```, are provided directly on this class for

convenience. E.g. one can access ```.labels```, or ```.exponents``` or

call ```.idx(label)``` directly.

See :class:`HierarchyADOs` for a full list of the available attributes

and methods.

extract (*idx_or_label*)

Extract a Qobj representing the specified ADO from a full representation of the ADO states.

Parameters

idx [int or label] The index of the ADO to extract. If an ADO label, e.g. (0, 1, 0, ...) is supplied instead, then the ADO is extracted by label instead.

Returns

Qobj A Qobj representing the state of the specified ADO.

class HEOMResult (*e_ops, options, *, solver=None, stats=None, **kw*)

5.1.7 Integrator

class IntegratorScipyAdams (*system, options*)

Integrator using Scipy *ode* with zvode integrator using adams method. Ordinary Differential Equation solver by netlib (<http://www.netlib.org/odepack>).

Usable with `method="adams"`

property options

Supported options by zvode integrator:

atol [float, default=1e-8] Absolute tolerance.

rtol [float, default=1e-6] Relative tolerance.

order [int, default=12, 'adams' or 5, 'bdf'] Order of integrator ≤ 12 'adams', ≤ 5 'bdf'

nsteps [int, default=2500] Max. number of internal steps/call.

first_step [float, default=0] Size of initial step (0 = automatic).

min_step [float, default=0] Minimum step size (0 = automatic).

max_step [float, default=0] Maximum step size (0 = automatic) When using pulses, change to half the thinnest pulse otherwise it may be skipped.

class IntegratorScipyBDF (*system, options*)

Integrator using Scipy *ode* with zode integrator using bdf method. Ordinary Differential Equation solver by netlib (<http://www.netlib.org/odepack>).

Usable with `method="bdf"`

property options

Supported options by zode integrator:

atol [float, default=1e-8] Absolute tolerance.

rtol [float, default=1e-6] Relative tolerance.

order [int, default=12, 'adams' or 5, 'bdf'] Order of integrator <=12 'adams', <=5 'bdf'

nsteps [int, default=2500] Max. number of internal steps/call.

first_step [float, default=0] Size of initial step (0 = automatic).

min_step [float, default=0] Minimum step size (0 = automatic).

max_step [float, default=0] Maximum step size (0 = automatic) When using pulses, change to half the thinnest pulse otherwise it may be skipped.

class IntegratorScipyLsoda (*system, options*)

Integrator using Scipy *ode* with lsoda integrator. ODE solver by netlib (<http://www.netlib.org/odepack>) Automatically choose between 'Adams' and 'BDF' methods to solve both stiff and non-stiff systems.

Usable with `method="lsoda"`

property options

Supported options by lsoda integrator:

atol [float, default=1e-8] Absolute tolerance.

rtol [float, default=1e-6] Relative tolerance.

nsteps [int, default=2500] Max. number of internal steps/call.

max_order_ns [int, default=12] Maximum order used in the nonstiff case (<= 12).

max_order_s [int, default=5] Maximum order used in the stiff case (<= 5).

first_step [float, default=0] Size of initial step (0 = automatic).

max_step [float, default=0] Maximum step size (0 = automatic) When using pulses, change to half the thinnest pulse otherwise it may be skipped.

min_step [float, default=0] Minimum step size (0 = automatic)

class IntegratorScipyDop853 (*system, options*)

Integrator using Scipy *ode* with dop853 integrator. Eight order runge-kutta method by Dormand & Prince. Use fortran implementation from [E. Hairer, S.P. Norsett and G. Wanner, Solving Ordinary Differential Equations i. Nonstiff Problems. 2nd edition. Springer Series in Computational Mathematics, Springer-Verlag (1993)].

Usable with `method="dop853"`

property options

Supported options by dop853 integrator:

atol [float, default=1e-8] Absolute tolerance.

rtol [float, default=1e-6] Relative tolerance.

nsteps [int, default=2500] Max. number of internal steps/call.

first_step [float, default=0] Size of initial step (0 = automatic).

max_step [float, default=0] Maximum step size (0 = automatic)

ifactor, dfactor [float, default=6., 0.3] Maximum factor to increase/decrease step size by in one step

beta [float, default=0] Beta parameter for stabilised step size control.

See `scipy.integrate.ode` for more detail

class IntegratorVern7 (*system, options*)

QuTiP's implementation of Verner's "most efficient" Runge-Kutta method of order 7. These are Runge-Kutta methods with variable steps and dense output.

The implementation uses QuTiP's Data objects for the state, allowing sparse, GPU or other data layer objects to be used efficiently by the solver in their native formats.

See <http://people.math.sfu.ca/~jverner/> for a detailed description of the methods.

Usable with `method="vern7"`

property options

Supported options by verner method:

atol [float, default=1e-8] Absolute tolerance.

rtol [float, default=1e-6] Relative tolerance.

nsteps [int, default=1000] Max. number of internal steps/call.

first_step [float, default=0] Size of initial step (0 = automatic).

min_step [float, default=0] Minimum step size (0 = automatic).

max_step [float, default=0] Maximum step size (0 = automatic) When using pulses, change to half the thinnest pulse otherwise it may be skipped.

interpolate [bool, default=True] Whether to use interpolation step, faster most of the time.

class IntegratorVern9 (*system, options*)

QuTiP's implementation of Verner's "most efficient" Runge-Kutta method of order 9. These are Runge-Kutta methods with variable steps and dense output.

The implementation uses QuTiP's Data objects for the state, allowing sparse, GPU or other data layer objects to be used efficiently by the solver in their native formats.

See <http://people.math.sfu.ca/~jverner/> for a detailed description of the methods.

Usable with `method="vern9"`

property options

Supported options by verner method:

atol [float, default=1e-8] Absolute tolerance.

rtol [float, default=1e-6] Relative tolerance.

nsteps [int, default=1000] Max. number of internal steps/call.

first_step [float, default=0] Size of initial step (0 = automatic).

min_step [float, default=0] Minimum step size (0 = automatic).

max_step [float, default=0] Maximum step size (0 = automatic) When using pulses, change to half the thinnest pulse otherwise it may be skipped.

interpolate [bool, default=True] Whether to use interpolation step, faster most of the time.

class IntegratorDiag (*system, options*)

Integrator solving the ODE by diagonalizing the system and solving analytically. It can only solve constant system and has a long preparation time, but the integration is fast.

Usable with `method="diag"`

property options

Supported options by "diag" method:

eigensolver_dtype [str, default="dense"] Qutip data type {"dense", "csr", etc.} to use when computing the eigenstates. The dense eigen solver is usually faster and more stable.

class IntegratorKrylov (*system, options*)

Evolve the state vector (“psi0”) finding an approximation for the time evolution operator of Hamiltonian (“H”) by obtaining the projection of the time evolution operator on a set of small dimensional Krylov subspaces ($m \ll \dim(H)$).

property options

Supported options by krylov method:

atol [float, default=1e-7] Absolute tolerance.

nsteps [int, default=100] Max. number of internal steps/call.

min_step, max_step [float, default=(1e-5, 1e5)] Minimum and maximum step size.

krylov_dim: int, default=0 Dimension of Krylov approximation subspaces used for the time evolution approximation. If the default 0 is given, the dimension is calculated from the system size N , using $\min(\text{int}((N + 100)**0.5), N-1)$.

sub_system_tol: float, default=1e-7 Tolerance to detect a happy breakdown. A happy breakdown occurs when the initial ket is in a subspace of the Hamiltonian smaller than `krylov_dim`.

always_compute_step: bool, default=False If True, the step length is computed each time a new Krylov subspace is computed. Otherwise it is computed only once when creating the integrator.

5.1.8 Non-Markovian Memory Cascade and Transfer Tensor Solvers

class MemoryCascade (*H_S, L1, L2, S_matrix=None, c_ops_markov=None, integrator='propagator', parallel=False, options=None*)

Class for running memory cascade simulations of open quantum systems with time-delayed coherent feedback.

Attributes

H_S [qutip.Qobj] System Hamiltonian (can also be a Liouvillian)

L1 [qutip.Qobj / list of qutip.Qobj] System operators coupling into the feedback loop. Can be a single operator or a list of operators.

L2 [qutip.Qobj / list of qutip.Qobj] System operators coupling out of the feedback loop. Can be a single operator or a list of operators. L2 must have the same length as L1.

S_matrix: *array* S matrix describing which operators in L1 are coupled to which operators in L2 by the feedback channel. Defaults to an n by n identity matrix where n is the number of elements in L1/L2.

c_ops_markov [qutip.Qobj / list of qutip.Qobj] Decay operators describing conventional Markovian decay channels. Can be a single operator or a list of operators.

integrator [str {‘propagator’, ‘mesolve’}] Integrator method to use. Defaults to ‘propagator’ which tends to be faster for long times (i.e., large Hilbert space).

parallel [bool] Run integrator in parallel if True. Only implemented for ‘propagator’ as the integrator method.

options [dict] Generic solver options.

outfieldcorr (*rho0, blist, tlist, tau, c1=None, c2=None*)

Compute output field expectation value $\langle O_n(t_n) \dots O_2(t_2) O_1(t_1) \rangle$ for times t_1, t_2, \dots and $O_i = I, b_{\text{out}}, b_{\text{out}}^\dagger, b_{\text{loop}}, b_{\text{loop}}^\dagger$

Parameters

rho0 [qutip.Qobj] initial density matrix or state vector (ket).

blist [array_like] List of integers specifying the field operators: 0: I (nothing) 1: b_{out} 2: b_{out}^\dagger 3: b_{loop} 4: b_{loop}^\dagger

tlist [array_like] list of corresponding times t_1, \dots, t_n at which to evaluate the field operators

tau [float] time-delay

c1 [qutip.Qobj] system collapse operator that couples to the in-loop field in question (only needs to be specified if self.L1 has more than one element)

c2 [qutip.Qobj] system collapse operator that couples to the output field in question (only needs to be specified if self.L2 has more than one element)

Returns

: **complex** expectation value of field correlation function

outfieldpropagator (blist, tlist, tau, c1=None, c2=None, notrace=False)

Compute propagator for computing output field expectation values $\langle O_n(t_n) \dots O_2(t_2) O_1(t_1) \rangle$ for times t_1, t_2, \dots and $O_i = I, b_{\text{out}}, b_{\text{out}}^\dagger, b_{\text{loop}}, b_{\text{loop}}^\dagger$

Parameters

blist [array_like] List of integers specifying the field operators: 0: I (nothing) 1: b_{out} 2: b_{out}^\dagger 3: b_{loop} 4: b_{loop}^\dagger

tlist [array_like] list of corresponding times t_1, \dots, t_n at which to evaluate the field operators

tau [float] time-delay

c1 [qutip.Qobj] system collapse operator that couples to the in-loop field in question (only needs to be specified if self.L1 has more than one element)

c2 [qutip.Qobj] system collapse operator that couples to the output field in question (only needs to be specified if self.L2 has more than one element)

notrace [bool {False}] If this optional is set to True, a propagator is returned for a cascade of k systems, where $(k-1)\tau < t < k\tau$. If set to False (default), a generalized partial trace is performed and a propagator for a single system is returned.

Returns

: **qutip.Qobj** time-propagator for computing field correlation function

propagator (t, tau, notrace=False)

Compute propagator for time t and time-delay τ

Parameters

t [float] current time

tau [float] time-delay

notrace [bool {False}] If this optional is set to True, a propagator is returned for a cascade of k systems, where $(k-1)\tau < t < k\tau$. If set to False (default), a generalized partial trace is performed and a propagator for a single system is returned.

Returns

: **:class:`qutip.Qobj`** time-propagator for reduced system dynamics

rho0 (rho0, t, tau)

Compute the reduced system density matrix $\rho(t)$

Parameters

rho0 [qutip.Qobj] initial density matrix or state vector (ket)

t [float] current time

tau [float] time-delay

Returns

: `qutip.Qobj` density matrix at time t

class TTMSolverOptions (*dynmaps=None, times=[], learningtimes=[], thres=0.0, options=None*)
Class of options for the Transfer Tensor Method solver.

Attributes

dynmaps [list of `qutip.Qobj`] List of precomputed dynamical maps (superoperators), or a callback function that returns the superoperator at a given time.

times [array_like] List of times t_n at which to calculate $\rho(t_n)$

learningtimes [array_like] List of times t_k to use as learning times if argument *dynmaps* is a callback function.

thres [float] Threshold for halting. Halts if $\|T_n - T_{n-1}\|$ is below threshold.

options [`qutip.solver.SolverOptions`] Generic solver options.

5.1.9 Solver Options and Results

class Result (*e_ops, options, *, solver=None, stats=None, **kw*)
Base class for storing solver results.

Parameters

e_ops [`Qobj`, `QobjEvo`, function or list or dict of these] The *e_ops* parameter defines the set of values to record at each time step t . If an element is a `Qobj` or `QobjEvo` the value recorded is the expectation value of that operator given the state at t . If the element is a function, f , the value recorded is $f(t, \text{state})$.

The values are recorded in the *e_data* and *expect* attributes of this result object. *e_data* is a dictionary and *expect* is a list, where each item contains the values of the corresponding *e_op*.

options [dict] The options for this result class.

solver [str or None] The name of the solver generating these results.

stats [dict or None] The stats generated by the solver while producing these results. Note that the solver may update the stats directly while producing results.

kw [dict] Additional parameters specific to a result sub-class.

Attributes

times [list] A list of the times at which the expectation values and states were recorded.

states [list of `Qobj`] The state at each time t (if the recording of the state was requested).

final_state [`Qobj`:] The final state (if the recording of the final state was requested).

expect [list of arrays of expectation values] A list containing the values of each *e_op*. The list is in the same order in which the *e_ops* were supplied and empty if no *e_ops* were given.

Each element is itself a list and contains the values of the corresponding *e_op*, with one value for each time in *times*.

The same lists of values may be accessed via the *.e_data* dictionary and the original *e_ops* are available via the *.e_ops* attribute.

e_data [dict] A dictionary containing the values of each *e_op*. If the *e_ops* were supplied as a dictionary, the keys are the same as in that dictionary. Otherwise the keys are the index of the *e_op* in the *.expect* list.

The lists of expectation values returned are the *same* lists as those returned by `.expect`.

e_ops [dict] A dictionary containing the supplied `e_ops` as `ExpectOp` instances. The keys of the dictionary are the same as for `.e_data`. Each value is object where `.e_ops[k](t, state)` calculates the value of `e_op k` at time `t` and the given state, and `.e_ops[k].op` is the original object supplied to create the `e_op`.

solver [str or None] The name of the solver generating these results.

stats [dict or None] The stats generated by the solver while producing these results.

options [dict] The options for this result class.

add (*t, state*)

Add a state to the results for the time `t` of the evolution.

Adding a state calculates the expectation value of the state for each of the supplied `e_ops` and stores the result in `.expect`.

The state is recorded in `.states` and `.final_state` if specified by the supplied result options.

Parameters

t [float] The time of the added state.

state [typically a `Qobj`] The state at time `t`. Usually this is a `Qobj` with suitable dimensions, but it sub-classes of result might support other forms of the state.

.. note:: The expectation values, i.e. `e_ops`, and states are recorded by the state processors (see `.add_processor`).

Additional processors may be added by sub-classes.

5.1.10 Permutational Invariance

class Dicke (*N, hamiltonian=None, emission=0.0, dephasing=0.0, pumping=0.0, collective_emission=0.0, collective_dephasing=0.0, collective_pumping=0.0*)

The Dicke class which builds the Lindbladian and Liouvillian matrix.

Parameters

N: int The number of two-level systems.

hamiltonian [`qutip.Qobj`] A Hamiltonian in the Dicke basis.

The matrix dimensions are `(nds, nds)`, with `nds` being the number of Dicke states. The Hamiltonian can be built with the operators given by the *jspin* functions.

emission: float Incoherent emission coefficient (also nonradiative emission). default: 0.0

dephasing: float Local dephasing coefficient. default: 0.0

pumping: float Incoherent pumping coefficient. default: 0.0

collective_emission: float Collective (superradiant) emission coefficient. default: 0.0

collective_pumping: float Collective pumping coefficient. default: 0.0

collective_dephasing: float Collective dephasing coefficient. default: 0.0

Examples

```
>>> from piqs import Dicke, jspin
>>> N = 2
>>> jx, jy, jz = jspin(N)
>>> jp = jspin(N, "+")
>>> jm = jspin(N, "-")
>>> ensemble = Dicke(N, emission=1.)
>>> L = ensemble.liouvillian()
```

Attributes

N: int The number of two-level systems.

hamiltonian [`qutip.Qobj`] A Hamiltonian in the Dicke basis.

The matrix dimensions are (nds, nds), with nds being the number of Dicke states. The Hamiltonian can be built with the operators given by the *jspin* function in the “dicke” basis.

emission: float Incoherent emission coefficient (also nonradiative emission). default: 0.0

dephasing: float Local dephasing coefficient. default: 0.0

pumping: float Incoherent pumping coefficient. default: 0.0

collective_emission: float Collective (superradiant) emission coefficient. default: 0.0

collective_dephasing: float Collective dephasing coefficient. default: 0.0

collective_pumping: float Collective pumping coefficient. default: 0.0

nds: int The number of Dicke states.

dshape: tuple The shape of the Hilbert space in the Dicke or uncoupled basis. default: (nds, nds).

`c_ops()`

Build collapse operators in the full Hilbert space 2^N .

Returns

c_ops_list: list The list with the collapse operators in the 2^N Hilbert space.

`coefficient_matrix()`

Build coefficient matrix for ODE for a diagonal problem.

Returns

M: ndarray The matrix *M* of the coefficients for the ODE $dp/dt = Mp$. *p* is the vector of the diagonal matrix elements of the density matrix ρ in the Dicke basis.

`lindbladian()`

Build the Lindbladian superoperator of the dissipative dynamics.

Returns

lindbladian [`qutip.Qobj`] The Lindbladian matrix as a *qutip.Qobj*.

`liouvillian()`

Build the total Liouvillian using the Dicke basis.

Returns

liouv [`qutip.Qobj`] The Liouvillian matrix for the system.

`pisolve(initial_state, tlist, options=None)`

Solve for diagonal Hamiltonians and initial states faster.

Parameters

initial_state [qutip.Qobj] An initial state specified as a density matrix of *qutip.Qobj* type.

tlist: ndarray A 1D numpy array of list of timesteps to integrate

options [qutip.solver.SolverOptions] The options for the solver.

Returns

result: list A dictionary of the type *qutip.solver.Result* which holds the results of the evolution.

class Pim (*N, emission=0.0, dephasing=0, pumping=0, collective_emission=0, collective_pumping=0, collective_dephasing=0*)
The Permutation Invariant Matrix class.

Initialize the class with the parameters for generating a Permutation Invariant matrix which evolves a given diagonal initial state *p* as:

$$dp/dt = Mp$$

Parameters

N: int The number of two-level systems.

emission: float Incoherent emission coefficient (also nonradiative emission). default: 0.0

dephasing: float Local dephasing coefficient. default: 0.0

pumping: float Incoherent pumping coefficient. default: 0.0

collective_emission: float Collective (superradiant) emission coefficient. default: 0.0

collective_pumping: float Collective pumping coefficient. default: 0.0

collective_dephasing: float Collective dephasing coefficient. default: 0.0

Attributes

N: int The number of two-level systems.

emission: float Incoherent emission coefficient (also nonradiative emission). default: 0.0

dephasing: float Local dephasing coefficient. default: 0.0

pumping: float Incoherent pumping coefficient. default: 0.0

collective_emission: float Collective (superradiant) emission coefficient. default: 0.0

collective_dephasing: float Collective dephasing coefficient. default: 0.0

collective_pumping: float Collective pumping coefficient. default: 0.0

M: dict A nested dictionary of the structure {row: {col: val}} which holds non zero elements of the matrix M

calculate_j_m (*dicke_row, dicke_col*)

Get the value of j and m for the particular Dicke space element.

Parameters

dicke_row, dicke_col: int The row and column from the Dicke space matrix

Returns

j, m: float The j and m values.

calculate_k (*dicke_row, dicke_col*)

Get k value from the current row and column element in the Dicke space.

Parameters

dicke_row, dicke_col: int The row and column from the Dicke space matrix.

Returns

k: int The row index for the matrix M for given Dicke space element.

coefficient_matrix()

Generate the matrix M governing the dynamics for diagonal cases.

If the initial density matrix and the Hamiltonian is diagonal, the evolution of the system is given by the simple ODE: $dp/dt = Mp$.

isdicke(dicke_row, dicke_col)

Check if an element in a matrix is a valid element in the Dicke space. Dicke row: j value index. Dicke column: m value index. The function returns True if the element exists in the Dicke space and False otherwise.

Parameters

dicke_row, dicke_col [int] Index of the element in Dicke space which needs to be checked

solve(rho0, tlist, options=None)

Solve the ODE for the evolution of diagonal states and Hamiltonians.

tau1(j, m)

Calculate coefficient matrix element relative to (j, m, m).

tau2(j, m)

Calculate coefficient matrix element relative to (j, m+1, m+1).

tau3(j, m)

Calculate coefficient matrix element relative to (j+1, m+1, m+1).

tau4(j, m)

Calculate coefficient matrix element relative to (j-1, m+1, m+1).

tau5(j, m)

Calculate coefficient matrix element relative to (j+1, m, m).

tau6(j, m)

Calculate coefficient matrix element relative to (j-1, m, m).

tau7(j, m)

Calculate coefficient matrix element relative to (j+1, m-1, m-1).

tau8(j, m)

Calculate coefficient matrix element relative to (j, m-1, m-1).

tau9(j, m)

Calculate coefficient matrix element relative to (j-1, m-1, m-1).

tau_valid(dicke_row, dicke_col)

Find the Tau functions which are valid for this value of (dicke_row, dicke_col) given the number of TLS. This calculates the valid tau values and returns a dictionary specifying the tau function name and the value.

Parameters

dicke_row, dicke_col [int] Index of the element in Dicke space which needs to be checked.

Returns

taus: dict A dictionary of key, val as {tau: value} consisting of the valid taus for this row and column of the Dicke space element.

5.1.11 Distribution functions

class Distribution (*data=None, xvecs=[], xlabels=[]*)

A class for representation spatial distribution functions.

The Distribution class can be used to represent spatial distribution functions of arbitrary dimension (although only 1D and 2D distributions are used so far).

It is intended as a base class for specific distribution function, and provide implementation of basic functions that are shared among all Distribution functions, such as visualization, calculating marginal distributions, etc.

Parameters

data [array_like] Data for the distribution. The dimensions must match the lengths of the coordinate arrays in **xvecs**.

xvecs [list] List of arrays that spans the space for each coordinate.

xlabels [list] List of labels for each coordinate.

marginal (*dim=0*)

Calculate the marginal distribution function along the dimension *dim*. Return a new Distribution instance describing this reduced- dimensionality distribution.

Parameters

dim [int] The dimension (coordinate index) along which to obtain the marginal distribution.

Returns

d [Distributions] A new instances of Distribution that describes the marginal distribution.

project (*dim=0*)

Calculate the projection (max value) distribution function along the dimension *dim*. Return a new Distribution instance describing this reduced-dimensionality distribution.

Parameters

dim [int] The dimension (coordinate index) along which to obtain the projected distribution.

Returns

d [Distributions] A new instances of Distribution that describes the projection.

visualize (*fig=None, ax=None, figsize=(8, 6), colorbar=True, cmap=None, style='colormap', show_xlabel=True, show_ylabel=True*)

Visualize the data of the distribution in 1D or 2D, depending on the dimensionality of the underlying distribution.

Parameters:

fig [matplotlib Figure instance] If given, use this figure instance for the visualization,

ax [matplotlib Axes instance] If given, render the visualization using this axis instance.

figsize [tuple] Size of the new Figure instance, if one needs to be created.

colorbar: Bool Whether or not the colorbar (in 2D visualization) should be used.

cmap: matplotlib colormap instance If given, use this colormap for 2D visualizations.

style [string] Type of visualization: 'colormap' (default) or 'surface'.

Returns

fig, ax [tuple] A tuple of matplotlib figure and axes instances.

```

class WignerDistribution (rho=None, extent=[[- 5, 5], [- 5, 5]], steps=250)

class QDistribution (rho=None, extent=[[- 5, 5], [- 5, 5]], steps=250)

class TwoModeQuadratureCorrelation (state=None, theta1=0.0, theta2=0.0, extent=[[- 5, 5],
[- 5, 5]], steps=250)

    update (state)
        calculate probability distribution for quadrature measurement outcomes given a two-mode wavefunc-
        tion or density matrix

    update_psi (psi)
        calculate probability distribution for quadrature measurement outcomes given a two-mode wavefunc-
        tion

    update_rho (rho)
        calculate probability distribution for quadrature measurement outcomes given a two-mode density
        matrix

class HarmonicOscillatorWaveFunction (psi=None, omega=1.0, extent=[- 5, 5], steps=250)

    update (psi)
        Calculate the wavefunction for the given state of an harmonic oscillator

class HarmonicOscillatorProbabilityFunction (rho=None, omega=1.0, extent=[- 5, 5],
steps=250)

    update (rho)
        Calculate the probability function for the given state of an harmonic oscillator (as density matrix)

```

5.1.12 Optimal control

class Optimizer (*config, dyn, params=None*)
Base class for all control pulse optimisers. This class should not be instantiated, use its subclasses. This class implements the fidelity, gradient and iteration callback functions. All subclass objects must be initialised with a

- `OptimConfig` instance - various configuration options
- `Dynamics` instance - describes the dynamics of the (quantum) system to be control optimised

Attributes

log_level [integer] level of messaging output from the logger. Options are attributes of `qutip.logging_utils`, in decreasing levels of messaging, are: `DEBUG_INTENSE`, `DEBUG_VERBOSE`, `DEBUG`, `INFO`, `WARN`, `ERROR`, `CRITICAL`. Anything `WARN` or above is effectively ‘quiet’ execution, assuming everything runs as expected. The default `NOTSET` implies that the level will be taken from the QuTiP settings file, which by default is `WARN`.

params: Dictionary The key value pairs are the attribute name and value. Note: attributes are created if they do not exist already, and are overwritten if they do.

alg [string] Algorithm to use in pulse optimisation. Options are:

- ‘GRAPE’ (default) - GRAdient Ascent Pulse Engineering
- ‘CRAB’ - Chopped RANdom Basis

alg_params [Dictionary] Options that are specific to the pulse optim algorithm `alg`.

disp_conv_msg [bool] Set true to display a convergence message (for `scipy.optimize.minimize` methods anyway)

optim_method [string] a `scipy.optimize.minimize` method that will be used to optimise the pulse for minimum fidelity error

method_params [Dictionary] Options for the `optim_method`. Note that where there is an equivalent attribute of this instance or the `termination_conditions` (for example `maxiter`) it will override an value in these options

approx_grad [bool] If set `True` then the method will approximate the gradient itself (if it has requirement and facility for this) This will mean that the `fid_err_grad_wrapper` will not get called Note it should be left `False` when using the Dynamics to calculate approximate gradients Note it is set `True` automatically when the alg is CRAB

amp_lbound [float or list of floats] lower boundaries for the control amplitudes Can be a scalar value applied to all controls or a list of bounds for each control

amp_ubound [float or list of floats] upper boundaries for the control amplitudes Can be a scalar value applied to all controls or a list of bounds for each control

bounds [List of floats] Bounds for the parameters. If not set before the `run_optimization` call then the list is built automatically based on the `amp_lbound` and `amp_ubound` attributes. Setting this attribute directly allows specific bounds to be set for individual parameters. Note: Only some methods use bounds

dynamics [Dynamics (subclass instance)] describes the dynamics of the (quantum) system to be control optimised (see Dynamics classes for details)

config [OptimConfig instance] various configuration options (see OptimConfig for details)

termination_conditions [TerminationCondition instance] attributes determine when the optimisation will end

pulse_generator [PulseGen (subclass instance)] (can be) used to create initial pulses not used by the class, but set by `pulseoptim.create_pulse_optimizer`

stats [Stats] attributes of which give performance stats for the optimisation set to `None` to reduce overhead of calculating stats. Note it is (usually) shared with the Dynamics instance

dump [`qutip.control.dump.OptimDump`] Container for data dumped during the optimisation. Can be set by specifying the dumping level or set directly. Note this is mainly intended for user and a development debugging but could be used for status information during a long optimisation.

dumping [string] The level of data dumping that will occur during the optimisation

dump_to_file [bool] If set `True` then data will be dumped to file during the optimisation dumping will be set to `SUMMARY` during `init_optim` if `dump_to_file` is `True` and dumping not set. Default is `False`

dump_dir [string] Basically a link to `dump.dump_dir`. Exists so that it can be set through `optim_params`. If `dump` is `None` then will return `None` or will set dumping to `SUMMARY` when setting a path

iter_summary [`OptimIterSummary`] Summary of the most recent iteration. Note this is only set if dumping is on

apply_method_params (*params=None*)

Loops through all the `method_params` (either passed here or the `method_params` attribute) If the name matches an attribute of this object or the `termination_conditions` object, then the value of this attribute is set. Otherwise it is assumed to a `method_option` for the `scipy.optimize.minimize` function

apply_params (*params=None*)

Set object attributes based on the dictionary (if any) passed in the instantiation, or passed as a parameter This is called during the instantiation automatically. The key value pairs are the attribute name and value Note: attributes are created if they do not exist already, and are overwritten if they do.

property dumping

The level of data dumping that will occur during the optimisation

- NONE : No processing data dumped (Default)
- SUMMARY : A summary at each iteration will be recorded
- FULL : All logs will be generated and dumped
- CUSTOM : Some customised level of dumping

When first set to CUSTOM this is equivalent to SUMMARY. It is then up to the user to specify which logs are dumped

fid_err_func_wrapper (*args)

Get the fidelity error achieved using the ctrl amplitudes passed in as the first argument.

This is called by generic optimisation algorithm as the func to the minimised. The argument is the current variable values, i.e. control amplitudes, passed as a flat array. Hence these are reshaped as [nTimeslots, n_ctrls] and then used to update the stored ctrl values (if they have changed)

The error is checked against the target, and the optimisation is terminated if the target has been achieved.

fid_err_grad_wrapper (*args)

Get the gradient of the fidelity error with respect to all of the variables, i.e. the ctrl amplitudes in each timeslot

This is called by generic optimisation algorithm as the gradients of func to the minimised wrt the variables. The argument is the current variable values, i.e. control amplitudes, passed as a flat array. Hence these are reshaped as [nTimeslots, n_ctrls] and then used to update the stored ctrl values (if they have changed)

Although the optimisation algorithms have a check within them for function convergence, i.e. local minima, the sum of the squares of the normalised gradient is checked explicitly, and the optimisation is terminated if this is below the min_gradient_norm condition

init_optim (term_conds)

Check optimiser attribute status and passed parameters before running the optimisation. This is called by run_optimization, but could called independently to check the configuration.

iter_step_callback_func (*args)

Check the elapsed wall time for the optimisation run so far. Terminate if this has exceeded the maximum allowed time

run_optimization (term_conds=None)

This default function optimisation method is a wrapper to the scipy.optimize.minimize function.

It will attempt to minimise the fidelity error with respect to some parameters, which are determined by _get_optim_var_vals (see below)

The optimisation end when one of the passed termination conditions has been met, e.g. target achieved, wall time, or function call or iteration count exceeded. Note these conditions include gradient minimum met (local minima) for methods that use a gradient.

The function minimisation method is taken from the optim_method attribute. Note that not all of these methods have been tested. Note that some of these use a gradient and some do not. See the scipy documentation for details. Options specific to the method can be passed setting the method_params attribute.

If the parameter term_conds=None, then the termination_conditions attribute must already be set. It will be overwritten if the parameter is not None

The result is returned in an OptimResult object, which includes the final fidelity, time evolution, reason for termination etc

class OptimizerBFGS (config, dyn, params=None)

Implements the run_optimization method using the BFGS algorithm

run_optimization (*term_conds=None*)

Optimise the control pulse amplitudes to minimise the fidelity error using the BFGS (Broyden–Fletcher–Goldfarb–Shanno) algorithm. The optimisation ends when one of the passed termination conditions has been met, e.g. target achieved, gradient minimum met (local minima), wall time / iteration count exceeded.

Essentially this is a wrapper to the: `scipy.optimize.fmin_bfgs` function

If the parameter `term_conds=None`, then the `termination_conditions` attribute must already be set. It will be overwritten if the parameter is not `None`.

The result is returned in an `OptimResult` object, which includes the final fidelity, time evolution, reason for termination etc.

class OptimizerLBFGSB (*config, dyn, params=None*)

Implements the `run_optimization` method using the L-BFGS-B algorithm

Attributes

max_metric_corr [integer] The maximum number of variable metric corrections used to define the limited memory matrix. That is the number of previous gradient values that are used to approximate the Hessian see the `scipy.optimize.fmin_l_bfgs_b` documentation for description of `m` argument

init_optim (*term_conds*)

Check optimiser attribute status and passed parameters before running the optimisation. This is called by `run_optimization`, but could be called independently to check the configuration.

run_optimization (*term_conds=None*)

Optimise the control pulse amplitudes to minimise the fidelity error using the L-BFGS-B algorithm, which is the constrained (bounded amplitude values), limited memory, version of the Broyden–Fletcher–Goldfarb–Shanno algorithm.

The optimisation ends when one of the passed termination conditions has been met, e.g. target achieved, gradient minimum met (local minima), wall time / iteration count exceeded.

Essentially this is a wrapper to the: `scipy.optimize.fmin_l_bfgs_b` function. This in turn is a wrapper for a well established implementation of the L-BFGS-B algorithm written in Fortran, which is therefore very fast. See SciPy documentation for credit and details on this function.

If the parameter `term_conds=None`, then the `termination_conditions` attribute must already be set. It will be overwritten if the parameter is not `None`.

The result is returned in an `OptimResult` object, which includes the final fidelity, time evolution, reason for termination etc.

class OptimizerCrab (*config, dyn, params=None*)

Optimises the pulse using the CRAB algorithm [1]. It uses the `scipy.optimize.minimize` function with the method specified by the `optim_method` attribute. See `Optimizer.run_optimization` for details. It minimises the fidelity error function with respect to the CRAB basis function coefficients.

AJGP ToDo: Add citation here

init_optim (*term_conds*)

Check optimiser attribute status and passed parameters before running the optimisation. This is called by `run_optimization`, but could be called independently to check the configuration.

class OptimizerCrabFmin (*config, dyn, params=None*)

Optimises the pulse using the CRAB algorithm [1], [2]. It uses the `scipy.optimize.fmin` function which is effectively a wrapper for the Nelder-Mead method. It minimises the fidelity error function with respect to the CRAB basis function coefficients. This is the default Optimizer for CRAB.

References

[1], [2]

run_optimization (*term_conds=None*)

This function optimisation method is a wrapper to the `scipy.optimize.fmin` function.

It will attempt to minimise the fidelity error with respect to some parameters, which are determined by `_get_optim_var_vals` which in the case of CRAB are the basis function coefficients

The optimisation end when one of the passed termination conditions has been met, e.g. target achieved, wall time, or function call or iteration count exceeded. Specifically to the `fmin` method, the optimisation will stop when change parameter values is less than `xtol` or the change in function value is below `ftol`.

If the parameter `term_conds=None`, then the `termination_conditions` attribute must already be set. It will be overwritten if the parameter is not `None`

The result is returned in an `OptimResult` object, which includes the final fidelity, time evolution, reason for termination etc

class OptimIterSummary

A summary of the most recent iteration of the pulse optimisation

Attributes

iter_num [int] Iteration number of the pulse optimisation

fid_func_call_num [int] Fidelity function call number of the pulse optimisation

grad_func_call_num [int] Gradient function call number of the pulse optimisation

fid_err [float] Fidelity error

grad_norm [float] fidelity gradient (wrt the control parameters) vector norm that is the magnitude of the gradient

wall_time [float] Time spent computing the pulse optimisation so far (in seconds of elapsed time)

class TerminationConditions

Base class for all termination conditions Used to determine when to stop the optimisation algorithm Note different subclasses should be used to match the type of optimisation being used

Attributes

fid_err_targ [float] Target fidelity error

fid_goal [float] goal fidelity, e.g. `1 - self.fid_err_targ` It its typical to set this for unitary systems

max_wall_time [float] # maximum time for optimisation (seconds)

min_gradient_norm [float] Minimum normalised gradient after which optimisation will terminate

max_iterations [integer] Maximum iterations of the optimisation algorithm

max_fid_func_calls [integer] Maximum number of calls to the fidelity function during the optimisation algorithm

accuracy_factor [float] Determines the accuracy of the result. Typical values for `accuracy_factor` are: `1e12` for low accuracy; `1e7` for moderate accuracy; `10.0` for extremely high accuracy `scipy.optimize.fmin_l_bfgs_b` `factr` argument. Only set for specific methods (`fmin_l_bfgs_b`) that uses this Otherwise the same thing is passed as `method_option` `ftol` (although the scale is different) Hence it is not defined here, but may be set by the user

class OptimResult

Attributes give the result of the pulse optimisation attempt

Attributes

termination_reason [string] Description of the reason for terminating the optimisation

fidelity [float] final (normalised) fidelity that was achieved

initial_fid_err [float] fidelity error before optimisation starting

fid_err [float] final fidelity error that was achieved

goal_achieved [boolean] True if the fidelity error achieved was below the target

grad_norm_final [float] Final value of the sum of the squares of the (normalised) fidelity error gradients

grad_norm_min_reached [float] True if the optimisation terminated due to the minimum value of the gradient being reached

num_iter [integer] Number of iterations of the optimisation algorithm completed

max_iter_exceeded [boolean] True if the iteration limit was reached

max_fid_func_exceeded [boolean] True if the fidelity function call limit was reached

wall_time [float] time elapsed during the optimisation

wall_time_limit_exceeded [boolean] True if the wall time limit was reached

time [array[num_tslots+1] of float] Time are the start of each timeslot with the final value being the total evolution time

initial_amps [array[num_tslots, n_ctrls]] The amplitudes at the start of the optimisation

final_amps [array[num_tslots, n_ctrls]] The amplitudes at the end of the optimisation

evo_full_final [Qobj] The evolution operator from t=0 to t=T based on the final amps

evo_full_initial [Qobj] The evolution operator from t=0 to t=T based on the initial amps

stats [Stats] Object containing the stats for the run (if any collected)

optimizer [Optimizer] Instance of the Optimizer used to generate the result

class Dynamics (*optimconfig, params=None*)

This is a base class only. See subclass descriptions and choose an appropriate one for the application.

Note that `initialize_controls` must be called before most of the methods can be used. `init_timesteps` can be called sometimes earlier in order to access timeslot related attributes

This acts as a container for the operators that are used to calculate time evolution of the system under study. That is the dynamics generators (Hamiltonians, Lindbladians etc), the propagators from one timeslot to the next, and the evolution operators. Due to the large number of matrix additions and multiplications, for small systems at least, the optimisation performance is much better using `ndarrays` to represent these operators. However

Attributes

log_level [integer] level of messaging output from the logger. Options are attributes of `qutip.logging_utils`, in decreasing levels of messaging, are: `DEBUG_INTENSE`, `DEBUG_VERBOSE`, `DEBUG`, `INFO`, `WARN`, `ERROR`, `CRITICAL`. Anything `WARN` or above is effectively 'quiet' execution, assuming everything runs as expected. The default `NOTSET` implies that the level will be taken from the QuTiP settings file, which by default is `WARN`

params: Dictionary The key value pairs are the attribute name and value. Note: attributes are created if they do not exist already, and are overwritten if they do.

stats [Stats] Attributes of which give performance stats for the optimisation set to `None` to reduce overhead of calculating stats. Note it is (usually) shared with the Optimizer object

tslot_computer [TimeslotComputer (subclass instance)] Used to manage when the timeslot dynamics generators, propagators, gradients etc are updated

prop_computer [PropagatorComputer (subclass instance)] Used to compute the propagators and their gradients

fid_computer [FidelityComputer (subclass instance)] Used to compute the fidelity error and the fidelity error gradient.

memory_optimization [int] Level of memory optimisation. Setting to 0 (default) means that execution speed is prioritized over memory. Setting to 1 means that some memory prioritisation steps will be taken, for instance using Qobj (and hence sparse arrays) as the internal operator data type, and not caching some operators. Potentially further memory saving may be made with `memory_optimization > 1`. The options are processed in `_set_memory_optimizations`, see this for more information. Individual memory saving options can be switched by setting them directly (see below)

oper_dtype [type] Data type for internal dynamics generators, propagators and time evolution operators. This can be ndarray or Qobj. Qobj may perform better for larger systems, and will also perform better when (custom) fidelity measures use Qobj methods such as partial trace. See `_choose_oper_dtype` for how this is chosen when not specified

cache_phased_dyn_gen [bool] If True then the dynamics generators will be saved with and without the propagation prefactor (if there is one) Defaults to True when `memory_optimization=0`, otherwise False

cache_prop_grad [bool] If the True then the propagator gradients (for exact gradients) will be computed when the propagator are computed and cache until they are used by the fidelity computer. If False then the fidelity computer will calculate them as needed. Defaults to True when `memory_optimization=0`, otherwise False

cache_dyn_gen_eigenvectors_adj: bool If True then DynamicsUnitary will cache the adjoint of the Hamiltonian eigenvector matrix Defaults to True when `memory_optimization=0`, otherwise False

sparse_eigen_decomp: bool If True then DynamicsUnitary will use the sparse eigenvalue decomposition. Defaults to True when `memory_optimization <= 1`, otherwise False

num_tslots [integer] Number of timeslots (aka timeslices)

num_ctrls [integer] calculate the of controls from the length of the control list

evo_time [float] Total time for the evolution

tau [array[num_tslots] of float] Duration of each timeslot Note that if this is set before `initialize_controls` is called then `num_tslots` and `evo_time` are calculated from `tau`, otherwise `tau` is generated from `num_tslots` and `evo_time`, that is equal size time slices

time [array[num_tslots+1] of float] Cumulative time for the evolution, that is the time at the start of each time slice

drift_dyn_gen [Qobj or list of Qobj] Drift or system dynamics generator (Hamiltonian) Matrix defining the underlying dynamics of the system Can also be a list of Qobj (length `num_tslots`) for time varying drift dynamics

ctrl_dyn_gen [List of Qobj] Control dynamics generator (Hamiltonians) List of matrices defining the control dynamics

initial [Qobj] Starting state / gate The matrix giving the initial state / gate, i.e. at time 0 Typically the identity for gate evolution

target [Qobj] Target state / gate: The matrix giving the desired state / gate for the evolution

ctrl_amps [array[num_tslots, num_ctrls] of float] Control amplitudes The amplitude (scale factor) for each control in each timeslot

initial_ctrl_scaling [float] Scale factor applied to be applied the control amplitudes when they are initialised This is used by the PulseGens rather than in any fucntions in this class

initial_ctrl_offset [float] Linear offset applied to be applied the control amplitudes when they are initialised This is used by the PulseGens rather than in any fucntions in this class

dyn_gen [List of Qobj] List of combined dynamics generators (Qobj) for each timeslot

prop [list of Qobj] List of propagators (Qobj) for each timeslot

prop_grad [array[num_tslots, num_ctrls] of Qobj] Array of propagator gradients (Qobj) for each timeslot, control

fwd_evo [List of Qobj] List of evolution operators (Qobj) from the initial to the given

onwd_evo [List of Qobj] List of evolution operators (Qobj) from the initial to the given

onto_evo [List of Qobj] List of evolution operators (Qobj) from the initial to the given

evo_current [Boolean] Used to flag that the dynamics used to calculate the evolution operators is current. It is set to False when the amplitudes change

fact_mat_round_prec [float] Rounding precision used when calculating the factor matrix to determine if two eigenvalues are equivalent Only used when the PropagatorComputer uses diagonalisation

def_amps_fname [string] Default name for the output used when save_amps is called

unitarity_check_level [int] If > 0 then unitarity of the system evolution is checked at at evolution recomputation. level 1 checks all propagators level 2 checks eigen basis as well Default is 0

unitarity_tol : Tolerance used in checking if operator is unitary Default is 1e-10

dump [*qutip.control.dump.DynamicsDump*] Store of historical calculation data. Set to None (Default) for no storing of historical data Use dumping property to set level of data dumping

dumping [string] The level of data dumping that will occur during the time evolution calculation.

dump_to_file [bool] If set True then data will be dumped to file during the calculations dumping will be set to SUMMARY during init_evo if dump_to_file is True and dumping not set. Default is False

dump_dir [string] Basically a link to dump.dump_dir. Exists so that it can be set through dyn_params. If dump is None then will return None or will set dumping to SUMMARY when setting a path

apply_params (*params=None*)

Set object attributes based on the dictionary (if any) passed in the instantiation, or passed as a parameter This is called during the instantiation automatically. The key value pairs are the attribute name and value Note: attributes are created if they do not exist already, and are overwritten if they do.

combine_dyn_gen (*k*)

Computes the dynamics generator for a given timeslot The is the combined Hamiltonian for unitary systems

compute_evolution ()

Recalculate the time evolution operators Dynamics generators (e.g. Hamiltonian) and prop (propagators) are calculated as necessary Actual work is completed by the recompute_evolution method of the timeslot computer

property dumping

The level of data dumping that will occur during the time evolution calculation.

- NONE : No processing data dumped (Default)

- SUMMARY : A summary of each time evolution will be recorded
- FULL : All operators used or created in the calculation dumped
- CUSTOM : Some customised level of dumping

When first set to CUSTOM this is equivalent to SUMMARY. It is then up to the user to specify which operators are dumped. WARNING: FULL could consume a lot of memory!

property dyn_gen

List of combined dynamics generators (Qobj) for each timeslot

property dyn_gen_phase

Some op that is applied to the dyn_gen before exponentiating to get the propagator. See *phase_application* for how this is applied

flag_system_changed()

Flag evolution, fidelity and gradients as needing recalculation

property full_evo

Full evolution - time evolution at final time slot

property fwd_evo

List of evolution operators (Qobj) from the initial to the given timeslot

get_ctrl_dyn_gen(j)

Get the dynamics generator for the control Not implemented in the base class. Choose a subclass

get_drift_dim()

Returns the size of the matrix that defines the drift dynamics that is assuming the drift is NxN, then this returns N

get_dyn_gen(k)

Get the combined dynamics generator for the timeslot Not implemented in the base class. Choose a subclass

get_num_ctrls()

calculate the of controls from the length of the control list sets the num_ctrls property, which can be used alternatively subsequently

init_timeslots()

Generate the timeslot duration array 'tau' based on the evo_time and num_tsots attributes, unless the tau attribute is already set in which case this step is ignored Generate the cumulative time array 'time' based on the tau values

initialize_controls(amps, init_tsots=True)

Set the initial control amplitudes and time slices Note this must be called after the configuration is complete before any dynamics can be calculated

property num_ctrls

calculate the of controls from the length of the control list sets the num_ctrls property, which can be used alternatively subsequently

property onto_evo

List of evolution operators (Qobj) from the initial to the given timeslot

property onwd_evo

List of evolution operators (Qobj) from the initial to the given timeslot

property phase_application

scalar(string), default='preop' Determines how the phase is applied to the dynamics generators

- 'preop' : $P = \text{expm}(\text{phase} * \text{dyn_gen})$
- 'postop' : $P = \text{expm}(\text{dyn_gen} * \text{phase})$
- 'custom' : Customised phase application

The 'custom' option assumes that the `_apply_phase` method has been set to a custom function.

Type `phase_application`

property prop

List of propagators (Qobj) for each timeslot

property prop_grad

Array of propagator gradients (Qobj) for each timeslot, control

refresh_drift_attribs()

Reset the `dyn_shape`, `dyn_dims` and `time_depend_drift` attribs

save_amps (*file_name=None, times=None, amps=None, verbose=False*)

Save a file with the current control amplitudes in each timeslot. The first column in the file will be the start time of the slot

Parameters

file_name [string] Name of the file. If None given the `def_amps_fname` attribute will be used

times [List type (or string)] List / array of the start times for each slot. If None given this will be retrieved through `get_amp_times()`. If 'exclude' then times will not be saved in the file, just the amplitudes

amps [Array[num_tslots, num_ctrls]] Amplitudes to be saved. If None given the `ctrl_amps` attribute will be used

verbose [Boolean] If True then an info message will be logged

unitarity_check()

Checks whether all propagators are unitary

update_ctrl_amps (*new_amps*)

Determine if any amplitudes have changed. If so, then mark the timeslots as needing recalculation. The actual work is completed by the `compare_amps` method of the timeslot computer

class DynamicsGenMat (*optimconfig, params=None*)

This sub class can be used for any system where no additional operator is applied to the dynamics generator before calculating the propagator, e.g. classical dynamics, Lindbladian

class DynamicsUnitary (*optimconfig, params=None*)

This is the subclass to use for systems with dynamics described by unitary matrices. E.g. closed systems with Hermitian Hamiltonians. Note a matrix diagonalisation is used to compute the exponent. The eigen decomposition is also used to calculate the propagator gradient. The method is taken from DYNAMO (see file header)

Attributes

drift_ham [Qobj] This is the drift Hamiltonian for unitary dynamics. It is mapped to `drift_dyn_gen` during `initialize_controls`

ctrl_ham [List of Qobj] These are the control Hamiltonians for unitary dynamics. It is mapped to `ctrl_dyn_gen` during `initialize_controls`

H [List of Qobj] The combined drift and control Hamiltonians for each timeslot. These are the dynamics generators for unitary dynamics. It is mapped to `dyn_gen` during `initialize_controls`

check_unitarity()

Checks whether all propagators are unitary. For propagators found not to be unitary, the potential underlying causes are investigated.

initialize_controls (*amplitudes, init_tslots=True*)

Set the initial control amplitudes and time slices. Note this must be called after the configuration is complete before any dynamics can be calculated

property num_ctrls

calculate the of controls from the length of the control list sets the num_ctrls property, which can be used alternatively subsequently

class DynamicsSymplectic (*optimconfig, params=None*)

Symplectic systems This is the subclass to use for systems where the dynamics is described by symplectic matrices, e.g. coupled oscillators, quantum optics

Attributes

omega [array[drift_dyn_gen.shape]] matrix used in the calculation of propagators (time evolution) with symplectic systems.

property dyn_gen_phase

The phasing operator for the symplectic group generators usually referred to as Omega By default this is applied as 'postop' dyn_gen*-Omega If phase_application is 'preop' it is applied as Omega*dyn_gen

class PropagatorComputer (*dynamics, params=None*)

Base for all Propagator Computer classes that are used to calculate the propagators, and also the propagator gradient when exact gradient methods are used Note: they must be instantiated with a Dynamics object, that is the container for the data that the functions operate on This base class cannot be used directly. See subclass descriptions and choose the appropriate one for the application

Attributes

log_level [integer] level of messaging output from the logger. Options are attributes of qutip_utils.logging, in decreasing levels of messaging, are: DEBUG_INTENSE, DEBUG_VERBOSE, DEBUG, INFO, WARN, ERROR, CRITICAL Anything WARN or above is effectively 'quiet' execution, assuming everything runs as expected. The default NOTSET implies that the level will be taken from the QuTiP settings file, which by default is WARN

grad_exact [boolean] indicates whether the computer class instance is capable of computing propagator gradients. It is used to determine whether to create the Dynamics prop_grad array

apply_params (*params=None*)

Set object attributes based on the dictionary (if any) passed in the instantiation, or passed as a parameter This is called during the instantiation automatically. The key value pairs are the attribute name and value Note: attributes are created if they do not exist already, and are overwritten if they do.

reset ()

reset any configuration data

class PropCompApproxGrad (*dynamics, params=None*)

This subclass can be used when the propagator is calculated simply by expm of the dynamics generator, i.e. when gradients will be calculated using approximate methods.

reset ()

reset any configuration data

class PropCompDiag (*dynamics, params=None*)

Computes the propagator exponentiation using diagonalisation of the dynamics generator

reset ()

reset any configuration data

class PropCompFrechet (*dynamics, params=None*)

Frechet method for calculating the propagator: exponentiating the combined dynamics generator and the propagator gradient. It should work for all systems, e.g. unitary, open, symplectic. There are other *PropagatorComputer* subclasses that may be more efficient.

reset ()

reset any configuration data

class FidelityComputer (*dynamics, params=None*)

Base class for all Fidelity Computers. This cannot be used directly. See subclass descriptions and choose

one appropriate for the application Note: this must be instantiated with a Dynamics object, that is the container for the data that the methods operate on

Attributes

log_level [integer] level of messaging output from the logger. Options are attributes of `qutip.logging_utils`, in decreasing levels of messaging, are: `DEBUG_INTENSE`, `DEBUG_VERBOSE`, `DEBUG`, `INFO`, `WARN`, `ERROR`, `CRITICAL`. Anything `WARN` or above is effectively ‘quiet’ execution, assuming everything runs as expected. The default `NOTSET` implies that the level will be taken from the QuTiP settings file, which by default is `WARN`

dimensional_norm [float] Normalisation constant

fid_norm_func [function] Used to normalise the fidelity See `SU` and `PSU` options for the unitary dynamics

grad_norm_func [function] Used to normalise the fidelity gradient See `SU` and `PSU` options for the unitary dynamics

uses_onwd_evo [boolean] flag to specify whether the `onwd_evo` evolution operator (see Dynamics) is used by the `FidelityComputer`

uses_onto_evo [boolean]

flag to specify whether the `onto_evo` evolution operator (see Dynamics) is used by the `FidelityComputer`

fid_err [float] Last computed value of the fidelity error

fidelity [float] Last computed value of the normalised fidelity

fidelity_current [boolean] flag to specify whether the fidelity / `fid_err` are based on the current amplitude values. Set `False` when amplitudes change

fid_err_grad: array[num_tslot, num_ctrls] of float Last computed values for the fidelity error gradients wrt the control in the timeslot

grad_norm [float] Last computed value for the norm of the fidelity error gradients (sqrt of the sum of the squares)

fid_err_grad_current [boolean] flag to specify whether the fidelity / `fid_err` are based on the current amplitude values. Set `False` when amplitudes change

apply_params (*params=None*)

Set object attributes based on the dictionary (if any) passed in the instantiation, or passed as a parameter This is called during the instantiation automatically. The key value pairs are the attribute name and value Note: attributes are created if they do not exist already, and are overwritten if they do.

clear ()

clear any temporarily held status data

flag_system_changed ()

Flag fidelity and gradients as needing recalculation

get_fid_err ()

returns the absolute distance from the maximum achievable fidelity

get_fid_err_gradient ()

Returns the normalised gradient of the fidelity error in a (`nTimeslots` x `n_ctrls`) array wrt the timeslot control amplitude

init_comp ()

initialises the computer based on the configuration of the Dynamics

reset ()

reset any configuration data and clear any temporarily held status data

class FidCompUnitary (*dynamics, params=None*)

Computes fidelity error and gradient assuming unitary dynamics, e.g. closed qubit systems Note fidelity and gradient calculations were taken from DYNAMO (see file header)

Attributes

phase_option [string]

determines how global phase is treated in fidelity calculations: PSU - global phase ignored
SU - global phase included

fidelity_prenorm [complex] Last computed value of the fidelity before it is normalised It is stored to use in the gradient normalisation calculation

fidelity_prenorm_current [boolean] flag to specify whether fidelity_prenorm are based on the current amplitude values. Set False when amplitudes change

clear ()

clear any temporarily held status data

compute_fid_grad ()

Calculates exact gradient of function wrt to each timeslot control amplitudes. Note these gradients are not normalised These are returned as a (nTimeslots x n_ctrls) array

flag_system_changed ()

Flag fidelity and gradients as needing recalculation

get_fid_err ()

Gets the absolute error in the fidelity

get_fid_err_gradient ()

Returns the normalised gradient of the fidelity error in a (nTimeslots x n_ctrls) array The gradients are cached in case they are requested multiple times between control updates (although this is not typically found to happen)

get_fidelity ()

Gets the appropriately normalised fidelity value The normalisation is determined by the fid_norm_func pointer which should be set in the config

get_fidelity_prenorm ()

Gets the current fidelity value prior to normalisation Note the gradient function uses this value The value is cached, because it is used in the gradient calculation

init_comp ()

Check configuration and initialise the normalisation

init_normalization ()

Calc norm of $\langle U_{\text{final}} | U_{\text{final}} \rangle$ to scale subsequent norms When considering unitary time evolution operators, this basically results in calculating the trace of the identity matrix and is hence equal to the size of the target matrix There may be situations where this is not the case, and hence it is not assumed to be so. The normalisation function called should be set to either the PSU - global phase ignored SU - global phase respected

normalize_gradient_PSU (*grad*)

Normalise the gradient matrix passed as grad This PSU version is independent of global phase

normalize_gradient_SU (*grad*)

Normalise the gradient matrix passed as grad This SU version respects global phase

reset ()

reset any configuration data and clear any temporarily held status data

set_phase_option (*phase_option=None*)

Deprecated - use phase_option Phase options are SU - global phase important PSU - global phase is not important

class FidCompTraceDiff (*dynamics, params=None*)

Computes fidelity error and gradient for general system dynamics by calculating the the fidelity error as the trace of the overlap of the difference between the target and evolution resulting from the pulses with the transpose of the same. This should provide a distance measure for dynamics described by matrices Note the gradient calculation is taken from: ‘Robust quantum gates for open systems via optimal control: Markovian versus non-Markovian dynamics’ Frederik F Floether, Pierre de Fouquieres, and Sophie G Schirmer

Attributes

scale_factor [float] The fidelity error calculated is of some arbitrary scale. This factor can be used to scale the fidelity error such that it may represent some physical measure If None is given then it is caculated as $1/2N$, where N is the dimension of the drift, when the Dynamics are initialised.

compute_fid_err_grad ()

Calculate exact gradient of the fidelity error function wrt to each timeslot control amplitudes. Uses the trace difference norm fidelity These are returned as a (nTimeslots x n_ctrls) array

get_fid_err ()

Gets the absolute error in the fidelity

get_fid_err_gradient ()

Returns the normalised gradient of the fidelity error in a (nTimeslots x n_ctrls) array The gradients are cached in case they are requested mutliple times between control updates (although this is not typically found to happen)

init_comp ()

initialises the computer based on the configuration of the Dynamics Calculates the scale_factor is not already set

reset ()

reset any configuration data and clear any temporarily held status data

class FidCompTraceDiffApprox (*dynamics, params=None*)

As FidCompTraceDiff, except uses the finite difference method to compute approximate gradients

Attributes

epsilon [float] control amplitude offset to use when approximating the gradient wrt a timeslot control amplitude

compute_fid_err_grad ()

Calculates gradient of function wrt to each timeslot control amplitudes. Note these gradients are not normalised They are calulated These are returned as a (nTimeslots x n_ctrls) array

reset ()

reset any configuration data and clear any temporarily held status data

class TimeslotComputer (*dynamics, params=None*)

Base class for all Timeslot Computers Note: this must be instantiated with a Dynamics object, that is the container for the data that the methods operate on

Attributes

log_level [integer] level of messaging output from the logger. Options are attributes of `qutip.logging_utils`, in decreasing levels of messaging, are: `DEBUG_INTENSE`, `DEBUG_VERBOSE`, `DEBUG`, `INFO`, `WARN`, `ERROR`, `CRITICAL` Anything `WARN` or above is effectively ‘quiet’ execution, assuming everything runs as expected. The default `NOTSET` implies that the level will be taken from the QuTiP settings file, which by default is `WARN`

evo_comp_summary [EvoCompSummary] A summary of the most recent evolution computation Used in the stats and dump Will be set to None if neither stats or dump are set

apply_params (*params=None*)

Set object attributes based on the dictionary (if any) passed in the instantiation, or passed as a parameter

This is called during the instantiation automatically. The key value pairs are the attribute name and value Note: attributes are created if they do not exist already, and are overwritten if they do.

dump_current ()

Store a copy of the current time evolution

class TSlotCompUpdateAll (*dynamics, params=None*)

Timeslot Computer - Update All Updates all dynamics generators, propagators and evolutions when ctrl amplitudes are updated

compare_amps (*new_amps*)

Determine if any amplitudes have changed. If so, then mark the timeslots as needing recalculation Returns: True if amplitudes are the same, False if they have changed

get_timeslot_for_fidelity_calc ()

Returns the timeslot index that will be used calculate current fidelity value. This (default) method simply returns the last timeslot

recompute_evolution ()

Recalculates the evolution operators. Dynamics generators (e.g. Hamiltonian) and prop (propagators) are calculated as necessary

class PulseGen (*dyn=None, params=None*)

Pulse generator Base class for all Pulse generators The object can optionally be instantiated with a Dynamics object, in which case the timeslots and amplitude scaling and offset are copied from that. Otherwise the class can be used independently by setting: tau (array of timeslot durations) or num_tsots and pulse_time for equally spaced timeslots

Attributes

num_tsots [integer] Number of timeslots, aka timeslices (copied from Dynamics if given)

pulse_time [float] total duration of the pulse (copied from Dynamics.evo_time if given)

scaling [float] linear scaling applied to the pulse (copied from Dynamics.initial_ctrl_scaling if given)

offset [float] linear offset applied to the pulse (copied from Dynamics.initial_ctrl_offset if given)

tau [array[num_tsots] of float] Duration of each timeslot (copied from Dynamics if given)

lbound [float] Lower boundary for the pulse amplitudes Note that the scaling and offset attributes can be used to fully bound the pulse for all generators except some of the random ones This bound (if set) may result in additional shifting / scaling Default is -Inf

ubound [float] Upper boundary for the pulse amplitudes Note that the scaling and offset attributes can be used to fully bound the pulse for all generators except some of the random ones This bound (if set) may result in additional shifting / scaling Default is Inf

periodic [boolean] True if the pulse generator produces periodic pulses

random [boolean] True if the pulse generator produces random pulses

log_level [integer] level of messaging output from the logger. Options are attributes of qutip.logging_utils, in decreasing levels of messaging, are: DEBUG_INTENSE, DEBUG_VERBOSE, DEBUG, INFO, WARN, ERROR, CRITICAL Anything WARN or above is effectively 'quiet' execution, assuming everything runs as expected. The default NOTSET implies that the level will be taken from the QuTiP settings file, which by default is WARN

apply_params (*params=None*)

Set object attributes based on the dictionary (if any) passed in the instantiation, or passed as a parameter This is called during the instantiation automatically. The key value pairs are the attribute name and value

```

gen_pulse ()
    returns the pulse as an array of vales for each timeslot Must be implemented by subclass

init_pulse ()
    Initialise the pulse parameters

reset ()
    reset attributes to default values

class PulseGenRandom (dyn=None, params=None)
    Generates random pulses as simply random values for each timeslot

gen_pulse ()
    Generate a pulse of random values between 1 and -1 Values are scaled using the scaling property and
    shifted using the offset property Returns the pulse as an array of vales for each timeslot

reset ()
    reset attributes to default values

class PulseGenZero (dyn=None, params=None)
    Generates a flat pulse

gen_pulse ()
    Generate a pulse with the same value in every timeslot. The value will be zero, unless the offset is not
    zero, in which case it will be the offset

class PulseGenLinear (dyn=None, params=None)
    Generates linear pulses

    Attributes

        gradient [float] Gradient of the line. Note this is calculated from the start_val and end_val
        if these are given

        start_val [float] Start point of the line. That is the starting amplitude

        end_val [float] End point of the line. That is the amplitude at the start of the last timeslot

gen_pulse (gradient=None, start_val=None, end_val=None)
    Generate a linear pulse using either the gradient and start value or using the end point to calculate the
    gradient Note that the scaling and offset parameters are still applied, so unless these values are the
    default 1.0 and 0.0, then the actual gradient etc will be different Returns the pulse as an array of vales
    for each timeslot

init_pulse (gradient=None, start_val=None, end_val=None)
    Calculate the gradient if pulse is defined by start and end point values

reset ()
    reset attributes to default values

class PulseGenPeriodic (dyn=None, params=None)
    Intermediate class for all periodic pulse generators All of the periodic pulses range from -1 to 1 All have a
    start phase that can be set between 0 and 2pi

    Attributes

        num_waves [float] Number of complete waves (cycles) that occur in the pulse. wavelen
        and freq calculated from this if it is given

        wavelen [float] Wavelength of the pulse (assuming the speed is 1) freq is calculated from
        this if it is given

        freq [float] Frequency of the pulse

        start_phase [float] Phase of the pulse signal when t=0

init_pulse (num_waves=None, wavelen=None, freq=None, start_phase=None)
    Calculate the wavelength, frequency, number of waves etc from the each other and the other parameters

```

If `num_waves` is given then the other parameters are worked from this Otherwise if the wavelength is given then it is the driver Otherwise the frequency is used to calculate wavelength and `num_waves`

reset ()
reset attributes to default values

class PulseGenSine (*dyn=None, params=None*)
Generates sine wave pulses

gen_pulse (*num_waves=None, wavelen=None, freq=None, start_phase=None*)
Generate a sine wave pulse If no params are provided then the class object attributes are used. If they are provided, then these will reinitialise the object attribs. returns the pulse as an array of vales for each timeslot

class PulseGenSquare (*dyn=None, params=None*)
Generates square wave pulses

gen_pulse (*num_waves=None, wavelen=None, freq=None, start_phase=None*)
Generate a square wave pulse If no parameters are pavided then the class object attributes are used. If they are provided, then these will reinitialise the object attribs

class PulseGenSaw (*dyn=None, params=None*)
Generates saw tooth wave pulses

gen_pulse (*num_waves=None, wavelen=None, freq=None, start_phase=None*)
Generate a saw tooth wave pulse If no parameters are pavided then the class object attributes are used. If they are provided, then these will reinitialise the object attribs

class PulseGenTriangle (*dyn=None, params=None*)
Generates triangular wave pulses

gen_pulse (*num_waves=None, wavelen=None, freq=None, start_phase=None*)
Generate a sine wave pulse If no parameters are pavided then the class object attributes are used. If they are provided, then these will reinitialise the object attribs

class PulseGenGaussian (*dyn=None, params=None*)
Generates pulses with a Gaussian profile

gen_pulse (*mean=None, variance=None*)
Generate a pulse with Gaussian shape. The peak is centre around the mean and the variance determines the breadth The scaling and offset attributes are applied as an amplitude and fixed linear offset. Note that the maximum amplitude will be scaling + offset.

reset ()
reset attributes to default values

class PulseGenGaussianEdge (*dyn=None, params=None*)

Generate pulses with inverted Gaussian ramping in and out It's intended use for a ramping modulation, which is often required in experimental setups.

Attributes

decay_time [float] Determines the ramping rate. It is approximately the time required to bring the pulse to full amplitude It is set to 1/10 of the pulse time by default

gen_pulse (*decay_time=None*)
Generate a pulse that starts and ends at zero and 1.0 in between then apply scaling and offset The tailing in and out is an inverted Gaussian shape

reset ()
reset attributes to default values

class PulseGenCrab (*dyn=None, num_coeffs=None, params=None*)

Base class for all CRAB pulse generators Note these are more involved in the optimisation process as they are used to produce piecewise control amplitudes each time new optimisation parameters are tried

Attributes

num_coeffs [integer] Number of coefficients used for each basis function

num_basis_funcs [integer] Number of basis functions In this case set at 2 and should not be changed

coeffs [float array[num_coeffs, num_basis_funcs]] The basis coefficient values

randomize_coeffs [bool] If True (default) then the coefficients are set to some random values when initialised, otherwise they will all be equal to self.scaling

estimate_num_coeffs (*dim*)

Estimate the number coefficients based on the dimensionality of the system. :returns: **num_coeffs** – estimated number of coefficients :rtype: int

get_optim_var_vals ()

Get the parameter values to be optimised :returns: :rtype: list (or 1d array) of floats

init_coeffs (*num_coeffs=None*)

Generate the initial coefficient values.

Parameters

num_coeffs [integer] Number of coefficients used for each basis function If given this overrides the default and sets the attribute of the same name.

init_pulse (*num_coeffs=None*)

Set the initial freq and coefficient values

reset ()

reset attributes to default values

set_optim_var_vals (*param_vals*)

Set the values of the any of the pulse generation parameters based on new values from the optimisation method Typically this will be the basis coefficients

class PulseGenCrabFourier (*dyn=None, num_coeffs=None, params=None*)

Generates a pulse using the Fourier basis functions, i.e. sin and cos

Attributes

freqs [float array[num_coeffs]] Frequencies for the basis functions

randomize_freqs [bool] If True (default) the some random offset is applied to the frequencies

gen_pulse (*coeffs=None*)

Generate a pulse using the Fourier basis with the freqs and coeffs attributes.

Parameters

coeffs [float array[num_coeffs, num_basis_funcs]] The basis coefficient values If given this overrides the default and sets the attribute of the same name.

init_freqs ()

Generate the frequencies These are the Fourier harmonics with a uniformly distributed random offset

init_pulse (*num_coeffs=None*)

Set the initial freq and coefficient values

reset ()

reset attributes to default values

class Stats

Base class for all optimisation statistics Used for configurations where all timeslots are updated each iteration e.g. exact gradients Note that all times are generated using `timeit.default_timer()` and are in seconds

Attributes

dyn_gen_name [string] Text used in some report functions. Makes sense to set it to ‘Hamiltonian’ when using unitary dynamics Default is simply ‘dynamics generator’

num_iter [integer] Number of iterations of the optimisation algorithm

wall_time_optim_start [float] Start time for the optimisation

wall_time_optim_end [float] End time for the optimisation

wall_time_optim [float] Time elapsed during the optimisation

wall_time_dyn_gen_compute [float] Total wall (elapsed) time computing combined dynamics generator (for example combining drift and control Hamiltonians)

wall_time_prop_compute [float] Total wall (elapsed) time computing propagators, that is the time evolution from one timeslot to the next Includes calculating the propagator gradient for exact gradients

wall_time_fwd_prop_compute [float] Total wall (elapsed) time computing combined forward propagation, that is the time evolution from the start to a specific timeslot. Excludes calculating the propagators themselves

wall_time_onwd_prop_compute [float] Total wall (elapsed) time computing combined onward propagation, that is the time evolution from a specific timeslot to the end time. Excludes calculating the propagators themselves

wall_time_gradient_compute [float] Total wall (elapsed) time computing the fidelity error gradient. Excludes calculating the propagator gradients (in exact gradient methods)

num_fidelity_func_calls [integer] Number of calls to fidelity function by the optimisation algorithm

num_grad_func_calls [integer] Number of calls to gradient function by the optimisation algorithm

num_tslot_recompute [integer] Number of time the timeslot evolution is recomputed (It is only computed if any amplitudes changed since the last call)

num_fidelity_computes [integer] Number of time the fidelity is computed (It is only computed if any amplitudes changed since the last call)

num_grad_computes [integer] Number of time the gradient is computed (It is only computed if any amplitudes changed since the last call)

num_ctrl_amp_updates [integer] Number of times the control amplitudes are updated

mean_num_ctrl_amp_updates_per_iter [float] Mean number of control amplitude updates per iteration

num_timeslot_changes [integer] Number of times the amplitudes of a any control in a timeslot changes

mean_num_timeslot_changes_per_update [float] Mean average number of timeslot amplitudes that are changed per update

num_ctrl_amp_changes [integer] Number of times individual control amplitudes that are changed

mean_num_ctrl_amp_changes_per_update [float] Mean average number of control amplitudes that are changed per update

calculate()

Perform the calculations (e.g. averages) that are required on the stats Should be called before calling report

report()

Print a report of the stats to the console

class Dump

A container for dump items. The lists for dump items is depends on the type Note: abstract class

Attributes

parent [some control object (Dynamics or Optimizer)] aka the host. Object that generates the data that is dumped and is host to this dump object.

dump_dir [str] directory where files (if any) will be written out the path and be relative or absolute use ~/ to specify user home directory Note: files are only written when write_to_file is True or writeout is called explicitly Defaults to ~/.qtrl_dump

level [string] The level of data dumping that will occur.

write_to_file [bool] When set True data and summaries (as configured) will be written interactively to file during the processing Set during instantiation by the host based on its dump_to_file attrib

dump_file_ext [str] Default file extension for any file names that are auto generated

fname_base [str] First part of any auto generated file names. This is usually overridden in the subclass

dump_summary [bool] If True a summary is recorded each time a new item is added to the the dump. Default is True

summary_sep [str] delimiter for the summary file. default is a space

data_sep [str] delimiter for the data files (arrays saved to file). default is a space

summary_file [str] File path for summary file. Automatically generated. Can be set specifically

create_dump_dir()

Checks dump directory exists, creates it if not

property level

The level of data dumping that will occur.

SUMMARY A summary will be recorded

FULL All possible dumping

CUSTOM Some customised level of dumping

When first set to CUSTOM this is equivalent to SUMMARY. It is then up to the user to specify what specifically is dumped

class OptimDump (optim, level='SUMMARY')

A container for dumps of optimisation data generated during the pulse optimisation.

Attributes

dump_summary [bool] When True summary items are appended to the iter_summary

iter_summary [list of [qutip.control.optimizer.OptimIterSummary](#)] Summary at each iteration

dump_fid_err [bool] When True values are appended to the fid_err_log

fid_err_log [list of float] Fidelity error at each call of the fid_err_func

dump_grad_norm [bool] When True values are appended to the fid_err_log

grad_norm_log [list of float] Gradient norm at each call of the grad_norm_log

dump_grad [bool] When True values are appended to the grad_log

grad_log [list of ndarray] Gradients at each call of the fid_grad_func

add_iter_summary()

add copy of current optimizer iteration summary

property dump_all

True if everything (ignoring the summary) is to be dumped

property dump_any
 True if anything other than the summary is to be dumped

update_fid_err_log (*fid_err*)
 add an entry to the fid_err log

update_grad_log (*grad*)
 add an entry to the grad log

update_grad_norm_log (*grad_norm*)
 add an entry to the grad_norm log

writeout (*f=None*)
 write all the logs and the summary out to file(s)

Parameters

f [filename or filehandle] If specified then all summary and object data will go in one file. If None is specified then type specific files will be generated in the dump_dir. If a filehandle is specified then it must be a byte mode file as numpy.savetxt is used, and requires this.

class DynamicsDump (*dynamics, level='SUMMARY'*)
 A container for dumps of dynamics data. Mainly time evolution calculations.

Attributes

dump_summary [bool] If True a summary is recorded

evo_summary [list of `tslotcomp.EvoCompSummary`] Summary items are appended if dump_summary is True at each recomputation of the evolution.

dump_amps [bool] If True control amplitudes are dumped

dump_dyn_gen [bool] If True the dynamics generators (Hamiltonians) are dumped

dump_prop [bool] If True propagators are dumped

dump_prop_grad [bool] If True propagator gradients are dumped

dump_fwd_evo [bool] If True forward evolution operators are dumped

dump_onwd_evo [bool] If True onward evolution operators are dumped

dump_onto_evo [bool] If True onto (or backward) evolution operators are dumped

evo_dumps [list of `EvoCompDumpItem`] A new dump item is appended at each recomputation of the evolution. That is if any of the calculation objects are to be dumped.

add_evo_comp_summary (*dump_item_idx=None*)
 add copy of current evo comp summary

add_evo_dump ()
 Add dump of current time evolution generating objects

property dump_all
 True if all of the calculation objects are to be dumped

property dump_any
 True if any of the calculation objects are to be dumped

writeout (*f=None*)
 Write all the dump items and the summary out to file(s).

Parameters

f [filename or filehandle] If specified then all summary and object data will go in one file. If None is specified then type specific files will be generated in the dump_dir. If a filehandle is specified then it must be a byte mode file as numpy.savetxt is used, and requires this.

class DumpItem

An item in a dump list

class EvoCompDumpItem (*dump*)

A copy of all objects generated to calculate one time evolution. Note the attributes are only set if the corresponding *DynamicsDump* `dump_*` attribute is set.

writeout (*f=None*)

write all the objects out to files

Parameters

f [filename or filehandle] If specified then all object data will go in one file. If None is specified then type specific files will be generated in the `dump_dir`. If a filehandle is specified then it must be a byte mode file as `numpy.savetxt` is used, and requires this.

class DumpSummaryItem

A summary of the most recent iteration. Abstract class only.

Attributes

idx [int] Index in the summary list in which this is stored

5.2 Functions

5.2.1 Manipulation and Creation of States and Operators

Quantum States

basis (*dimensions, n=None, offset=None, *, dtype=<class 'qutip.core.data.dense.Dense'>*)

Generates the vector representation of a Fock state.

Parameters

dimensions [int or list of ints] Number of Fock states in Hilbert space. If a list, then the resultant object will be a tensor product over spaces with those dimensions.

n [int or list of ints, optional (default 0 for all dimensions)] Integer corresponding to desired number state, defaults to 0 for all dimensions if omitted. The shape must match `dimensions`, e.g. if `dimensions` is a list, then `n` must either be omitted or a list of equal length.

offset [int or list of ints, optional (default 0 for all dimensions)] The lowest number state that is included in the finite number state representation of the state in the relevant dimension.

dtype [type or str] storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

state [`qutip.Qobj`] `Qobj` representing the requested number state $|n\rangle$.

Notes

A subtle incompatibility with the quantum optics toolbox: In QuTiP:

```
basis(N, 0) = ground state
```

but in the qotoolbox:

```
basis(N, 1) = ground state
```

Examples

```
>>> basis(5,2)
Quantum object: dims = [[5], [1]], shape = (5, 1), type = ket
Qobj data =
[[ 0.+0.j]
 [ 0.+0.j]
 [ 1.+0.j]
 [ 0.+0.j]
 [ 0.+0.j]]
>>> basis([2,2,2], [0,1,0])
Quantum object: dims = [[2, 2, 2], [1, 1, 1]], shape = (8, 1), type = ket
Qobj data =
[[0.]
 [0.]
 [1.]
 [0.]
 [0.]
 [0.]
 [0.]
 [0.]]
```

bell_state (*state*='00', *, *dtype*=<class 'qutip.core.data.dense.Dense'>)

Returns the selected Bell state:

$$|B_{00}\rangle = \frac{1}{\sqrt{2}}(|00\rangle + |11\rangle)$$

$$|B_{01}\rangle = \frac{1}{\sqrt{2}}(|00\rangle - |11\rangle)$$

$$|B_{10}\rangle = \frac{1}{\sqrt{2}}(|01\rangle + |10\rangle)$$

$$|B_{11}\rangle = \frac{1}{\sqrt{2}}(|01\rangle - |10\rangle)$$

Parameters

state [str ['00', '01', '10', '11']] Which bell state to return

dtype [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

Bell_state [qobj] Bell state

bra (*seq*, *dim*=2, *, *dtype*=<class 'qutip.core.data.dense.Dense'>)

Produces a multiparticle bra state for a list or string, where each element stands for state of the respective particle.

Parameters

seq [str / list of ints or characters] Each element defines state of the respective particle. (e.g. [1,1,0,1] or a string "1101"). For qubits it is also possible to use the following conventions:

- 'g'/'e' (ground and excited state)
- 'u'/'d' (spin up and down)
- 'H'/'V' (horizontal and vertical polarization)

Note: for dimension > 9 you need to use a list.

dim [int (default: 2) / list of ints] Space dimension for each particle: int if there are the same, list if they are different.

dtype [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

bra [qobj]

Examples

```
>>> bra("10")
Quantum object: dims = [[1, 1], [2, 2]], shape = [1, 4], type = bra
Qobj data =
[[ 0.  0.  1.  0.]]
```

```
>>> bra("Hue")
Quantum object: dims = [[1, 1, 1], [2, 2, 2]], shape = [1, 8], type = bra
Qobj data =
[[ 0.  1.  0.  0.  0.  0.  0.  0.]]
```

```
>>> bra("12", 3)
Quantum object: dims = [[1, 1], [3, 3]], shape = [1, 9], type = bra
Qobj data =
[[ 0.  0.  0.  0.  0.  1.  0.  0.  0.]]
```

```
>>> bra("31", [5, 2])
Quantum object: dims = [[1, 1], [5, 2]], shape = [1, 10], type = bra
Qobj data =
[[ 0.  0.  0.  0.  0.  0.  0.  1.  0.  0.]]
```

coherent (*N*, *alpha*, *offset*=0, *method*=None, *, *dtype*=<class 'qutip.core.data.dense.Dense'>)

Generates a coherent state with eigenvalue *alpha*.

Constructed using displacement operator on vacuum state.

Parameters

N [int] Number of Fock states in Hilbert space.

alpha [float/complex] Eigenvalue of coherent state.

offset [int (default 0)] The lowest number state that is included in the finite number state representation of the state. Using a non-zero offset will make the default method 'analytic'.

method [string {'operator', 'analytic'}] Method for generating coherent state.

dtype [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

state [qobj] Qobj quantum object for coherent state

Notes

Select method ‘operator’ (default) or ‘analytic’. With the ‘operator’ method, the coherent state is generated by displacing the vacuum state using the displacement operator defined in the truncated Hilbert space of size ‘N’. This method guarantees that the resulting state is normalized. With ‘analytic’ method the coherent state is generated using the analytical formula for the coherent state coefficients in the Fock basis. This method does not guarantee that the state is normalized if truncated to a small number of Fock states, but would in that case give more accurate coefficients.

Examples

```
>>> coherent(5, 0.25j)
Quantum object: dims = [[5], [1]], shape = [5, 1], type = ket
Qobj data =
[[ 9.69233235e-01+0.j          ]
 [ 0.00000000e+00+0.24230831j]
 [-4.28344935e-02+0.j          ]
 [ 0.00000000e+00-0.00618204j]
 [ 7.80904967e-04+0.j          ]]
```

coherent_dm (*N*, *alpha*, *offset*=0, *method*='operator', *, *dtype*=<class 'qutip.core.data.dense.Dense'>)
Density matrix representation of a coherent state.

Constructed via outer product of `qutip.states.coherent`

Parameters

N [int] Number of Fock states in Hilbert space.

alpha [float/complex] Eigenvalue for coherent state.

offset [int (default 0)] The lowest number state that is included in the finite number state representation of the state.

method [string {'operator', 'analytic'}] Method for generating coherent density matrix.

dtype [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

dm [qobj] Density matrix representation of coherent state.

Notes

Select method ‘operator’ (default) or ‘analytic’. With the ‘operator’ method, the coherent density matrix is generated by displacing the vacuum state using the displacement operator defined in the truncated Hilbert space of size ‘N’. This method guarantees that the resulting density matrix is normalized. With ‘analytic’ method the coherent density matrix is generated using the analytical formula for the coherent state coefficients in the Fock basis. This method does not guarantee that the state is normalized if truncated to a small number of Fock states, but would in that case give more accurate coefficients.

Examples

```
>>> coherent_dm(3,0.25j)
Quantum object: dims = [[3], [3]], shape = [3, 3], type = oper, isHerm = True
Qobj data =
[[ 0.93941695+0.j          0.00000000-0.23480733j -0.04216943+0.j          ]
 [ 0.00000000+0.23480733j  0.05869011+0.j          0.00000000-0.01054025j]
 [-0.04216943+0.j          0.00000000+0.01054025j  0.00189294+0.j          ]]
```

enr_fock (*dims*, *excitations*, *state*, *, *dtype*=<class 'qutip.core.data.dense.Dense'>)

Generate the Fock state representation in a excitation-number restricted state space. The *dims* argument is a list of integers that define the number of quantum states of each component of a composite quantum system, and the *excitations* specifies the maximum number of excitations for the basis states that are to be included in the state space. The *state* argument is a tuple of integers that specifies the state (in the number basis representation) for which to generate the Fock state representation.

Parameters

- dims** [list] A list of the dimensions of each subsystem of a composite quantum system.
- excitations** [integer] The maximum number of excitations that are to be included in the state space.
- state** [list of integers] The state in the number basis representation.
- dtype** [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

- ket** [Qobj] A Qobj instance that represent a Fock state in the excitation-number- restricted state space defined by *dims* and *excitations*.

enr_state_dictionaries (*dims*, *excitations*)

Return the number of states, and lookup-dictionaries for translating a state tuple to a state index, and vice versa, for a system with a given number of components and maximum number of excitations.

Parameters

- dims: list** A list with the number of states in each sub-system.
- excitations** [integer] The maximum numbers of dimension

Returns

- nstates, state2idx, idx2state: integer, dict, list** The number of states *nstates*, a dictionary for looking up state indices from a state tuple, and a list containing the state tuples ordered by state indices. *state2idx* and *idx2state* are reverses of each other, i.e., *state2idx[idx2state[idx]] = idx* and *idx2state[state2idx[state]] = state*.

enr_thermal_dm (*dims*, *excitations*, *n*, *, *dtype*=<class 'qutip.core.data.csr.CSR'>)

Generate the density operator for a thermal state in the excitation-number- restricted state space defined by the *dims* and *excitations* arguments. See the documentation for *enr_fock* for a more detailed description of these arguments. The temperature of each mode in *dims* is specified by the average number of excitations *n*.

Parameters

- dims** [list] A list of the dimensions of each subsystem of a composite quantum system.
- excitations** [integer] The maximum number of excitations that are to be included in the state space.
- n** [integer] The average number of excitations in the thermal state. *n* can be a float (which then applies to each mode), or a list/array of the same length as *dims*, in which each element corresponds specifies the temperature of the corresponding mode.
- dtype** [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

dm [Qobj] Thermal state density matrix.

fock (*dimensions*, *n=None*, *offset=None*, *, *dtype=<class 'qutip.core.data.dense.Dense'>*)
Bosonic Fock (number) state.

Same as `qutip.states.basis`.

Parameters

dimensions [int or list of ints] Number of Fock states in Hilbert space. If a list, then the resultant object will be a tensor product over spaces with those dimensions.

n [int or list of ints, optional (default 0 for all dimensions)] Integer corresponding to desired number state, defaults to 0 for all dimensions if omitted. The shape must match *dimensions*, e.g. if *dimensions* is a list, then *n* must either be omitted or a list of equal length.

offset [int or list of ints, optional (default 0 for all dimensions)] The lowest number state that is included in the finite number state representation of the state in the relevant dimension.

dtype [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

Requested number state $|n\rangle$.

Examples

```
>>> fock(4,3)
Quantum object: dims = [[4], [1]], shape = [4, 1], type = ket
Qobj data =
[[ 0.+0.j]
 [ 0.+0.j]
 [ 0.+0.j]
 [ 1.+0.j]]
```

fock_dm (*dimensions*, *n=None*, *offset=None*, *, *dtype=<class 'qutip.core.data.csr.CSR'>*)
Density matrix representation of a Fock state

Constructed via outer product of `qutip.states.fock`.

Parameters

dimensions [int or list of ints] Number of Fock states in Hilbert space. If a list, then the resultant object will be a tensor product over spaces with those dimensions.

n [int or list of ints, optional (default 0 for all dimensions)] Integer corresponding to desired number state, defaults to 0 for all dimensions if omitted. The shape must match *dimensions*, e.g. if *dimensions* is a list, then *n* must either be omitted or a list of equal length.

offset [int or list of ints, optional (default 0 for all dimensions)] The lowest number state that is included in the finite number state representation of the state in the relevant dimension.

dtype [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

dm [qobj] Density matrix representation of Fock state.

Examples

```
>>> fock_dm(3,1)
Quantum object: dims = [[3], [3]], shape = [3, 3], type = oper, isHerm = True
Qobj data =
[[ 0.+0.j  0.+0.j  0.+0.j]
 [ 0.+0.j  1.+0.j  0.+0.j]
 [ 0.+0.j  0.+0.j  0.+0.j]]
```

ghz_state ($N=3$, *, $dtype=<class\ 'qutip.core.data.dense.Dense'>$)

Returns the N-qubit GHZ-state: $[|00\dots00\rangle + |11\dots11\rangle] / \sqrt{2}$

Parameters

N [int (default=3)] Number of qubits in state

dtype [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

G [qobj] N-qubit GHZ-state

ket (seq , $dim=2$, *, $dtype=<class\ 'qutip.core.data.dense.Dense'>$)

Produces a multiparticle ket state for a list or string, where each element stands for state of the respective particle.

Parameters

seq [str / list of ints or characters] Each element defines state of the respective particle. (e.g. [1,1,0,1] or a string "1101"). For qubits it is also possible to use the following conventions: - 'g'/'e' (ground and excited state) - 'u'/'d' (spin up and down) - 'H'/'V' (horizontal and vertical polarization) Note: for dimension > 9 you need to use a list.

dim [int (default: 2) / list of ints] Space dimension for each particle: int if there are the same, list if they are different.

dtype [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

ket [qobj]

Examples

```
>>> ket("10")
Quantum object: dims = [[2, 2], [1, 1]], shape = [4, 1], type = ket
Qobj data =
[[ 0.]
 [ 0.]
 [ 1.]
 [ 0.]]
```

```
>>> ket("Hue")
Quantum object: dims = [[2, 2, 2], [1, 1, 1]], shape = [8, 1], type = ket
Qobj data =
[[ 0.]
 [ 1.]
 [ 0.]
 [ 0.]
 [ 0.]
 [ 0.]
 [ 0.]
 [ 0.]]
```

(continues on next page)

(continued from previous page)

```
[ 0.]
[ 0.]
[ 0.]]
```

```
>>> ket("12", 3)
Quantum object: dims = [[3, 3], [1, 1]], shape = [9, 1], type = ket
Qobj data =
[[ 0.]
 [ 0.]
 [ 0.]
 [ 0.]
 [ 0.]
 [ 1.]
 [ 0.]
 [ 0.]
 [ 0.]]
```

```
>>> ket("31", [5, 2])
Quantum object: dims = [[5, 2], [1, 1]], shape = [10, 1], type = ket
Qobj data =
[[ 0.]
 [ 0.]
 [ 0.]
 [ 0.]
 [ 0.]
 [ 0.]
 [ 0.]
 [ 0.]
 [ 1.]
 [ 0.]
 [ 0.]]
```

ket2dm(*Q*)

Takes input ket or bra vector and returns density matrix formed by outer product. This is completely identical to calling *Q.proj()*.

Parameters

Q [qobj] Ket or bra type quantum object.

Returns

dm [qobj] Density matrix formed by outer product of *Q*.

Examples

```
>>> x=basis(3,2)
>>> ket2dm(x)
Quantum object: dims = [[3], [3]], shape = [3, 3], type = oper, isHerm = True
Qobj data =
[[ 0.+0.j  0.+0.j  0.+0.j]
 [ 0.+0.j  0.+0.j  0.+0.j]
 [ 0.+0.j  0.+0.j  1.+0.j]]
```

maximally_mixed_dm(*N*, *, dtype=<class 'qutip.core.data.csr.CSR'>)

Returns the maximally mixed density matrix for a Hilbert space of dimension *N*.

Parameters

N [int] Number of basis states in Hilbert space.

dtype [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

dm [qobj] Thermal state density matrix.

phase_basis (*N, m, phi0=0, *, dtype=<class 'qutip.core.data.dense.Dense'>*)

Basis vector for the *m*th phase of the Pegg-Barnett phase operator.

Parameters

N [int] Number of basis vectors in Hilbert space.

m [int] Integer corresponding to the *m*th discrete phase $\phi_m = \phi_0 + 2 * \pi * m / N$

phi0 [float (default=0)] Reference phase angle.

dtype [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

state [qobj] Ket vector for *m*th Pegg-Barnett phase operator basis state.

Notes

The Pegg-Barnett basis states form a complete set over the truncated Hilbert space.

projection (*N, n, m, offset=None, *, dtype=<class 'qutip.core.data.csr.CSR'>*)

The projection operator that projects state $|m\rangle$ on state $|n\rangle$.

Parameters

N [int] Number of basis states in Hilbert space.

n, m [float] The number states in the projection.

offset [int (default 0)] The lowest number state that is included in the finite number state representation of the projector.

dtype [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

oper [qobj] Requested projection operator.

qutrit_basis (*, dtype=<class 'qutip.core.data.dense.Dense'>)

Basis states for a three level system (qutrit)

dtype [type or str] storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

qstates [array] Array of qutrit basis vectors

singlet_state (*, dtype=<class 'qutip.core.data.dense.Dense'>)

Returns the two particle singlet-state:

$$|S\rangle = \frac{1}{\sqrt{2}}(|01\rangle - |10\rangle)$$

that is identical to the fourth bell state.

Parameters

dtype [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

Bell_state [qobj] $|B_{11}\rangle$ Bell state

spin_coherent (*j, theta, phi, type='ket', *, dtype=<class 'qutip.core.data.dense.Dense'>*)
Generate the coherent spin state $|\theta, \phi\rangle$.

Parameters

- j** [float] The spin of the state.
- theta** [float] Angle from z axis.
- phi** [float] Angle from x axis.
- type** [string {'ket', 'bra', 'dm'}] Type of state to generate.
- dtype** [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

state [qobj] Qobj quantum object for spin coherent state

spin_state (*j, m, type='ket', *, dtype=<class 'qutip.core.data.dense.Dense'>*)
Generates the spin state $|j, m\rangle$, i.e. the eigenstate of the spin-j Sz operator with eigenvalue m.

Parameters

- j** [float] The spin of the state ().
- m** [int] Eigenvalue of the spin-j Sz operator.
- type** [string {'ket', 'bra', 'dm'}] Type of state to generate.
- dtype** [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

state [qobj] Qobj quantum object for spin state

state_index_number (*dims, index*)
Return a quantum number representation given a state index, for a system of composite structure defined by dims.

Example

```
>>> state_index_number([2, 2, 2], 6)
[1, 1, 0]
```

Parameters

- dims** [list or array] The quantum state dimensions array, as it would appear in a Qobj.
- index** [integer] The index of the state in standard enumeration ordering.

Returns

state [tuple] The state number tuple corresponding to index *index* in standard enumeration ordering.

state_number_enumerate (*dims, excitations=None*)
An iterator that enumerates all the state number tuples (quantum numbers of the form (n1, n2, n3, ...)) for a system with dimensions given by dims.

Example

```
>>> for state in state_number_enumerate([2,2]):
>>>     print(state)
( 0  0 )
( 0  1 )
( 1  0 )
( 1  1 )
```

Parameters

dims [list or array] The quantum state dimensions array, as it would appear in a Qobj.

excitations [integer (None)] Restrict state space to states with excitation numbers below or equal to this value.

Returns

state_number [tuple] Successive state number tuples that can be used in loops and other iterations, using standard state enumeration *by definition*.

state_number_index (*dims, state*)

Return the index of a quantum state corresponding to state, given a system with dimensions given by dims.

Example

```
>>> state_number_index([2, 2, 2], [1, 1, 0])
6
```

Parameters

dims [list or array] The quantum state dimensions array, as it would appear in a Qobj.

state [list] State number array.

Returns

idx [int] The index of the state given by *state* in standard enumeration ordering.

state_number_qobj (*dims, state, *, dtype=<class 'qutip.core.data.dense.Dense'>*)

Return a Qobj representation of a quantum state specified by the state array *state*.

Example

```
>>> state_number_qobj([2, 2, 2], [1, 0, 1])
Quantum object: dims = [[2, 2, 2], [1, 1, 1]], shape = [8, 1], type = ket
Qobj data =
[[ 0.]
 [ 0.]
 [ 0.]
 [ 0.]
 [ 0.]
 [ 1.]
 [ 0.]
 [ 0.]]
```

Parameters

dims [list or array] The quantum state dimensions array, as it would appear in a Qobj.

state [list] State number array.

dtype [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

state [*qutip.Qobj*] The state as a *qutip.Qobj* instance.

Note: Deprecated in QuTiP 5.0, use *basis* instead.

thermal_dm (*N, n, method='operator', *, dtype=<class 'qutip.core.data.csr.CSR'>*)

Density matrix for a thermal state of *n* particles

Parameters

N [int] Number of basis states in Hilbert space.

n [float] Expectation value for number of particles in thermal state.

method [string {'operator', 'analytic'}] string that sets the method used to generate the thermal state probabilities

dtype [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

dm [qobj] Thermal state density matrix.

Notes

The 'operator' method (default) generates the thermal state using the truncated number operator `num(N)`. This is the method that should be used in computations. The 'analytic' method uses the analytic coefficients derived in an infinite Hilbert space. The analytic form is not necessarily normalized, if truncated too aggressively.

Examples

```
>>> thermal_dm(5, 1)
Quantum object: dims = [[5], [5]], shape = [5, 5], type = oper, isHerm = True
Qobj data =
[[ 0.51612903  0.          0.          0.          0.          ]
 [ 0.          0.25806452  0.          0.          0.          ]
 [ 0.          0.          0.12903226  0.          0.          ]
 [ 0.          0.          0.          0.06451613  0.          ]
 [ 0.          0.          0.          0.          0.03225806]]
```

```
>>> thermal_dm(5, 1, 'analytic')
Quantum object: dims = [[5], [5]], shape = [5, 5], type = oper, isHerm = True
Qobj data =
[[ 0.5       0.         0.         0.         0.        ]
 [ 0.        0.25      0.         0.         0.        ]
 [ 0.        0.        0.125     0.         0.        ]
 [ 0.        0.        0.        0.0625    0.         ]
 [ 0.        0.        0.        0.        0.03125]]
```

triplet_states (*, dtype=<class 'qutip.core.data.dense.Dense'>)

Returns a list of the two particle triplet-states:

$$|T_1\rangle = |11\rangle|T_2\rangle = \frac{1}{\sqrt{2}}(|01\rangle + |10\rangle)|T_3\rangle = |00\rangle$$

Parameters

dtype [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

trip_states [list] 2 particle triplet states

w_state ($N=3$, *, *dtype*=<class 'qutip.core.data.dense.Dense'>)

Returns the N-qubit W-state: $[|100\dots0\rangle + |010\dots0\rangle + |001\dots0\rangle + \dots |000\dots1\rangle] / \sqrt{n}$

Parameters

N [int (default=3)] Number of qubits in state

dtype [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

W [Qobj] N-qubit W-state

zero_ket (N , *dims*=None, *, *dtype*=<class 'qutip.core.data.dense.Dense'>)

Creates the zero ket vector with shape $N \times 1$ and dimensions *dims*.

Parameters

N [int] Hilbert space dimensionality

dims [list] Optional dimensions if ket corresponds to a composite Hilbert space.

dtype [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

zero_ket [qobj] Zero ket on given Hilbert space.

Quantum Operators

This module contains functions for generating Qobj representation of a variety of commonly occurring quantum operators.

charge (N_{\max} , $N_{\min}=None$, *frac*=1, *, *dtype*=<class 'qutip.core.data.csr.CSR'>)

Generate the diagonal charge operator over charge states from N_{\min} to N_{\max} .

Parameters

Nmax [int] Maximum charge state to consider.

Nmin [int (default = -Nmax)] Lowest charge state to consider.

frac [float (default = 1)] Specify fractional charge if needed.

dtype [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

C [Qobj] Charge operator over $[N_{\min}, N_{\max}]$.

Notes

New in version 3.2.

commutator (*A*, *B*, *kind*='normal')

Return the commutator of kind *kind* (normal, anti) of the two operators *A* and *B*.

create (*N*, *offset*=0, *, *dtype*=<class 'qutip.core.data.csr.CSR'>)

Creation (raising) operator.

Parameters

N [int] Dimension of Hilbert space.

offset [int (default 0)] The lowest number state that is included in the finite number state representation of the operator.

dtype [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

oper [qobj] Qobj for raising operator.

offset [int (default 0)] The lowest number state that is included in the finite number state representation of the operator.

Examples

```
>>> create(4)
Quantum object: dims=[[4], [4]], shape=(4, 4), type='oper', isherm=False
Qobj data =
[[ 0.00000000+0.j  0.00000000+0.j  0.00000000+0.j  0.00000000+0.j]
 [ 1.00000000+0.j  0.00000000+0.j  0.00000000+0.j  0.00000000+0.j]
 [ 0.00000000+0.j  1.41421356+0.j  0.00000000+0.j  0.00000000+0.j]
 [ 0.00000000+0.j  0.00000000+0.j  1.73205081+0.j  0.00000000+0.j]]
```

destroy (*N*, *offset*=0, *, *dtype*=<class 'qutip.core.data.csr.CSR'>)

Destruction (lowering) operator.

Parameters

N [int] Dimension of Hilbert space.

offset [int (default 0)] The lowest number state that is included in the finite number state representation of the operator.

dtype [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

oper [qobj] Qobj for lowering operator.

Examples

```
>>> destroy(4)
Quantum object: dims=[[4], [4]], shape=(4, 4), type='oper', isherm=False
Qobj data =
[[ 0.00000000+0.j  1.00000000+0.j  0.00000000+0.j  0.00000000+0.j]
 [ 0.00000000+0.j  0.00000000+0.j  1.41421356+0.j  0.00000000+0.j]
 [ 0.00000000+0.j  0.00000000+0.j  0.00000000+0.j  1.73205081+0.j]
 [ 0.00000000+0.j  0.00000000+0.j  0.00000000+0.j  0.00000000+0.j]]
```

displace (*N*, *alpha*, *offset*=0, *, *dtype*=<class 'qutip.core.data.dense.Dense'>)
Single-mode displacement operator.

Parameters

N [int] Dimension of Hilbert space.

alpha [float/complex] Displacement amplitude.

offset [int (default 0)] The lowest number state that is included in the finite number state representation of the operator.

dtype [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

oper [qobj] Displacement operator.

Examples

```
>>> displace(4, 0.25)
Quantum object: dims = [[4], [4]], shape = [4, 4], type = oper, isHerm = False
Qobj data =
[[ 0.96923323+0.j -0.24230859+0.j  0.04282883+0.j -0.00626025+0.j]
 [ 0.24230859+0.j  0.90866411+0.j -0.33183303+0.j  0.07418172+0.j]
 [ 0.04282883+0.j  0.33183303+0.j  0.84809499+0.j -0.41083747+0.j]
 [ 0.00626025+0.j  0.07418172+0.j  0.41083747+0.j  0.90866411+0.j]]
```

enr_destroy (*dims*, *excitations*, *, *dtype*=<class 'qutip.core.data.csr.CSR'>)

Generate annihilation operators for modes in a excitation-number-restricted state space. For example, consider a system consisting of 4 modes, each with 5 states. The total hilbert space size is $5*4 = 625$. If we are only interested in states that contain up to 2 excitations, we only need to include states such as

(0, 0, 0, 0) (0, 0, 0, 1) (0, 0, 0, 2) (0, 0, 1, 0) (0, 0, 1, 1) (0, 0, 2, 0) ...

This function creates annihilation operators for the 4 modes that act within this state space:

a1, a2, a3, a4 = enr_destroy([5, 5, 5, 5], excitations=2)

From this point onwards, the annihilation operators a1, ..., a4 can be used to setup a Hamiltonian, collapse operators and expectation-value operators, etc., following the usual pattern.

Parameters

dims [list] A list of the dimensions of each subsystem of a composite quantum system.

excitations [integer] The maximum number of excitations that are to be included in the state space.

dtype [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

a_ops [list of qobj] A list of annihilation operators for each mode in the composite quantum system described by *dims*.

enr_identity (*dims*, *excitations*, *, *dtype*=<class 'qutip.core.data.csr.CSR'>)

Generate the identity operator for the excitation-number restricted state space defined by the *dims* and *excitations* arguments. See the docstring for `enr_fock` for a more detailed description of these arguments.

Parameters

dims [list] A list of the dimensions of each subsystem of a composite quantum system.

excitations [integer] The maximum number of excitations that are to be included in the state space.

state [list of integers] The state in the number basis representation.

dtype [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

op [Qobj] A Qobj instance that represent the identity operator in the excitation-number-restricted state space defined by *dims* and *excitations*.

identity (*dimensions*, *, *dtype*=<class 'qutip.core.data.csr.CSR'>)

Identity operator.

Parameters

dimensions [(int) or (list of int) or (list of list of int)] Dimension of Hilbert space. If provided as a list of ints, then the dimension is the product over this list, but the *dims* property of the new Qobj are set to this list. This can produce either *oper* or *super* depending on the passed *dimensions*.

dtype [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

oper [qobj] Identity operator Qobj.

Examples

```
>>> qeye(3)
Quantum object: dims = [[3], [3]], shape = (3, 3), type = oper, isherm = True
Qobj data =
[[ 1.  0.  0.]
 [ 0.  1.  0.]
 [ 0.  0.  1.]]
>>> qeye([2,2])
Quantum object: dims = [[2, 2], [2, 2]], shape = (4, 4), type = oper, isherm = True
Qobj data =
[[1. 0. 0. 0.]
 [0. 1. 0. 0.]
 [0. 0. 1. 0.]
 [0. 0. 0. 1.]]
```

jmat (*j*, *which*=None, *, *dtype*=<class 'qutip.core.data.csr.CSR'>)

Higher-order spin operators:

Parameters

j [float] Spin of operator

which [str] Which operator to return 'x','y','z','+','-'. If no args given, then output is ['x','y','z']

dtype [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

jmat [Qobj or tuple of Qobj] *qobj* for requested spin operator(s).

Notes

If no 'args' input, then returns array of ['x','y','z'] operators.

Examples

```
>>> jmat(1)
[ Quantum object: dims = [[3], [3]], shape = [3, 3], type = oper, isHerm = True
Qobj data =
[[ 0.          0.70710678  0.          ]
 [ 0.70710678  0.          0.70710678]
 [ 0.          0.70710678  0.          ]]
Quantum object: dims = [[3], [3]], shape = [3, 3], type = oper, isHerm = True
Qobj data =
[[ 0.+0.j          0.-0.70710678j  0.+0.j          ]
 [ 0.+0.70710678j  0.+0.j          0.-0.70710678j]
 [ 0.+0.j          0.+0.70710678j  0.+0.j          ]]
Quantum object: dims = [[3], [3]], shape = [3, 3], type = oper, isHerm = True
Qobj data =
[[ 1.  0.  0.]
 [ 0.  0.  0.]
 [ 0.  0. -1.]]]
```

momentum (*N*, *offset*=0, *, *dtype*=<class 'qutip.core.data.csr.CSR'>)

Momentum operator $p = -1j/\sqrt{2}*(a - a.dag())$

Parameters

N [int] Number of Fock states in Hilbert space.

offset [int (default 0)] The lowest number state that is included in the finite number state representation of the operator.

dtype [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

oper [qobj] Momentum operator as Qobj.

num (*N*, *offset*=0, *, *dtype*=<class 'qutip.core.data.csr.CSR'>)

Quantum object for number operator.

Parameters

N [int] The dimension of the Hilbert space.

offset [int (default 0)] The lowest number state that is included in the finite number state representation of the operator.

dtype [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

oper: qobj Qobj for number operator.

Examples

```
>>> num(4)
Quantum object: dims=[[4], [4]], shape=(4, 4), type='oper', isherm=True
Qobj data =
[[0 0 0 0]
 [0 1 0 0]
 [0 0 2 0]
 [0 0 0 3]]
```

phase (*N*, *phi0*=0, *, *dtype*=<class 'qutip.core.data.dense.Dense'>)
Single-mode Pegg-Barnett phase operator.

Parameters

- N** [int] Number of basis states in Hilbert space.
- phi0** [float] Reference phase.
- dtype** [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

- oper** [qobj] Phase operator with respect to reference phase.

Notes

The Pegg-Barnett phase operator is Hermitian on a truncated Hilbert space.

position (*N*, *offset*=0, *, *dtype*=<class 'qutip.core.data.csr.CSR'>)
Position operator $x=1/\sqrt{2}*(a+a.dag())$

Parameters

- N** [int] Number of Fock states in Hilbert space.
- offset** [int (default 0)] The lowest number state that is included in the finite number state representation of the operator.
- dtype** [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

- oper** [qobj] Position operator as Qobj.

qdiags (*diagonals*, *offsets*=None, *dims*=None, *shape*=None, *, *dtype*=<class 'qutip.core.data.csr.CSR'>)
Constructs an operator from an array of diagonals.

Parameters

- diagonals** [sequence of array_like] Array of elements to place along the selected diagonals.
- offsets** [sequence of ints, optional]

Sequence for diagonals to be set:

- *k*=0 main diagonal
- *k*>0 *k*th upper diagonal
- *k*<0 *k*th lower diagonal

dims [list, optional] Dimensions for operator

shape [list, tuple, optional] Shape of operator. If omitted, a square operator large enough to contain the diagonals is generated.

dtype [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Examples

```
>>> qdiags(sqrt(range(1, 4)), 1)
Quantum object: dims = [[4], [4]], shape = [4, 4], type = oper, isherm = False
Qobj data =
[[ 0.          1.          0.          0.          ]
 [ 0.          0.          1.41421356  0.          ]
 [ 0.          0.          0.          1.73205081]
 [ 0.          0.          0.          0.          ]]
```

qeye (*dimensions*, *, *dtype*=<class 'qutip.core.data.csr.CSR'>)

Identity operator.

Parameters

dimensions [(int) or (list of int) or (list of list of int)] Dimension of Hilbert space. If provided as a list of ints, then the dimension is the product over this list, but the *dims* property of the new Qobj are set to this list. This can produce either *oper* or *super* depending on the passed *dimensions*.

dtype [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

oper [qobj] Identity operator Qobj.

Examples

```
>>> qeye(3)
Quantum object: dims = [[3], [3]], shape = (3, 3), type = oper, isherm = True
Qobj data =
[[ 1.  0.  0.]
 [ 0.  1.  0.]
 [ 0.  0.  1.]]
>>> qeye([2,2])
Quantum object: dims = [[2, 2], [2, 2]], shape = (4, 4), type = oper, isherm = True
Qobj data =
[[1. 0. 0. 0.]
 [0. 1. 0. 0.]
 [0. 0. 1. 0.]
 [0. 0. 0. 1.]]
```

qutrit_ops (*, *dtype*=<class 'qutip.core.data.csr.CSR'>)

Operators for a three level system (qutrit).

Parameters

dtype [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

opers: array array of qutrit operators.

qzero (*dimensions*, *, *dtype*=<class 'qutip.core.data.csr.CSR'>)

Zero operator.

Parameters

dimensions [(int) or (list of int) or (list of list of int)] Dimension of Hilbert space. If provided as a list of ints, then the dimension is the product over this list, but the `dims` property of the new `Qobj` are set to this list. This can produce either *oper* or *super* depending on the passed *dimensions*.

dtype [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

qzero [qobj] Zero operator `Qobj`.

sigmam()
Annihilation operator for Pauli spins.

Examples

```
>>> sigmam()
Quantum object: dims = [[2], [2]], shape = [2, 2], type = oper, isHerm = False
Qobj data =
[[ 0.  0.]
 [ 1.  0.]]
```

sigmap()
Creation operator for Pauli spins.

Examples

```
>>> sigmap()
Quantum object: dims = [[2], [2]], shape = [2, 2], type = oper, isHerm = False
Qobj data =
[[ 0.  1.]
 [ 0.  0.]]
```

sigmax()
Pauli spin 1/2 sigma-x operator

Examples

```
>>> sigmax()
Quantum object: dims = [[2], [2]], shape = [2, 2], type = oper, isHerm = False
Qobj data =
[[ 0.  1.]
 [ 1.  0.]]
```

sigmay()
Pauli spin 1/2 sigma-y operator.

Examples

```
>>> sigmay()
Quantum object: dims = [[2], [2]], shape = [2, 2], type = oper, isHerm = True
Qobj data =
[[ 0.+0.j  0.-1.j]
 [ 0.+1.j  0.+0.j]]
```

sigmaz()
Pauli spin 1/2 sigma-z operator.

Examples

```
>>> sigmaz()
Quantum object: dims = [[2], [2]], shape = [2, 2], type = oper, isHerm = True
Qobj data =
[[ 1.  0.]
 [ 0. -1.]]
```

spin_Jm(j, *, dtype=<class 'qutip.core.data.csr.CSR'>)
Spin-j annihilation operator

Parameters

- j** [float] Spin of operator
- dtype** [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

- op** [Qobj] qobj representation of the operator.

spin_Jp(j, *, dtype=<class 'qutip.core.data.csr.CSR'>)
Spin-j creation operator

Parameters

- j** [float] Spin of operator
- dtype** [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

- op** [Qobj] qobj representation of the operator.

spin_Jx(j, *, dtype=<class 'qutip.core.data.csr.CSR'>)
Spin-j x operator

Parameters

- j** [float] Spin of operator
- dtype** [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

- op** [Qobj] qobj representation of the operator.

spin_Jy(j, *, dtype=<class 'qutip.core.data.csr.CSR'>)
Spin-j y operator

Parameters

- j** [float] Spin of operator

dtype [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

op [Qobj] *qobj* representation of the operator.

spin_Jz (*j*, *, *dtype*=<class 'qutip.core.data.csr.CSR'>)
Spin-j z operator

Parameters

j [float] Spin of operator

dtype [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

op [Qobj] *qobj* representation of the operator.

squeeze (*N*, *z*, *offset*=0, *, *dtype*=<class 'qutip.core.data.csr.CSR'>)
Single-mode squeezing operator.

Parameters

N [int] Dimension of hilbert space.

z [float/complex] Squeezing parameter.

offset [int (default 0)] The lowest number state that is included in the finite number state representation of the operator.

dtype [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

oper [qutip.Qobj] Squeezing operator.

Examples

```
>>> squeeze(4, 0.25)
Quantum object: dims = [[4], [4]], shape = [4, 4], type = oper, isHerm = False
Qobj data =
[[ 0.98441565+0.j  0.00000000+0.j  0.17585742+0.j  0.00000000+0.j]
 [ 0.00000000+0.j  0.95349007+0.j  0.00000000+0.j  0.30142443+0.j]
 [-0.17585742+0.j  0.00000000+0.j  0.98441565+0.j  0.00000000+0.j]
 [ 0.00000000+0.j -0.30142443+0.j  0.00000000+0.j  0.95349007+0.j]]
```

squeezing (*a1*, *a2*, *z*)
Generalized squeezing operator.

$$S(z) = \exp\left(\frac{1}{2}\left(z^*a_1a_2 - za_1^\dagger a_2^\dagger\right)\right)$$

Parameters

a1 [qutip.Qobj] Operator 1.

a2 [qutip.Qobj] Operator 2.

z [float/complex] Squeezing parameter.

Returns

oper [qutip.Qobj] Squeezing operator.

tunneling (*N*, *m*=1, *, *dtype*=<class 'qutip.core.data.csr.CSR'>)

Tunneling operator with elements of the form

$$\text{sum}|N\rangle\langle N+m| + |N+m\rangle\langle N|.$$

Parameters

N [int] Number of basis states in Hilbert space.

m [int (default = 1)] Number of excitations in tunneling event.

dtype [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

T [Qobj] Tunneling operator.

Notes

New in version 3.2.

Quantum Objects

The Quantum Object (Qobj) class, for representing quantum states and operators, and related functions.

ptrace (*Q*, *sel*)

Partial trace of the Qobj with selected components remaining.

Parameters

Q [qutip.Qobj] Composite quantum object.

sel [int/list] An int or list of components to keep after partial trace.

Returns

oper [qutip.Qobj] Quantum object representing partial trace with selected components remaining.

Notes

This function is for legacy compatibility only. It is recommended to use the `ptrace()` Qobj method.

Random Operators and States

This module is a collection of random state and operator generators.

rand_dm (*dimensions*, *density*=0.75, *distribution*='ginibre', *, *eigenvalues*=(), *rank*=None, *seed*=None, *dtype*=<class 'qutip.core.data.csr.CSR'>)

Creates a random density matrix of the desired dimensions.

Parameters

dimensions [(int) or (list of int) or (list of list of int)] Dimension of Hilbert space. If provided as a list of ints, then the dimension is the product over this list, but the `dims` property of the new Qobj are set to this list. This can produce either `oper` or `super` depending on the passed `dimensions`.

density [float] Density between [0,1] of output density matrix. Used by the “pure”, “eigen” and “herm”.

distribution [str {“ginibre”, “hs”, “pure”, “eigen”, “uniform”}] Method used to obtain the density matrices.

- “ginibre” : Ginibre random density operator of rank `rank` by using the algorithm of [BCSZ08].
- “hs” : Hilbert-Schmidt ensemble, equivalent to a full rank ginibre operator.
- “pure” : Density matrix created from a random ket.
- “eigen” : A density matrix with the given `eigenvalues`.
- “herm” : Build from a random hermitian matrix using `rand_herm`.

eigenvalues [array_like, optional] Eigenvalues of the output Hermitian matrix. The len must match the shape of the matrix.

rank [int, optional] When using the “ginibre” distribution, rank of the density matrix. Will default to a full rank operator when not provided.

seed [int, SeedSequence, Generator, optional] Seed to create the random number generator or a pre prepared generator. When none is supplied, a default generator is used.

dtype [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

oper [qobj] Density matrix quantum operator.

rand_herm (*dimensions*, *density*=0.3, *distribution*='fill', *, *eigenvalues*=(), *seed*=None, *dtype*=<class 'qutip.core.data.csr.CSR'>)

Creates a random sparse Hermitian quantum object.

Parameters

dimensions [(int) or (list of int) or (list of list of int)] Dimension of Hilbert space. If provided as a list of ints, then the dimension is the product over this list, but the `dims` property of the new Qobj are set to this list. This can produce either *oper* or *super* depending on the passed *dimensions*.

density [float, [0.30]] Density between [0,1] of output Hermitian operator.

distribution [str {"fill", "pos_def", "eigen"}] Method used to obtain the density matrices.

- “fill” : Uses $H = 0.5*(X + X^+)$ where X is a randomly generated quantum operator with elements uniformly distributed between $[-1, 1] + [-1j, 1j]$.
- “eigen” : A density matrix with the given `eigenvalues`. It uses random complex Jacobi rotations to shuffle the operator.
- “pos_def” : Return a positive semi-definite matrix by diagonal dominance.

eigenvalues [array_like, optional] Eigenvalues of the output Hermitian matrix. The len must match the shape of the matrix.

seed [int, SeedSequence, Generator, optional] Seed to create the random number generator or a pre prepared generator. When none is supplied, a default generator is used.

dtype [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

oper [qobj] Hermitian quantum operator.

Notes

If given a list of eigenvalues the object is created using complex Jacobi rotations. While this method is fast for small matrices, it should not be repeatedly used for generating matrices larger than ~1000x1000.

rand_ket (*dimensions*, *density=1*, *distribution='haar'*, *, *seed=None*, *dtype=<class 'qutip.core.data.dense.Dense'>*)

Creates a random ket vector.

Parameters

dimensions [(int) or (list of int) or (list of list of int)] Dimension of Hilbert space. If provided as a list of ints, then the dimension is the product over this list, but the `dims` property of the new Qobj are set to this list. This can produce either *oper* or *super* depending on the passed *dimensions*.

density [float, [1]] Density between [0,1] of output ket state when using the `fill` method.

distribution [str {"haar", "fill"}] Method used to obtain the kets.

- `haar` : Haar random pure state obtained by applying a Haar random unitary to a fixed pure state.
- `fill` : Fill the ket with uniformly distributed random complex number.

seed [int, SeedSequence, Generator, optional] Seed to create the random number generator or a pre prepared generator. When none is supplied, a default generator is used.

dtype [type or str] Storage representation. Any data-layer known to `qutip.data.to` is accepted.

Returns

oper [qobj] Ket quantum state vector.

rand_stochastic (*dimensions*, *density=0.75*, *kind='left'*, *, *seed=None*, *dtype=<class 'qutip.core.data.csr.CSR'>*)

Generates a random stochastic matrix.

Parameters

dimensions [(int) or (list of int) or (list of list of int)] Dimension of Hilbert space. If provided as a list of ints, then the dimension is the product over this list, but the `dims` property of the new Qobj are set to this list. This can produce either *oper* or *super* depending on the passed *dimensions*.

density [float, [0.75]] Density between [0,1] of output density matrix.

kind [str (Default = 'left')] Generate 'left' or 'right' stochastic matrix.

seed [int, SeedSequence, Generator, optional] Seed to create the random number generator or a pre prepared generator. When none is supplied, a default generator is used.

dtype [type or str] Storage representation. Any data-layer known to `qutip.data.to` is accepted.

Returns

oper [qobj] Quantum operator form of stochastic matrix.

rand_super (*dimensions*, *, *superrep='super'*, *seed=None*, *dtype=<class 'qutip.core.data.dense.Dense'>*)

Returns a randomly drawn superoperator acting on operators acting on N dimensions.

Parameters

dimensions [(int) or (list of int) or (list of list of int)] Dimension of Hilbert space. If provided as a list of ints, then the dimension is the product over this list, but the `dims` property of the new Qobj are set to this list. This can produce either *oper* or *super* depending on the passed *dimensions*.

superrop [str, optional, {"super"}] Representation of the super operator

seed [int, SeedSequence, Generator, optional] Seed to create the random number generator or a pre prepared generator. When none is supplied, a default generator is used.

dtype [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

rand_super_bcsz (*dimensions*, *enforce_tp=True*, *rank=None*, *, *superrep='super'*, *seed=None*, *dtype=<class 'qutip.core.data.csr.CSR'>*)

Returns a random superoperator drawn from the Bruzda et al ensemble for CPTP maps [BCSZ08]. Note that due to finite numerical precision, for ranks less than full-rank, zero eigenvalues may become slightly negative, such that the returned operator is not actually completely positive.

Parameters

dimensions [(int) or (list of int) or (list of list of int)] Dimension of Hilbert space. If an int is provided, it is understood as the Square root of the dimension of the superoperator to be returned, with the corresponding dims as $[[[N], [N]], [[N], [N]]]$. If provided as a list of ints, then the dimensions is understood as the space of density matrices this superoperator is applied to: *dimensions*=[2,2] *dims*=[[[2,2], [2,2]], [[2,2], [2,2]]].

enforce_tp [bool] If True, the trace-preserving condition of [BCSZ08] is enforced; otherwise only complete positivity is enforced.

rank [int or None] Rank of the sampled superoperator. If None, a full-rank superoperator is generated.

seed [int, SeedSequence, Generator, optional] Seed to create the random number generator or a pre prepared generator. When none is supplied, a default generator is used.

superrop [str, optional, {"super"}] representation of the

dtype [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

rho [Qobj] A superoperator acting on vectorized $\text{dim} \times \text{dim}$ density operators, sampled from the BCSZ distribution.

rand_unitary (*dimensions*, *density=1*, *distribution='haar'*, *, *seed=None*, *dtype=<class 'qutip.core.data.dense.Dense'>*)

Creates a random sparse unitary quantum object.

Parameters

dimensions [(int) or (list of int) or (list of list of int)] Dimension of Hilbert space. If provided as a list of ints, then the dimension is the product over this list, but the *dims* property of the new Qobj are set to this list. This can produce either *oper* or *super* depending on the passed *dimensions*.

density [float, [1]] Density between [0,1] of output unitary operator.

distribution [{"haar", "exp"}] Method used to obtain the unitary matrices.

- haar : Haar random unitary matrix using the algorithm of [Mez07].
- exp : Uses $\exp(-iH)$, where H is a randomly generated Hermitian operator.

seed [int, SeedSequence, Generator, optional] Seed to create the random number generator or a pre prepared generator. When none is supplied, a default generator is used.


dtype [type or str] Storage representation. Any data-layer known to *qutip.data.to* is accepted.

Returns

oper [qobj] Unitary quantum operator.

Three-Level Atoms

This module provides functions that are useful for simulating the three level atom with QuTiP. A three level atom (qutrit) has three states, which are linked by dipole transitions so that $1 \leftrightarrow 2 \leftrightarrow 3$. Depending on there relative energies they are in the ladder, lambda or vee configuration. The structure of the relevant operators is the same for any of the three configurations:



References

The naming of qutip operators follows the convention in [1].

Notes

Contributed by Markus Baden, Oct. 07, 2011

three_level_basis()

Basis states for a three level atom.

Returns

states [np.array] `numpy.ndarray` of three level atom basis vectors.

three_level_ops()

Operators for a three level system (qutrit)

Returns

ops [np.array] `numpy.ndarray` of three level operators.

Superoperators and Liouvillians

lindblad_dissipator(a, b=None, data_only=False, chi=None)

Lindblad dissipator (generalized) for a single pair of collapse operators (a, b), or for a single collapse operator (a) when b is not specified:

$$\mathcal{D}[a, b]\rho = a\rho b^\dagger - \frac{1}{2}a^\dagger b\rho - \frac{1}{2}\rho a^\dagger b$$

Parameters

- a** [Qobj or QobjEvo] Left part of collapse operator.
- b** [Qobj or QobjEvo (optional)] Right part of collapse operator. If not specified, b defaults to a.
- chi** [float [None]] In some systems it is possible to determine the statistical moments (mean, variance, etc) of the probability distribution of the occupation numbers of states by numerically evaluating the derivatives of the steady state occupation probability as a function of an artificial phase parameter `chi` which multiplies the `a \rho a^\dagger`

term of the dissipator by $e^{(i * \chi)}$. The factor $e^{(i * \chi)}$ is introduced via the generating function of the statistical moments. For examples of the technique, see [Full counting statistics of nano-electromechanical systems](#) and [Photon-mediated electron transport in hybrid circuit-QED](#). This parameter is deprecated and may be removed in QuTiP 5.

data_only [bool [False]] Return the data object instead of a Qobj

Returns

D [Qobj, QobjEvo] Lindblad dissipator superoperator.

liouvillian ($H=None, c_ops=None, data_only=False, \chi=None$)

Assembles the Liouvillian superoperator from a Hamiltonian and a list of collapse operators.

Parameters

H [Qobj or QobjEvo (optional)] System Hamiltonian or Hamiltonian component of a Liouvillian. Considered 0 if not given.

c_ops [array_like of Qobj or QobjEvo] A list or array of collapse operators.

data_only [bool [False]] Return the data object instead of a Qobj

chi [array_like of float [None]] In some systems it is possible to determine the statistical moments (mean, variance, etc) of the probability distributions of occupation of various states by numerically evaluating the derivatives of the steady state occupation probability as a function of artificial phase parameters **chi** which are included in the [lindblad_dissipator](#) for each collapse operator. See the documentation of [lindblad_dissipator](#) for references and further details. This parameter is deprecated and may be removed in QuTiP 5.

Returns

L [Qobj or QobjEvo] Liouvillian superoperator.

operator_to_vector (*op*)

Create a vector representation given a quantum operator in matrix form. The passed object should have a `Qobj.type` of 'oper' or 'super'; this function is not designed for general-purpose matrix reshaping.

Parameters

op [Qobj or QobjEvo] Quantum operator in matrix form. This must have a type of 'oper' or 'super'.

Returns

Qobj or QobjEvo The same object, but re-cast into a column-stacked-vector form of type 'operator-ket'. The output is the same type as the passed object.

spost (*A*)

Superoperator formed from post-multiplication by operator *A*

Parameters

A [Qobj or QobjEvo] Quantum operator for post multiplication.

Returns

super [Qobj or QobjEvo] Superoperator formed from input quantum object.

spre (*A*)

Superoperator formed from pre-multiplication by operator *A*.

Parameters

A [Qobj or QobjEvo] Quantum operator for pre-multiplication.

Returns

super :Qobj or QobjEvo Superoperator formed from input quantum object.

sprepost (*A*, *B*)

Superoperator formed from pre-multiplication by *A* and post-multiplication by *B*.

Parameters

A [Qobj or QobjEvo] Quantum operator for pre-multiplication.

B [Qobj or QobjEvo] Quantum operator for post-multiplication.

Returns

super [Qobj or QobjEvo] Superoperator formed from input quantum objects.

vector_to_operator (*op*)

Create a matrix representation given a quantum operator in vector form. The passed object should have a `Qobj.type` of 'operator-ket'; this function is not designed for general-purpose matrix reshaping.

Parameters

op [Qobj or QobjEvo] Quantum operator in column-stacked-vector form. This must have a type of 'operator-ket'.

Returns

Qobj or QobjEvo The same object, but re-cast into "standard" operator form. The output is the same type as the passed object.

Superoperator Representations

This module implements transformations between superoperator representations, including supermatrix, Kraus, Choi and Chi (process) matrix formalisms.

kraus_to_choi (*kraus_list*)

Take a list of Kraus operators and returns the Choi matrix for the channel represented by the Kraus operators in *kraus_list*

kraus_to_super (*kraus_list*)

Convert a list of Kraus operators to a superoperator.

to_chi (*q_oper*)

Converts a Qobj representing a quantum map to a representation as a chi (process) matrix in the Pauli basis, such that the trace of the returned operator is equal to the dimension of the system.

Parameters

q_oper [Qobj] Superoperator to be converted to Chi representation. If *q_oper* is `type="oper"`, then it is taken to act by conjugation, such that `to_chi(A) == to_chi(sprepost(A, A.dag()))`.

Returns

chi [Qobj] A quantum object representing the same map as *q_oper*, such that `chi.superrep == "chi"`.

Raises

TypeError: if the given quantum object is not a map, or cannot be converted to Chi representation.

to_choi (*q_oper*)

Converts a Qobj representing a quantum map to the Choi representation, such that the trace of the returned operator is equal to the dimension of the system.

Parameters

q_oper [Qobj] Superoperator to be converted to Choi representation. If *q_oper* is `type="oper"`, then it is taken to act by conjugation, such that `to_choi(A) == to_choi(sprepost(A, A.dag()))`.

Returns

choi [Qobj] A quantum object representing the same map as `q_oper`, such that `choi.superrep == "choi"`.

Raises

TypeError: if the given quantum object is not a map, or cannot be converted to Choi representation.

to_kraus (*q_oper*, *tol*=1e-09)

Converts a Qobj representing a quantum map to a list of quantum objects, each representing an operator in the Kraus decomposition of the given map.

Parameters

q_oper [Qobj] Superoperator to be converted to Kraus representation. If `q_oper` is `type="oper"`, then it is taken to act by conjugation, such that `to_kraus(A) == to_kraus(sprepost(A, A.dag())) == [A]`.

tol [Float] Optional threshold parameter for eigenvalues/Kraus ops to be discarded. The default is `tol=1e-9`.

Returns

kraus_ops [list of Qobj] A list of quantum objects, each representing a Kraus operator in the decomposition of `q_oper`.

Raises

TypeError: if the given quantum object is not a map, or cannot be decomposed into Kraus operators.

to_stinespring (*q_oper*, *threshold*=1e-10)

Converts a Qobj representing a quantum map Λ to a pair of partial isometries A and B such that $\Lambda(X) = \text{Tr}_2(A X B^\dagger)$ for all inputs X , where the partial trace is taken over a new index on the output dimensions of A and B .

For completely positive inputs, A will always equal B up to precision errors.

Parameters

q_oper [Qobj] Superoperator to be converted to a Stinespring pair.

Returns

A, B [Qobj] Quantum objects representing each of the Stinespring matrices for the input Qobj.

to_super (*q_oper*)

Converts a Qobj representing a quantum map to the supermatrix (Liouville) representation.

Parameters

q_oper [Qobj] Superoperator to be converted to supermatrix representation. If `q_oper` is `type="oper"`, then it is taken to act by conjugation, such that `to_super(A) == sprepost(A, A.dag())`.

Returns

superop [Qobj] A quantum object representing the same map as `q_oper`, such that `superop.superrep == "super"`.

Raises

TypeError If the given quantum object is not a map, or cannot be converted to supermatrix representation.

Operators and Superoperator Dimensions

Internal use module for manipulating dims specifications.

collapse_dims_oper (*dims*)

Given the dimensions specifications for a ket-, bra- or oper-type Qobj, returns a dimensions specification describing the same shape by collapsing all composite systems. For instance, the bra-type dimensions specification `[[2, 3], [1]]` collapses to `[[6], [1]]`.

Parameters

dims [list of lists of ints] Dimensions specifications to be collapsed.

Returns

collapsed_dims [list of lists of ints] Collapsed dimensions specification describing the same shape such that `len(collapsed_dims[0]) == len(collapsed_dims[1]) == 1`.

collapse_dims_super (*dims*)

Given the dimensions specifications for an operator-ket-, operator-bra- or super-type Qobj, returns a dimensions specification describing the same shape by collapsing all composite systems. For instance, the super-type dimensions specification `[[[2, 3], [2, 3]], [[2, 3], [2, 3]]]` collapses to `[[[6], [6]], [[6], [6]]]`.

Parameters

dims [list of lists of ints] Dimensions specifications to be collapsed.

Returns

collapsed_dims [list of lists of ints] Collapsed dimensions specification describing the same shape such that `len(collapsed_dims[i][j]) == 1` for `i` and `j` in `range(2)`.

deep_remove (*l, *what*)

Removes scalars from all levels of a nested list.

Given a list containing a mix of scalars and lists, returns a list of the same structure, but where one or more scalars have been removed.

Examples

```
>>> deep_remove([[[[0, 1, 2]], [3, 4], [5], [6, 7]]], 0, 5)
[[[1, 2]], [3, 4], [], [6, 7]]
```

dims_idxes_to_tensor_idxes (*dims, indices*)

Given the dims of a Qobj instance, and some indices into dims, returns the corresponding tensor indices. This helps resolve, for instance, that column-stacking for superoperators, oper-ket and oper-bra implies that the input and output tensor indices are reversed from their order in dims.

Parameters

dims [list] Dimensions specification for a Qobj.

indices [int, list or tuple] Indices to convert to tensor indices. Can be specified as a single index, or as a collection of indices. In the latter case, this can be nested arbitrarily deep. For instance, `[0, [0, (2, 3)]]`.

Returns

tens_indices [int, list or tuple] Container of the same structure as indices containing the tensor indices for each element of indices.

dims_to_tensor_perm (*dims*)

Given the dims of a Qobj instance, returns a list representing a permutation from the flattening of that dims specification to the corresponding tensor indices.

Parameters

dims [list] Dimensions specification for a Qobj.

Returns

perm [list] A list such that `data[flatten(dims)[idx]]` gives the index of the tensor data corresponding to the `idx`'th dimension of `dims`.

dims_to_tensor_shape (*dims*)

Given the dims of a Qobj instance, returns the shape of the corresponding tensor. This helps, for instance, resolve the column-stacking convention for superoperators.

Parameters

dims [list] Dimensions specification for a Qobj.

Returns

tensor_shape [tuple] NumPy shape of the corresponding tensor.

enumerate_flat (*l*)

Labels the indices at which scalars occur in a flattened list.

Given a list containing a mix of scalars and lists, returns a list of the same structure, where each scalar has been replaced by an index into the flattened list.

Examples

```
>>> print(enumerate_flat([[10], [20, 30]], 40))
[[0], [1, 2]], 3]
```

flatten (*l*)

Flattens a list of lists to the first level.

Given a list containing a mix of scalars and lists, flattens down to a list of the scalars within the original list.

Examples

```
>>> flatten([[0], 1], 2)
[0, 1, 2]
```

is_scalar (*dims*)

Returns True if a dims specification is effectively a scalar (has dimension 1).

unflatten (*l, idxs*)

Unflattens a list by a given structure.

Given a list of scalars and a deep list of indices as produced by *flatten*, returns an “unflattened” form of the list. This perfectly inverts *flatten*.

Examples

```
>>> l = [[[10, 20, 30], [40, 50, 60]], [[70, 80, 90], [100, 110, 120]]]
>>> idxs = enumerate_flat(l)
>>> unflatten(flatten(l), idxs) == l
True
```

5.2.2 Functions acting on states and operators

Expectation Values

expect (*oper*, *state*)

Calculate the expectation value for operator(s) and state(s). The expectation of state k on operator A is defined as $k.dag() @ A @ k$, and for density matrix R on operator A it is $trace(A @ R)$.

Parameters

oper [qobj/array-like] A single or a *list* of operators for expectation value.

state [qobj/array-like] A single or a *list* of quantum states or density matrices.

Returns

expt [float/complex/array-like] Expectation value. *real* if *oper* is Hermitian, *complex* otherwise. A (nested) array of expectation values of state or operator are arrays.

Examples

```
>>> expect(num(4), basis(4, 3)) == 3
True
```

variance (*oper*, *state*)

Variance of an operator for the given state vector or density matrix.

Parameters

oper [qobj] Operator for expectation value.

state [qobj/list] A single or *list* of quantum states or density matrices..

Returns

var [float] Variance of operator ‘oper’ for given state.

Tensor

Module for the creation of composite quantum objects via the tensor product.

composite (*args)

Given two or more operators, kets or bras, returns the Qobj corresponding to a composite system over each argument. For ordinary operators and vectors, this is the tensor product, while for superoperators and vectorized operators, this is the column-reshuffled tensor product.

If a mix of Qobjs supported on Hilbert and Liouville spaces are passed in, the former are promoted. Ordinary operators are assumed to be unitaries, and are promoted using `to_super`, while kets and bras are promoted by taking their projectors and using `operator_to_vector(ket2dm(arg))`.

super_tensor (*args)

Calculate the tensor product of input superoperators, by tensoring together the underlying Hilbert spaces on which each vectorized operator acts.

Parameters

args [array_like] list or array of quantum objects with `type="super"`.

Returns

obj [qobj] A composite quantum object.

tensor (*args)

Calculates the tensor product of input operators.

Parameters

args [array_like] list or array of quantum objects for tensor product.

Returns

obj [qobj] A composite quantum object.

Examples

```
>>> tensor([sigmax(), sigmax()])
Quantum object: dims = [[2, 2], [2, 2]], shape = [4, 4], type = oper, isHerm = True
→ True
Qobj data =
[[ 0.+0.j  0.+0.j  0.+0.j  1.+0.j]
 [ 0.+0.j  0.+0.j  1.+0.j  0.+0.j]
 [ 0.+0.j  1.+0.j  0.+0.j  0.+0.j]
 [ 1.+0.j  0.+0.j  0.+0.j  0.+0.j]]
```

tensor_contract (qobj, *pairs)

Contracts a qobj along one or more index pairs. Note that this uses dense representations and thus should *not* be used for very large Qobjs.

Parameters

pairs [tuple] One or more tuples (*i*, *j*) indicating that the *i* and *j* dimensions of the original qobj should be contracted.

Returns

cqobj [Qobj] The original Qobj with all named index pairs contracted away.

Partial Transpose

partial_transpose (rho, mask, method='dense')

Return the partial transpose of a Qobj instance *rho*, where *mask* is an array/list with length that equals the number of components of *rho* (that is, the length of *rho.dims[0]*), and the values in *mask* indicates whether or not the corresponding subsystem is to be transposed. The elements in *mask* can be boolean or integers 0 or 1, where *True/1* indicates that the corresponding subsystem should be transposed.

Parameters

rho [qutip.qobj] A density matrix.

mask [list / array] A mask that selects which subsystems should be transposed.

method [str] choice of method, *dense* or *sparse*. The default method is *dense*. The *sparse* implementation can be faster for large and sparse systems (hundreds of quantum states).

Returns

rho_pr: qutip.qobj A density matrix with the selected subsystems transposed.

Entropy Functions

concurrence (*rho*)

Calculate the concurrence entanglement measure for a two-qubit state.

Parameters

state [qobj] Ket, bra, or density matrix for a two-qubit state.

Returns

concur [float] Concurrence

References

[1]

entropy_conditional (*rho, selB, base=2.718281828459045, sparse=False*)

Calculates the conditional entropy $S(A|B) = S(A, B) - S(B)$ of a selected density matrix component.

Parameters

rho [qobj] Density matrix of composite object

selB [int/list] Selected components for density matrix B

base [{e,2}] Base of logarithm.

sparse [{False,True}] Use sparse eigensolver.

Returns

ent_cond [float] Value of conditional entropy

entropy_linear (*rho*)

Linear entropy of a density matrix.

Parameters

rho [qobj] density matrix or ket/bra vector.

Returns

entropy [float] Linear entropy of rho.

Examples

```
>>> rho=0.5*fock_dm(2,0)+0.5*fock_dm(2,1)
>>> entropy_linear(rho)
0.5
```

entropy_mutual (*rho, selA, selB, base=2.718281828459045, sparse=False*)

Calculates the mutual information $S(A:B)$ between selection components of a system density matrix.

Parameters

rho [qobj] Density matrix for composite quantum systems

selA [int/list] *int* or *list* of first selected density matrix components.

selB [int/list] *int* or *list* of second selected density matrix components.

base [{e,2}] Base of logarithm.

sparse [{False,True}] Use sparse eigensolver.

Returns

ent_mut [float] Mutual information between selected components.

entropy_relative (*rho*, *sigma*, *base*=2.718281828459045, *sparse*=False, *tol*=1e-12)

Calculates the relative entropy $S(\rho||\sigma)$ between two density matrices.

Parameters

rho [qutip.Qobj] First density matrix (or ket which will be converted to a density matrix).

sigma [qutip.Qobj] Second density matrix (or ket which will be converted to a density matrix).

base [{e,2}] Base of logarithm. Defaults to e.

sparse [bool] Flag to use sparse solver when determining the eigenvectors of the density matrices. Defaults to False.

tol [float] Tolerance to use to detect 0 eigenvalues or dot product between eigenvectors. Defaults to 1e-12.

Returns

rel_ent [float] Value of relative entropy. Guaranteed to be greater than zero and should equal zero only when rho and sigma are identical.

References

See Nielsen & Chuang, “Quantum Computation and Quantum Information”, Section 11.3.1, pg. 511 for a detailed explanation of quantum relative entropy.

Examples

First we define two density matrices:

```
>>> rho = qutip.ket2dm(qutip.ket("00"))
>>> sigma = rho + qutip.ket2dm(qutip.ket("01"))
>>> sigma = sigma.unit()
```

Then we calculate their relative entropy using base 2 (i.e. \log_2) and base e (i.e. \log).

```
>>> qutip.entropy_relative(rho, sigma, base=2)
1.0
>>> qutip.entropy_relative(rho, sigma)
0.6931471805599453
```

entropy_vn (*rho*, *base*=2.718281828459045, *sparse*=False)

Von-Neumann entropy of density matrix

Parameters

rho [qobj] Density matrix.

base [{e,2}] Base of logarithm.

sparse [{False,True}] Use sparse eigensolver.

Returns

entropy [float] Von-Neumann entropy of *rho*.

Examples

```
>>> rho=0.5*fock_dm(2,0)+0.5*fock_dm(2,1)
>>> entropy_vn(rho,2)
1.0
```

Density Matrix Metrics

This module contains a collection of functions for calculating metrics (distance measures) between states and operators.

average_gate_fidelity (*oper*, *target=None*)

Returns the average gate fidelity of a quantum channel to the target channel, or to the identity channel if no target is given.

Parameters

oper [qutip.Qobj/list] A unitary operator, or a superoperator in supermatrix, Choi or chi-matrix form, or a list of Kraus operators

target [qutip.Qobj] A unitary operator

Returns

fid [float] Average gate fidelity between oper and target, or between oper and identity.

Notes

The average gate fidelity is defined for example in: A. Gilchrist, N.K. Langford, M.A. Nielsen, Phys. Rev. A 71, 062310 (2005). The definition of state fidelity that the average gate fidelity is based on is the one from R. Jozsa, Journal of Modern Optics, 41:12, 2315 (1994). It is the square of the fidelity implemented in `qutip.core.metrics.fidelity` which follows Nielsen & Chuang, “Quantum Computation and Quantum Information”

bures_angle (*A*, *B*)

Returns the Bures Angle between two density matrices A & B.

The Bures angle ranges from 0, for states with unit fidelity, to $\pi/2$.

Parameters

A [qobj] Density matrix or state vector.

B [qobj] Density matrix or state vector with same dimensions as A.

Returns

angle [float] Bures angle between density matrices.

bures_dist (*A*, *B*)

Returns the Bures distance between two density matrices A & B.

The Bures distance ranges from 0, for states with unit fidelity, to $\sqrt{2}$.

Parameters

A [qobj] Density matrix or state vector.

B [qobj] Density matrix or state vector with same dimensions as A.

Returns

dist [float] Bures distance between density matrices.

dnorm (*A*, *B=None*, *solver='CVXOPT'*, *verbose=False*, *force_solve=False*, *sparse=True*)

Calculates the diamond norm of the quantum map *q_oper*, using the simplified semidefinite program of [Wat13].

The diamond norm SDP is solved by using CVXPY.

Parameters

A [Qobj] Quantum map to take the diamond norm of.

B [Qobj or None] If provided, the diamond norm of $A - B$ is taken instead.

solver [str] Solver to use with CVXPY. One of “CVXOPT” (default) or “SCS”. The latter tends to be significantly faster, but somewhat less accurate.

verbose [bool] If True, prints additional information about the solution.

force_solve [bool] If True, forces dnorm to solve the associated SDP, even if a special case is known for the argument.

sparse [bool] Whether to use sparse matrices in the convex optimisation problem. Default True.

Returns

dn [float] Diamond norm of *q_oper*.

Raises

ImportError If CVXPY cannot be imported.

fidelity (*A*, *B*)

Calculates the fidelity (pseudo-metric) between two density matrices. See: Nielsen & Chuang, “Quantum Computation and Quantum Information”

Parameters

A [qobj] Density matrix or state vector.

B [qobj] Density matrix or state vector with same dimensions as A.

Returns

fid [float] Fidelity pseudo-metric between A and B.

Examples

```
>>> x = fock_dm(5,3)
>>> y = coherent_dm(5,1)
>>> np.testing.assert_almost_equal(fidelity(x,y), 0.24104350624628332)
```

hellinger_dist (*A*, *B*, *sparse=False*, *tol=0*)

Calculates the quantum Hellinger distance between two density matrices.

Formula: $\text{hellinger_dist}(A, B) = \sqrt{2 \cdot \text{Tr}(\sqrt{A} \sqrt{B})}$

See: D. Spehner, F. Illuminati, M. Orszag, and W. Roga, “Geometric measures of quantum correlations with Bures and Hellinger distances” arXiv:1611.03449

Parameters

A [qutip.Qobj] Density matrix or state vector.

B [qutip.Qobj] Density matrix or state vector with same dimensions as A.

tol [float] Tolerance used by sparse eigensolver, if used. (0=Machine precision)

sparse [{False, True}] Use sparse eigensolver.

Returns

hellinger_dist [float] Quantum Hellinger distance between A and B. Ranges from 0 to $\sqrt{2}$.

Examples

```
>>> x=fock_dm(5,3)
>>> y=coherent_dm(5,1)
>>> np.testing.assert_almost_equal(hellinger_dist(x,y), 1.3725145002591095)
```

hilbert_dist (A, B)

Returns the Hilbert-Schmidt distance between two density matrices A & B.

Parameters

- A** [qobj] Density matrix or state vector.
- B** [qobj] Density matrix or state vector with same dimensions as A.

Returns

dist [float] Hilbert-Schmidt distance between density matrices.

Notes

See V. Vedral and M. B. Plenio, Phys. Rev. A 57, 1619 (1998).

process_fidelity (oper, target=None)

Returns the process fidelity of a quantum channel to the target channel, or to the identity channel if no target is given. The process fidelity between two channels is defined as the state fidelity between their normalized Choi matrices.

Parameters

- oper** [qutip.Qobj/list] A unitary operator, or a superoperator in supermatrix, Choi or chi-matrix form, or a list of Kraus operators
- target** [qutip.Qobj/list] A unitary operator, or a superoperator in supermatrix, Choi or chi-matrix form, or a list of Kraus operators

Returns

fid [float] Process fidelity between oper and target, or between oper and identity.

Notes

Since Qutip 5.0, this function computes the process fidelity as defined for example in: A. Gilchrist, N.K. Langford, M.A. Nielsen, Phys. Rev. A 71, 062310 (2005). Previously, it computed a function that is now implemented in `control.fidcomp.FidCompUnitary.get_fidelity`. The definition of state fidelity that the process fidelity is based on is the one from R. Jozsa, Journal of Modern Optics, 41:12, 2315 (1994). It is the square of the one implemented in `qutip.core.metrics.fidelity` which follows Nielsen & Chuang, “Quantum Computation and Quantum Information”

tracedist (A, B, sparse=False, tol=0)

Calculates the trace distance between two density matrices.. See: Nielsen & Chuang, “Quantum Computation and Quantum Information”

Parameters

- A** [qobj] Density matrix or state vector.
- B** [qobj] Density matrix or state vector with same dimensions as A.
- tol** [float] Tolerance used by sparse eigensolver, if used. (0=Machine precision)

sparse [{False, True}] Use sparse eigensolver.

Returns

tracedist [float] Trace distance between A and B.

Examples

```
>>> x=fock_dm(5,3)
>>> y=coherent_dm(5,1)
>>> np.testing.assert_almost_equal(tracedist(x,y), 0.9705143161472971)
```

unitarity(*oper*)

Returns the unitarity of a quantum map, defined as the Frobenius norm of the unital block of that map's superoperator representation.

Parameters

oper [Qobj] Quantum map under consideration.

Returns

u [float] Unitarity of *oper*.

Continuous Variables

This module contains a collection functions for calculating continuous variable quantities from fock-basis representation of the state of multi-mode fields.

correlation_matrix(*basis*, *rho=None*)

Given a basis set of operators $\{a\}_n$, calculate the correlation matrix:

$$C_{mn} = \langle a_m a_n \rangle$$

Parameters

basis [list] List of operators that defines the basis for the correlation matrix.

rho [Qobj] Density matrix for which to calculate the correlation matrix. If *rho* is *None*, then a matrix of correlation matrix operators is returned instead of expectation values of those operators.

Returns

corr_mat [ndarray] A 2-dimensional *array* of correlation values or operators.

correlation_matrix_field(*a1*, *a2*, *rho=None*)

Calculates the correlation matrix for given field operators a_1 and a_2 . If a density matrix is given the expectation values are calculated, otherwise a matrix with operators is returned.

Parameters

a1 [Qobj] Field operator for mode 1.

a2 [Qobj] Field operator for mode 2.

rho [Qobj] Density matrix for which to calculate the covariance matrix.

Returns

cov_mat [ndarray] Array of complex numbers or Qobj's A 2-dimensional *array* of covariance values, or, if *rho=0*, a matrix of operators.

correlation_matrix_quadrature(*a1*, *a2*, *rho=None*, *g=1.4142135623730951*)

Calculate the quadrature correlation matrix with given field operators a_1 and a_2 . If a density matrix is given the expectation values are calculated, otherwise a matrix with operators is returned.

Parameters

a1 [Qobj] Field operator for mode 1.

a2 [Qobj] Field operator for mode 2.

rho [Qobj] Density matrix for which to calculate the covariance matrix.

g [float] Scaling factor for $a = 0.5 * g * (x + iy)$, default $g = \sqrt{2}$. The value of g is related to the value of \hbar in the commutation relation $[x, y] = i * \hbar$ via $\hbar = 2/g$ giving the default value $\hbar = 1$.

Returns

corr_mat [ndarray] Array of complex numbers or Qobj's A 2-dimensional array of covariance values for the field quadratures, or, if $\rho=0$, a matrix of operators.

covariance_matrix (*basis, rho, symmetrized=True*)

Given a basis set of operators $\{a\}_n$, calculate the covariance matrix:

$$V_{mn} = \frac{1}{2} \langle a_m a_n + a_n a_m \rangle - \langle a_m \rangle \langle a_n \rangle$$

or, if of the optional argument *symmetrized=False*,

$$V_{mn} = \langle a_m a_n \rangle - \langle a_m \rangle \langle a_n \rangle$$

Parameters

basis [list] List of operators that defines the basis for the covariance matrix.

rho [Qobj] Density matrix for which to calculate the covariance matrix.

symmetrized [bool {True, False}] Flag indicating whether the symmetrized (default) or non-symmetrized correlation matrix is to be calculated.

Returns

corr_mat [ndarray] A 2-dimensional array of covariance values.

logarithmic_negativity (*V, g=1.4142135623730951*)

Calculates the logarithmic negativity given a symmetrized covariance matrix, see [qutip.continuous_variables.covariance_matrix](#). Note that the two-mode field state that is described by V must be Gaussian for this function to be applicable.

Parameters

V [2d array] The covariance matrix.

g [float] Scaling factor for $a = 0.5 * g * (x + iy)$, default $g = \sqrt{2}$. The value of g is related to the value of \hbar in the commutation relation $[x, y] = i * \hbar$ via $\hbar = 2/g$ giving the default value $\hbar = 1$.

Returns

N [float] The logarithmic negativity for the two-mode Gaussian state that is described by the Wigner covariance matrix V .

wigner_covariance_matrix (*a1=None, a2=None, R=None, rho=None, g=1.4142135623730951*)

Calculates the Wigner covariance matrix $V_{ij} = \frac{1}{2} \langle R_{ij} + R_{ji} \rangle$, given the quadrature correlation matrix $R_{ij} = \langle R_i R_j \rangle - \langle R_i \rangle \langle R_j \rangle$, where $R = (q_1, p_1, q_2, p_2)^T$ is the vector with quadrature operators for the two modes.

Alternatively, if $R = None$, and if annihilation operators $a1$ and $a2$ for the two modes are supplied instead, the quadrature correlation matrix is constructed from the annihilation operators before then the covariance matrix is calculated.

Parameters

a1 [Qobj] Field operator for mode 1.

a2 [Qobj] Field operator for mode 2.

R [ndarray] The quadrature correlation matrix.

rho [Qobj] Density matrix for which to calculate the covariance matrix.

g [float] Scaling factor for $a = 0.5 * g * (x + iy)$, default $g = \sqrt{2}$. The value of g is related to the value of \hbar in the commutation relation $[x, y] = i * \hbar$ via $\hbar = 2/g$ giving the default value $\hbar = 1$.

Returns

cov_mat [ndarray] A 2-dimensional array of covariance values.

5.2.3 Measurement

Measurement of quantum states

Module for measuring quantum objects.

measure (*state, ops*)

A dispatch method that provides measurement results handling both observable style measurements and projector style measurements (POVMs and PVMs).

For return signatures, please check:

- `measure_observable` for observable measurements.
- `measure_povm` for POVM measurements.

Parameters

state [Qobj] The ket or density matrix specifying the state to measure.

ops [Qobj or list of Qobj]

- measurement observable (Qobj); or
- list of measurement operators M_i or kets (list of Qobj) Either:
 1. specifying a POVM s.t. $E_i = M_i^\dagger M_i$
 2. projection operators if ops correspond to projectors (s.t. $E_i = M_i^\dagger = M_i$)
 3. kets (transformed to projectors)

measure_observable (*state, op*)

Perform a measurement specified by an operator on the given state.

This function simulates the classic quantum measurement described in many introductory texts on quantum mechanics. The measurement collapses the state to one of the eigenstates of the given operator and the result of the measurement is the corresponding eigenvalue.

Parameters

state [Qobj] The ket or density matrix specifying the state to measure.

op [Qobj] The measurement operator.

Returns

measured_value [float] The result of the measurement (one of the eigenvalues of op).

state [Qobj] The new state (a ket if a ket was given, otherwise a density matrix).

Examples

Measure the z-component of the spin of the spin-up basis state:

```
>>> measure_observable(basis(2, 0), sigmaz())
(1.0, Quantum object: dims = [[2], [1]], shape = (2, 1), type = ket
Qobj data =
[[-1.]
 [ 0.]])
```

Since the spin-up basis is an eigenstate of `sigmaz`, this measurement always returns 1 as the measurement result (the eigenvalue of the spin-up basis) and the original state (up to a global phase).

Measure the x-component of the spin of the spin-down basis state:

```
>>> measure_observable(basis(2, 1), sigmax())
(-1.0, Quantum object: dims = [[2], [1]], shape = (2, 1), type = ket
Qobj data =
[[-0.70710678]
 [ 0.70710678]])
```

This measurement returns 1 fifty percent of the time and -1 the other fifty percent of the time. The new state returned is the corresponding eigenstate of `sigmax`.

One may also perform a measurement on a density matrix. Below we perform the same measurement as above, but on the density matrix representing the pure spin-down state:

```
>>> measure_observable(ket2dm(basis(2, 1)), sigmax())
(-1.0, Quantum object: dims = [[2], [2]], shape = (2, 2), type = oper
Qobj data =
[[ 0.5 -0.5]
 [-0.5  0.5]])
```

The measurement result is the same, but the new state is returned as a density matrix.

`measure_povm(state, ops)`

Perform a measurement specified by list of POVMs.

This function simulates a POVM measurement. The measurement collapses the state to one of the resultant states of the measurement and returns the index of the operator corresponding to the collapsed state as well as the collapsed state.

Parameters

state [*Qobj*] The ket or density matrix specifying the state to measure.

ops [list of *Qobj*] List of measurement operators M_i or kets. Either:

1. specifying a POVM s.t. $E_i = M_i^\dagger M_i$
2. projection operators if ops correspond to projectors (s.t. $E_i = M_i^\dagger = M_i$)
3. kets (transformed to projectors)

Returns

index [float] The resultant index of the measurement.

state [*Qobj*] The new state (a ket if a ket was given, otherwise a density matrix).

`measurement_statistics(state, ops)`

A dispatch method that provides measurement statistics handling both observable style measurements and projector style measurements(POVMs and PVMs).

For return signatures, please check:

- `measurement_statistics_observable` for observable measurements.

- `measurement_statistics_povm` for POVM measurements.

Parameters

state [*Qobj*] The ket or density matrix specifying the state to measure.

ops [*Qobj* or list of *Qobj*]

- measurement observable (:class:Qobj); or
- list of measurement operators M_i or kets (list of *Qobj*) Either:
 1. specifying a POVM s.t. $E_i = M_i^\dagger * M_i$
 2. projection operators if ops correspond to projectors (s.t. $E_i = M_i^\dagger = M_i$)
 3. kets (transformed to projectors)

measurement_statistics_observable (*state*, *op*)

Return the measurement eigenvalues, eigenstates (or projectors) and measurement probabilities for the given state and measurement operator.

Parameters

state [*Qobj*] The ket or density matrix specifying the state to measure.

op [*Qobj*] The measurement operator.

Returns

eigenvalues: list of float The list of eigenvalues of the measurement operator.

eigenstates_or_projectors: list of *Qobj* If the state was a ket, return the eigenstates of the measurement operator. Otherwise return the projectors onto the eigenstates.

probabilities: list of float The probability of measuring the state as being in the corresponding eigenstate (and the measurement result being the corresponding eigenvalue).

measurement_statistics_povm (*state*, *ops*)

Returns measurement statistics (resultant states and probabilities) for a measurement specified by a set of positive operator valued measurements on a specified ket or density matrix.

Parameters

state [*Qobj*] The ket or density matrix specifying the state to measure.

ops [list of *Qobj*] List of measurement operators M_i or kets. Either:

1. specifying a POVM s.t. $E_i = M_i^\dagger M_i$
2. projection operators if ops correspond to projectors (s.t. $E_i = M_i^\dagger = M_i$)
3. kets (transformed to projectors)

Returns

collapsed_states [list of *Qobj*] The collapsed states obtained after measuring the qubits and obtaining the qubit specified by the target in the state specified by the index.

probabilities [list of floats] The probability of measuring a state in a the state specified by the index.

5.2.4 Dynamics and Time-Evolution

Schrödinger Equation

This module provides solvers for the unitary Schrodinger equation.

sesolve (*H*, *psi0*, *tlist*, *e_ops=None*, *args=None*, *options=None*)

Schrodinger equation evolution of a state vector or unitary matrix for a given Hamiltonian.

Evolve the state vector (*psi0*) using a given Hamiltonian (*H*), by integrating the set of ordinary differential equations that define the system. Alternatively evolve a unitary matrix in solving the Schrodinger operator equation.

The output is either the state vector or unitary matrix at arbitrary points in time (*tlist*), or the expectation values of the supplied operators (*e_ops*). If *e_ops* is a callback function, it is invoked for each time in *tlist* with time and the state as arguments, and the function does not use any return values. *e_ops* cannot be used in conjunction with solving the Schrodinger operator equation

Time-dependent operators

For time-dependent problems, *H* and *c_ops* can be a `QobjEvo` or object that can be interpreted as `QobjEvo` such as a list of (`Qobj`, `Coefficient`) pairs or a function.

Parameters

H [`Qobj`, `QobjEvo`, `QobjEvo` compatible format.] System Hamiltonian as a `Qobj` or `QobjEvo` for time-dependent Hamiltonians. List of [`Qobj`, `Coefficient`] or callable that can be made into `QobjEvo` are also accepted.

psi0 [`qutip.qobj`] initial state vector (ket) or initial unitary operator $\psi_0 = U$

tlist [*list* / *array*] list of times for *t*.

e_ops [`qutip.qobj`, callable, or list.] Single operator or list of operators for which to evaluate expectation values or callable or list of callable. Callable signature must be, $f(t: \text{float}, \text{state}: \text{Qobj})$. See `expect` for more detail of operator expectation.

args [*None* / *dictionary*] dictionary of parameters for time-dependent Hamiltonians

options [*None* / *dict*] Dictionary of options for the solver.

- **store_final_state** : bool Whether or not to store the final state of the evolution in the result class.
- **store_states** : bool, None Whether or not to store the state vectors or density matrices. On *None* the states will be saved if no expectation operators are given.
- **normalize_output** : bool Normalize output state to hide ODE numerical errors.
- **progress_bar** : str { 'text', 'enhanced', 'tqdm', '' } How to present the solver progress. 'tqdm' uses the python module of the same name and raise an error if not installed. Empty string or False will disable the bar.
- **progress_kwargs** : dict kwargs to pass to the progress_bar. Qutip's bars use *chunk_size*.
- **method** : str ["adams", "bdf", "lsoda", "dop853", "vern9", etc.] Which differential equation integration method to use.
- **atol**, **rtol** : float Absolute and relative tolerance of the ODE integrator.
- **nsteps** : Maximum number of (internally defined) steps allowed in one *tlist* step.
- **max_step** : float, 0 Maximum length of one internal step. When using pulses, it should be less than half the width of the thinnest pulse.

Other options could be supported depending on the integration method, see [Integrator](#).

Returns

result: qutip.Result An instance of the class `qutip.Result`, which contains a *list of array result.expect* of expectation values for the times specified by *tlist*, and/or a *list result.states* of state vectors or density matrices corresponding to the times in *tlist* [if *e_ops* is an empty list of *store_states=True* in options].

Master Equation

This module provides solvers for the Lindblad master equation and von Neumann equation.

mesolve (*H*, *rho0*, *tlist*, *c_ops=None*, *e_ops=None*, *args=None*, *options=None*)

Master equation evolution of a density matrix for a given Hamiltonian and set of collapse operators, or a Liouvillian.

Evolve the state vector or density matrix (*rho0*) using a given Hamiltonian or Liouvillian (*H*) and an optional set of collapse operators (*c_ops*), by integrating the set of ordinary differential equations that define the system. In the absence of collapse operators the system is evolved according to the unitary evolution of the Hamiltonian.

The output is either the state vector at arbitrary points in time (*tlist*), or the expectation values of the supplied operators (*e_ops*). If *e_ops* is a callback function, it is invoked for each time in *tlist* with time and the state as arguments, and the function does not use any return values.

If either *H* or the Qobj elements in *c_ops* are superoperators, they will be treated as direct contributions to the total system Liouvillian. This allows the solution of master equations that are not in standard Lindblad form.

Time-dependent operators

For time-dependent problems, *H* and *c_ops* can be a QobjEvo or object that can be interpreted as QobjEvo such as a list of (Qobj, Coefficient) pairs or a function.

Additional options

Additional options to mesolve can be set via the *options* argument. Many ODE integration options can be set this way, and the *store_states* and *store_final_state* options can be used to store states even though expectation values are requested via the *e_ops* argument.

Note: When no collapse operator are given and the *H* is not a superoperator, it will defer to *sesolve*.

Parameters

H [Qobj, QobjEvo, QobjEvo compatible format.] Possibly time-dependent system Liouvillian or Hamiltonian as a Qobj or QobjEvo. List of [Qobj, Coefficient] or callable that can be made into QobjEvo are also accepted.

rho0 [Qobj] initial density matrix or state vector (ket).

tlist [list / array] list of times for *t*.

c_ops [list of (QobjEvo, QobjEvo compatible format)] Single collapse operator, or list of collapse operators, or a list of Liouvillian superoperators. None is equivalent to an empty list.

e_ops [list of Qobj / callback function] Single operator or list of operators for which to evaluate expectation values or callable or list of callable. Callable signature must be, *f(t: float, state: Qobj)*. See *expect* for more detail of operator expectation.

args [None / dictionary] dictionary of parameters for time-dependent Hamiltonians and collapse operators.

options [None / dict] Dictionary of options for the solver.

- **store_final_state** : bool Whether or not to store the final state of the evolution in the result class.

- `store_states` : bool, None Whether or not to store the state vectors or density matrices. On *None* the states will be saved if no expectation operators are given.
- `normalize_output` : bool Normalize output state to hide ODE numerical errors.
- `progress_bar` : str { 'text', 'enhanced', 'tqdm', '' } How to present the solver progress. 'tqdm' uses the python module of the same name and raise an error if not installed. Empty string or False will disable the bar.
- `progress_kwargs` : dict kwargs to pass to the `progress_bar`. Qutip's bars use *chunk_size*.
- `method` : str ["adams", "bdf", "lsoda", "dop853", "vern9", etc.] Which differential equation integration method to use.
- `atol`, `rtol` : float Absolute and relative tolerance of the ODE integrator.
- `nsteps` : Maximum number of (internally defined) steps allowed in one `tlist` step.
- `max_step` : float, 0 Maximum length of one internal step. When using pulses, it should be less than half the width of the thinnest pulse.

Other options could be supported depending on the integration method, see [Integrator](#).

Returns

result: `qutip.Result` An instance of the class `qutip.Result`, which contains a *list of array result.expect* of expectation values for the times specified by *tlist*, and/or a *list result.states* of state vectors or density matrices corresponding to the times in *tlist* [if *e_ops* is an empty list of *store_states=True* in options].

Monte Carlo Evolution

mcsolve (*H*, *state*, *tlist*, *c_ops*=(), *e_ops*=None, *ntraj*=500, *, *args*=None, *options*=None, *seeds*=None, *target_tol*=None, *timeout*=None)

Monte Carlo evolution of a state vector $|\psi\rangle$ for a given Hamiltonian and sets of collapse operators. Options for the underlying ODE solver are given by the Options class.

Parameters

H [`qutip.Qobj`, `qutip.QobjEvo`, list, callable.] System Hamiltonian as a `Qobj`, `QobjEvo`. It can also be any input type that `QobjEvo` accepts (see `qutip.QobjEvo`'s documentation). *H* can also be a superoperator (liouvillian) if some collapse operators are to be treated deterministically.

state [`qutip.Qobj`] Initial state vector.

tlist [array_like] Times at which results are recorded.

c_ops [list] A list of collapse operators in any input type that `QobjEvo` accepts (see `qutip.QobjEvo`'s documentation). They must be operators even if *H* is a superoperator. If none are given, the solver will defer to `sesolve` or `mesolve`.

e_ops [list, [optional]] A list of operator as `Qobj`, `QobjEvo` or callable with signature of (t, state: `Qobj`) for calculating expectation values. When no *e_ops* are given, the solver will default to save the states.

ntraj [int] Maximum number of trajectories to run. Can be cut short if a time limit is passed with the `timeout` keyword or if the target tolerance is reached, see `target_tol`.

args [None / dict] Arguments for time-dependent Hamiltonian and collapse operator terms.

options [None / dict] Dictionary of options for the solver.

- `store_final_state` : bool [False] Whether or not to store the final state of the evolution in the result class.

- `store_states` : bool, NoneType, [None] Whether or not to store the state vectors or density matrices. On *None* the states will be saved if no expectation operators are given.
- `progress_bar` : str { 'text', 'enhanced', 'tqdm', '' }, ['text'] How to present the solver progress. 'tqdm' uses the python module of the same name and raise an error if not installed. Empty string or False will disable the bar.
- `progress_kwargs` : dict, [{"chunk_size": 10}] kwargs to pass to the progress_bar. Qutip's bars use *chunk_size*.
- `method` : str { "adams", "bdf", "dop853", "vern9", etc. } ["adams"] Which differential equation integration method to use.
- `keep_runs_results` : bool, [False] Whether to store results from all trajectories or just store the averages.
- `map` : str { "serial", "parallel", "loky" }, ["serial"] How to run the trajectories. "parallel" uses concurrent module to run in parallel while "loky" use the module of the same name to do so.
- `job_timeout` : NoneType, int, [None] Maximum time to compute one trajectory.
- `num_cpus` : NoneType, int, [None] Number of cpus to use when running in parallel. *None* detect the number of available cpus.
- `norm_t_tol`, `norm_tol`, `norm_steps` : float, float, int, [1e-6, 1e-4, 5] Parameters used to find the collapse location. `norm_t_tol` and `norm_tol` are the tolerance in time and norm respectively. An error will be raised if the collapse could not be found within `norm_steps` tries.
- `mc_corr_eps` : float, [1e-10] Small number used to detect non-physical collapse caused by numerical imprecision.
- `atol`, `rtol` : float, [1e-8, 1e-6] Absolute and relative tolerance of the ODE integrator.
- `nsteps` : int [2500] Maximum number of (internally defined) steps allowed in one `tlist` step.
- `max_step` : float, [0] Maximum lenght of one internal step. When using pulses, it should be less than half the width of the thinnest pulse.

seeds [int, SeedSequence, list, [optional]] Seed for the random number generator. It can be a single seed used to spawn seeds for each trajectory or a list of seeds, one for each trajectory. Seeds are saved in the result and they can be reused with:

```
seeds=prev_result.seeds
```

target_tol [{float, tuple, list}, optional] Target tolerance of the evolution. The evolution will compute trajectories until the error on the expectation values is lower than this tolerance. The maximum number of trajectories employed is given by `ntraj`. The error is computed using jackknife resampling. `target_tol` can be an absolute tolerance or a pair of absolute and relative tolerance, in that order. Lastly, it can be a list of pairs of (`atol`, `rtol`) for each `e_ops`.

timeout [float [optional]] Maximum time for the evolution in second. When reached, no more trajectories will be computed. Overwrite the option of the same name.

Returns

results [qutip.solver.Result] Object storing all results from the simulation. Which results is saved depends on the presence of `e_ops` and the options used. `collapse` and `photocurrent` is available to Monte Carlo simulation results.

Krylov Subspace Solver

krylovsolve (*H*, *psi0*, *tlist*, *krylov_dim*, *e_ops*=None, *args*=None, *options*=None)

Schrodinger equation evolution of a state vector for time independent Hamiltonians using Krylov method.

Evolve the state vector (“psi0”) finding an approximation for the time evolution operator of Hamiltonian (“H”) by obtaining the projection of the time evolution operator on a set of small dimensional Krylov subspaces ($m \ll \dim(H)$).

The output is either the state vector or unitary matrix at arbitrary points in time (*tlist*), or the expectation values of the supplied operators (*e_ops*). If *e_ops* is a callback function, it is invoked for each time in *tlist* with time and the state as arguments, and the function does not use any return values. *e_ops* cannot be used in conjunction with solving the Schrodinger operator equation

Parameters

H [*Qobj*, *QobjEvo*, *QobjEvo* compatible format.] System Hamiltonian as a *Qobj* or *QobjEvo* for time-dependent Hamiltonians. List of [*Qobj*, *Coefficient*] or callable that can be made into *QobjEvo* are also accepted.

psi0 [*qutip.qobj*] initial state vector (ket) or initial unitary operator $\psi_0 = U$

tlist [*list* / *array*] list of times for *t*.

krylov_dim: int Dimension of Krylov approximation subspaces used for the time evolution approximation.

e_ops [*qutip.qobj*, callable, or list.] Single operator or list of operators for which to evaluate expectation values or callable or list of callable. Callable signature must be, $f(t: \text{float}, \text{state}: \text{Qobj})$. See `expect` for more detail of operator expectation.

args [None / *dictionary*] dictionary of parameters for time-dependent Hamiltonians

options [None / *dict*] Dictionary of options for the solver.

- **store_final_state** : bool, [False] Whether or not to store the final state of the evolution in the result class.
- **store_states** : bool, [None] Whether or not to store the state vectors or density matrices. On *None* the states will be saved if no expectation operators are given.
- **normalize_output** : bool, [True] Normalize output state to hide ODE numerical errors.
- **progress_bar** : str {‘text’, ‘enhanced’, ‘tqdm’, ‘’, [“text”]} How to present the solver progress. ‘tqdm’ uses the python module of the same name and raise an error if not installed. Empty string or False will disable the bar.
- **progress_kwargs** : dict, [{“chunk_size”: 10}] kwargs to pass to the progress_bar. Qutip’s bars use *chunk_size*.
- **atol**: float [1e-7] Absolute and relative tolerance of the ODE integrator.
- **nsteps** : int [100] Maximum number of (internally defined) steps allowed in one *tlist* step.
- **min_step, max_step** : float, [1e-5, 1e5] Minimum and maximum length of one internal step.
- **always_compute_step**: bool [False] If True, the step length is computed each time a new Krylov subspace is computed. Otherwise it is computed only once when creating the integrator.
- **sub_system_tol**: float, [1e-7] Tolerance to detect an happy breakdown. An happy breakdown happens when the initial ket is in a subspace of the Hamiltonian smaller than *krylov_dim*.

Returns

result: qutip.Result An instance of the class `qutip.Result`, which contains a *list of array result.expect* of expectation values for the times specified by *tlist*, and/or a *list result.states* of state vectors or density matrices corresponding to the times in *tlist* [if *e_ops* is an empty list of *store_states=True* in options].

Bloch-Redfield Master Equation

This module provides solvers for the Lindblad master equation and von Neumann equation.

brmesolve (*H, psi0, tlist, a_ops=[], e_ops=[], c_ops=[], args={}, sec_cutoff=0.1, options=None*)

Solves for the dynamics of a system using the Bloch-Redfield master equation, given an input Hamiltonian, Hermitian bath-coupling terms and their associated spectral functions, as well as possible Lindblad collapse operators.

Parameters

H [*Qobj*, *QobjEvo*] Possibly time-dependent system Liouvillian or Hamiltonian as a *Qobj* or *QobjEvo*. list of [*Qobj*, *Coefficient*] or callable that can be made into *QobjEvo* are also accepted.

psi0: Qobj Initial density matrix or state vector (ket).

tlist [array_like] List of times for evaluating evolution

a_ops [list of (*a_op*, *spectra*)] Nested list of system operators that couple to the environment, and the corresponding bath spectra.

a_op [*qutip.Qobj*, *qutip.QobjEvo*] The operator coupling to the environment. Must be hermitian.

spectra [*Coefficient*, *str*, *func*] The corresponding bath spectral response. Can be a *Coefficient* using an 'w' args, a function of the frequency or a string. *Coefficient* build from a numpy array are understood as a function of *w* instead of *t*. Function are expected to be of the signature *f(w)* or *f(t, w, **args)*.

The spectra function can depend on *t* if the corresponding *a_op* is a *QobjEvo*.

Example:

```
a_ops = [
    (a+a.dag(), ('w>0', args={"w": 0})),
    (QobjEvo(a+a.dag()), 'w > exp(-t)'),
    (QobjEvo([b+b.dag(), lambda t: ...], lambda w: ...),
    (c+c.dag(), SpectraCoefficient(coefficient(array,
    ↪tlist=ws))),
]
```

e_ops [list of *Qobj* / callback function] Single operator or list of operators for which to evaluate expectation values or callable or list of callable. Callable signature must be, *f(t: float, state: Qobj)*. See *expect* for more detail of operator expectation

c_ops [list of (*QobjEvo*, *QobjEvo* compatible format)] List of collapse operators.

args [dict] Dictionary of parameters for time-dependent Hamiltonians and collapse operators. The key *w* is reserved for the spectra function.

sec_cutoff [float {0.1}] Cutoff for secular approximation. Use -1 if secular approximation is not used when evaluating bath-coupling terms.

options [None / dict] Dictionary of options for the solver.

- **store_final_state** : bool Whether or not to store the final state of the evolution in the result class.
- **store_states** : bool, None Whether or not to store the state vectors or density matrices. On *None* the states will be saved if no expectation operators are given.

- `normalize_output` : bool Normalize output state to hide ODE numerical errors.
- `progress_bar` : str { 'text', 'enhanced', 'tqdm', '' } How to present the solver progress. 'tqdm' uses the python module of the same name and raise an error if not installed. Empty string or False will disable the bar.
- `progress_kwargs` : dict kwargs to pass to the `progress_bar`. Qutip's bars use `chunk_size`.
- `tensor_type` : str ['sparse', 'dense', 'data'] Which data type to use when computing the brtensor. With a cutoff 'sparse' is usually the most efficient.
- `sparse_eigsolver` : bool {False} Whether to use the sparse eigensolver
- `method` : str ["adams", "bdf", "lsoda", "dop853", "vern9", etc.] Which differential equation integration method to use.
- `atol, rtol` : float Absolute and relative tolerance of the ODE integrator.
- `nsteps` : Maximum number of (internally defined) steps allowed in one `tlist` step.
- `max_step` : float, 0 Maximum length of one internal step. When using pulses, it should be less than half the width of the thinnest pulse.

Other options could be supported depending on the integration method, see [Integrator](#).

Returns

result: `qutip.solver.Result` An instance of the class `qutip.solver.Result`, which contains either an array of expectation values, for operators given in `e_ops`, or a list of states for the times specified by `tlist`.

Floquet States and Floquet-Markov Master Equation

class FMESolver (*floquet_basis, a_ops, w_th=0.0, *, kmax=5, nT=None, options=None*)
 Solver for the Floquet-Markov master equation.

Note: Operators (`c_ops` and `e_ops`) are in the laboratory basis.

Parameters

- floquet_basis** [`qutip.FloquetBasis`] The system Hamiltonian wrapped in a Floquet-Basis object. Choosing a different integrator for the `floquet_basis` than for the evolution of the floquet state can improve the performance.
- a_ops** [list of tuple(`qutip.Qobj`, callable)] List of collapse operators and the corresponding function for the noise power spectrum. The collapse operator must be a `Qobj` and cannot be time dependent. The spectrum function must take and return a numpy array.
- w_th** [float] The temperature of the environment in units of Hamiltonian frequency.
- kmax** [int [5]] The truncation of the number of sidebands..
- nT** [int [20*kmax]] The number of integration steps (for calculating X) within one period.
- options** [dict, optional] Options for the solver, see `FMESolver.options` and [Integrator](#) for a list of all options.

resultclass

alias of `qutip.solver.floquet.FloquetResult`

run (*state0, tlist, *, floquet=False, args=None, e_ops=None*)
 Calculate the evolution of the quantum system.

For a `state0` at time `tlist[0]` do the evolution as directed by `rhs` and for each time in `tlist` store the state and/or expectation values in a `Result`. The evolution method and stored results are determined by `options`.

Parameters

- state0** [`Qobj`] Initial state of the evolution.
- tlist** [list of double] Time for which to save the results (state and/or expect) of the evolution. The first element of the list is the initial time of the evolution. Each times of the list must be increasing, but does not need to be uniformly distributed.
- floquet** [bool, optional {False}] Whether the initial state in the floquet basis or laboratory basis.
- args** [dict, optional {None}] Not supported
- e_ops** [list {None}] List of `Qobj`, `QobjEvo` or callable to compute the expectation values. Function[s] must have the signature `f(t : float, state : Qobj) -> expect`.

Returns

- results** [`qutip.solver.FloquetResult`] Results of the evolution. States and/or expect will be saved. You can control the saved data in the options.

start (`state0`, `t0`, *, `floquet=False`)

Set the initial state and time for a step evolution. `options` for the evolutions are read at this step.

Parameters

- state0** [`Qobj`] Initial state of the evolution.
- t0** [double] Initial time of the evolution.
- floquet** [bool, optional {False}] Whether the initial state is in the floquet basis or laboratory basis.

step (`t`, *, `args=None`, `copy=True`, `floquet=False`)

Evolve the state to `t` and return the state as a `Qobj`.

Parameters

- t** [double] Time to evolve to, must be higher than the last call.
- copy** [bool, optional {True}] Whether to return a copy of the data or the data in the ODE solver.
- floquet** [bool, optional {False}] Whether to return the state in the floquet basis or laboratory basis.
- args** [dict, optional {None}] Not supported
- .. note::** The state must be initialized first by calling `start` or `run`. If `run` is called, `step` will continue from the last time and state obtained.

class FloquetBasis (`H`, `T`, `args=None`, `options=None`, `sparse=False`, `sort=True`, `precompute=None`)

Utility to compute floquet modes and states.

Attributes

- U** [`Propagator`] The propagator of the Hamiltonian over one period.
- evects** [`qutip.data.Data`] Matrix where each column is an initial Floquet mode.
- e_quasi** [`np.ndarray[float]`] The quasi energies of the Hamiltonian.

from_floquet_basis (`floquet_basis`, `t=0`)

Transform a ket or density matrix from the Floquet basis at time `t` to the lab basis.

Parameters

floquet_basis [Qobj, qutip.data.Data] Initial state in the Floquet basis at time t . May be either a ket or density matrix.

t [float [0]] The time at which to evaluate the Floquet states.

Returns

output [Qobj, qutip.data.Data] The state in the lab basis. The return type is the same as the type of the input state.

mode (t , $data=False$)

Calculate the Floquet modes at time t .

Parameters

t [float] The time for which to evaluate the Floquet mode.

data [bool [False]] Whether to return the states as a single data matrix or a list of ket states.

Returns

output [list[Qobj], qutip.data.Data] A list of Floquet states for the time t or the states as column in a single matrix.

state (t , $data=False$)

Evaluate the floquet states at time t .

Parameters

t [float] The time for which to evaluate the Floquet states.

data [bool [False]] Whether to return the states as a single data matrix or a list of ket states.

Returns

output [list[Qobj], qutip.data.Data] A list of Floquet states for the time t or the states as column in a single matrix.

to_floquet_basis (lab_basis , $t=0$)

Transform a ket or density matrix in the lab basis to the Floquet basis at time t .

Parameters

lab_basis [Qobj, qutip.data.Data] Initial state in the lab basis.

t [float [0]] The time at which to evaluate the Floquet states.

Returns

output [Qobj, qutip.data.Data] The state in the Floquet basis. The return type is the same as the type of the input state.

floquet_tensor (H , c_ops , $spectra_cb$, $T=0$, $w_th=0.0$, $kmax=5$, $nT=100$)

Construct a tensor that represents the master equation in the floquet basis.

Simplest RWA approximation [Grifoni et al, Phys.Rep. 304 229 (1998)]

Parameters

H [QobjEvo] Periodic Hamiltonian

T [float] The period of the time-dependence of the hamiltonian.

c_ops [list of qutip.qobj] list of collapse operators.

spectra_cb [list callback functions] List of callback functions that compute the noise power spectrum as a function of frequency for the collapse operators in c_ops .

w_th [float] The temperature in units of frequency.

kmax [int] The truncation of the number of sidebands (default 5).

Returns

output [array] The Floquet-Markov master equation tensor R .

fmmesolve (H , ρ_0 , $tlist$, $c_ops=None$, $e_ops=None$, $spectra_cb=None$, $T=0$, $w_th=0.0$, $args=None$, $options=None$)

Solve the dynamics for the system using the Floquet-Markov master equation.

Parameters

H [Qobj, QobjEvo, QobjEvo compatible format.] Periodic system Hamiltonian as QobjEvo. List of [Qobj, Coefficient] or callable that can be made into QobjEvo are also accepted.

rho0 / psi0 [qutip.Qobj] Initial density matrix or state vector (ket).

tlist [list / array] List of times for t .

c_ops [list of qutip.Qobj] List of collapse operators. Time dependent collapse operators are not supported.

e_ops [list of qutip.Qobj / callback function] List of operators for which to evaluate expectation values. The states are reverted to the lab basis before applying the

spectra_cb [list callback functions] List of callback functions that compute the noise power spectrum as a function of frequency for the collapse operators in c_ops .

T [float] The period of the time-dependence of the hamiltonian. The default value 'None' indicates that the 'tlist' spans a single period of the driving.

w_th [float] The temperature of the environment in units of frequency. For example, if the Hamiltonian written in units of 2pi GHz, and the temperature is given in K, use the following conversion:

$$\text{temperature} = 25\text{e-}3 \text{ \# unit K } h = 6.626\text{e-}34 \text{ kB} = 1.38\text{e-}23 \text{ args['w_th']} = \text{temperature} * (\text{kB} / h) * 2 * \pi * 1\text{e-}9$$

args [dictionary] Dictionary of parameters for time-dependent Hamiltonian

options [None / dict] Dictionary of options for the solver.

- **store_final_state** : bool Whether or not to store the final state of the evolution in the result class.
- **store_states** : bool, None Whether or not to store the state vectors or density matrices. On *None* the states will be saved if no expectation operators are given.
- **store_floquet_states** : bool Whether or not to store the density matrices in the floquet basis in `result.floquet_states`.
- **normalize_output** : bool Normalize output state to hide ODE numerical errors.
- **progress_bar** : str { 'text', 'enhanced', 'tqdm', '' } How to present the solver progress. 'tqdm' uses the python module of the same name and raise an error if not installed. Empty string or False will disable the bar.
- **progress_kwargs** : dict kwargs to pass to the progress_bar. Qutip's bars use *chunk_size*.
- **method** : str ["adams", "bdf", "lsoda", "dop853", "vern9", etc.] Which differential equation integration method to use.
- **atol, rtol** : float Absolute and relative tolerance of the ODE integrator.
- **nsteps** : Maximum number of (internally defined) steps allowed in one `tlist` step.
- **max_step** : float, 0 Maximum length of one internal step. When using pulses, it should be less than half the width of the thinnest pulse.

Other options could be supported depending on the integration method, see [Integrator](#).

Returns

result: `qutip.Result` An instance of the class `qutip.Result`, which contains the expectation values for the times specified by *tlist*, and/or the state density matrices corresponding to the times.

fsesolve (*H*, *psi0*, *tlist*, *e_ops*=None, *T*=0.0, *args*=None, *options*=None)

Solve the Schrodinger equation using the Floquet formalism.

Parameters

H [`Qobj`, `QobjEvo`, `QobjEvo` compatible format.] Periodic system Hamiltonian as `QobjEvo`. List of [`Qobj`, `Coefficient`] or callable that can be made into `QobjEvo` are also accepted.

psi0 [`qutip.Qobj`] Initial state vector (ket). If an operator is provided,

tlist [*list* / *array*] List of times for *t*.

e_ops [*list* of `qutip.Qobj` / *callback* function, optional] List of operators for which to evaluate expectation values. If this list is empty, the state vectors for each time in *tlist* will be returned instead of expectation values.

T [*float*, default=`tlist[-1]`] The period of the time-dependence of the hamiltonian.

args [*dictionary*, optional] Dictionary with variables required to evaluate H.

options [*dict*, optional] Options for the results.

- **store_final_state** : *bool* Whether or not to store the final state of the evolution in the result class.
- **store_states** : *bool*, *None* Whether or not to store the state vectors or density matrices. On *None* the states will be saved if no expectation operators are given.
- **normalize_output** : *bool* Normalize output state to hide ODE numerical errors.

Returns

output [`qutip.solver.Result`] An instance of the class `qutip.solver.Result`, which contains either an *array* of expectation values or an *array* of state vectors, for the times specified by *tlist*.

Stochastic Schrödinger Equation and Master Equation

general_stochastic (*state0*, *times*, *d1*, *d2*, *e_ops*=[], *m_ops*=[], *_safe_mode*=True, *len_d2*=1, *args*={}, ***kwargs*)

Solve stochastic general equation. Dispatch to specific solvers depending on the value of the *solver* keyword argument.

Parameters

state0 [`qutip.Qobj`] Initial state vector (ket) or density matrix as a vector.

times [*list* / *array*] List of times for *t*. Must be uniformly spaced.

d1 [*function*, *callable* class] Function representing the deterministic evolution of the system.

def d1(time (double), state (as a np.array vector)): return 1d np.array

d2 [*function*, *callable* class] Function representing the stochastic evolution of the system.

def d2(time (double), state (as a np.array vector)): return 2d np.array (N_sc_ops, len(state0))

len_d2 [*int*] Number of output vector produced by d2

e_ops [*list* of `qutip.Qobj`] single operator or list of operators for which to evaluate expectation values. Must be a superoperator if the state vector is a density matrix.

kwargs [dictionary] Optional keyword arguments. See `qutip.stochastic.StochasticSolverOptions`.

Returns

output: `qutip.solver.Result` An instance of the class `qutip.solver.Result`.

`photocurrent_mesolve` (*H*, *rho0*, *times*, *c_ops*=[], *sc_ops*=[], *e_ops*=[], *_safe_mode*=True, *args*={}, **kwargs)

Solve stochastic master equation using the photocurrent method.

Parameters

H [`qutip.Qobj`, or time dependent system.] System Hamiltonian. Can depend on time, see `StochasticSolverOptions` help for format.

rho0 [`qutip.Qobj`] Initial density matrix or state vector (ket).

times [list / array] List of times for *t*. Must be uniformly spaced.

c_ops [list of `qutip.Qobj`, or time dependent Qobjs.] Deterministic collapse operator which will contribute with a standard Lindblad type of dissipation. Can depend on time, see `StochasticSolverOptions` help for format.

sc_ops [list of `qutip.Qobj`, or time dependent Qobjs.] List of stochastic collapse operators. Each stochastic collapse operator will give a deterministic and stochastic contribution to the equation of motion according to how the d1 and d2 functions are defined. Can depend on time, see `StochasticSolverOptions` help for format.

e_ops [list of `qutip.Qobj` / callback function single] single operator or list of operators for which to evaluate expectation values.

kwargs [dictionary] Optional keyword arguments. See `qutip.stochastic.StochasticSolverOptions`.

Returns

output: `qutip.solver.Result` An instance of the class `qutip.solver.Result`.

`photocurrent_sesolve` (*H*, *psi0*, *times*, *sc_ops*=[], *e_ops*=[], *_safe_mode*=True, *args*={}, **kwargs)

Solve stochastic schrodinger equation using the photocurrent method.

Parameters

H [`qutip.Qobj`, or time dependent system.] System Hamiltonian. Can depend on time, see `StochasticSolverOptions` help for format.

psi0 [`qutip.Qobj`] Initial state vector (ket).

times [list / array] List of times for *t*. Must be uniformly spaced.

sc_ops [list of `qutip.Qobj`, or time dependent Qobjs.] List of stochastic collapse operators. Each stochastic collapse operator will give a deterministic and stochastic contribution to the equation of motion according to how the d1 and d2 functions are defined. Can depend on time, see `StochasticSolverOptions` help for format.

e_ops [list of `qutip.Qobj` / callback function single] single operator or list of operators for which to evaluate expectation values.

kwargs [dictionary] Optional keyword arguments. See `qutip.stochastic.StochasticSolverOptions`.

Returns

output: `qutip.solver.Result` An instance of the class `qutip.solver.Result`.

`smepdpsolve` (*H*, *rho0*, *times*, *c_ops*, *e_ops*, **kwargs)

A stochastic (piecewise deterministic process) PDP solver for density matrix evolution.

Parameters

H [qutip.Qobj] System Hamiltonian.

rho0 [qutip.Qobj] Initial density matrix.

times [list / array] List of times for t . Must be uniformly spaced.

c_ops [list of qutip.Qobj] Deterministic collapse operator which will contribute with a standard Lindblad type of dissipation.

sc_ops [list of qutip.Qobj] List of stochastic collapse operators. Each stochastic collapse operator will give a deterministic and stochastic contribution to the equation of motion according to how the d1 and d2 functions are defined.

e_ops [list of qutip.Qobj / callback function single] single operator or list of operators for which to evaluate expectation values.

kwargs [dictionary] Optional keyword arguments. See `qutip.stochastic.StochasticSolverOptions`.

Returns

output: qutip.solver.Result An instance of the class `qutip.solver.Result`.

smesolve (H , $\rho0$, $times$, $c_ops=[]$, $sc_ops=[]$, $e_ops=[]$, $_safe_mode=True$, $args={}$, $**kwargs$)
Solve stochastic master equation. Dispatch to specific solvers depending on the value of the *solver* keyword argument.

Parameters

H [qutip.Qobj, or time dependent system.] System Hamiltonian. Can depend on time, see `StochasticSolverOptions` help for format.

rho0 [qutip.Qobj] Initial density matrix or state vector (ket).

times [list / array] List of times for t . Must be uniformly spaced.

c_ops [list of qutip.Qobj, or time dependent Qobjs.] Deterministic collapse operator which will contribute with a standard Lindblad type of dissipation. Can depend on time, see `StochasticSolverOptions` help for format.

sc_ops [list of qutip.Qobj, or time dependent Qobjs.] List of stochastic collapse operators. Each stochastic collapse operator will give a deterministic and stochastic contribution to the equation of motion according to how the d1 and d2 functions are defined. Can depend on time, see `StochasticSolverOptions` help for format.

e_ops [list of qutip.Qobj] single operator or list of operators for which to evaluate expectation values.

kwargs [dictionary] Optional keyword arguments. See `qutip.stochastic.StochasticSolverOptions`.

Returns

output: qutip.solver.Result An instance of the class `qutip.solver.Result`.

ssepdpsolve (H , $\psi0$, $times$, c_ops , e_ops , $**kwargs$)
A stochastic (piecewise deterministic process) PDP solver for wavefunction evolution. For most purposes, use `qutip.mcsolve` instead for quantum trajectory simulations.

Parameters

H [qutip.Qobj] System Hamiltonian.

psi0 [qutip.Qobj] Initial state vector (ket).

times [list / array] List of times for t . Must be uniformly spaced.

c_ops [list of qutip.Qobj] Deterministic collapse operator which will contribute with a standard Lindblad type of dissipation.

e_ops [list of `qutip.Qobj` / callback function single] single operator or list of operators for which to evaluate expectation values.

kwargs [dictionary] Optional keyword arguments. See `qutip.stochastic.StochasticSolverOptions`.

Returns

output: `qutip.solver.Result` An instance of the class `qutip.solver.Result`.

ssesolve (*H*, *psi0*, *times*, *sc_ops*=[], *e_ops*=[], *_safe_mode*=True, *args*={}, **kwargs)
Solve stochastic schrodinger equation. Dispatch to specific solvers depending on the value of the *solver* keyword argument.

Parameters

H [`qutip.Qobj`, or time dependent system.] System Hamiltonian. Can depend on time, see `StochasticSolverOptions` help for format.

psi0 [`qutip.Qobj`] State vector (ket).

times [list / array] List of times for *t*. Must be uniformly spaced.

sc_ops [list of `qutip.Qobj`, or time dependent `Qobjs`.] List of stochastic collapse operators. Each stochastic collapse operator will give a deterministic and stochastic contribution to the equation of motion according to how the *d1* and *d2* functions are defined. Can depend on time, see `StochasticSolverOptions` help for format.

e_ops [list of `qutip.Qobj`] single operator or list of operators for which to evaluate expectation values.

kwargs [dictionary] Optional keyword arguments. See `qutip.stochastic.StochasticSolverOptions`.

Returns

output: `qutip.solver.Result` An instance of the class `qutip.solver.Result`.

stochastic_solvers ()

This function is purely a reference point for documenting the available stochastic solver methods, and takes no actions.

Notes

Available solvers for *ssesolve* and *smesolve*

euler-maruyama A simple generalization of the Euler method for ordinary differential equations to stochastic differential equations. Only solver which could take non-commuting *sc_ops*. *not tested*

- Order 0.5
- Code: 'euler-maruyama', 'euler' or 0.5

milstein An order 1.0 strong Taylor scheme. Better approximate numerical solution to stochastic differential equations. See eq. (2.9) of chapter 12.2 of [1].

- Order strong 1.0
- Code: 'milstein' or 1.0

milstein-imp An order 1.0 implicit strong Taylor scheme. Implicit Milstein scheme for the numerical simulation of stiff stochastic differential equations.

- Order strong 1.0
- Code: 'milstein-imp'

predictor-corrector Generalization of the trapezoidal method to stochastic differential equations. More stable than explicit methods. See eq. (5.4) of chapter 15.5 of [1].

- Order strong 0.5, weak 1.0
- Codes to only correct the stochastic part ($\alpha = 0$, $\eta = 1/2$): 'pred-corr', 'predictor-corrector' or 'pc-euler'
- Codes to correct both the stochastic and deterministic parts ($\alpha = 1/2$, $\eta = 1/2$): 'pc-euler-imp', 'pc-euler-2' or 'pred-corr-2'

platen Explicit scheme, creates the Milstein using finite differences instead of analytic derivatives. Also contains some higher order terms, thus converges better than Milstein while staying strong order 1.0. Does not require derivatives, therefore usable by *general_stochastic*. See eq. (7.47) of chapter 7 of [2].

- Order strong 1.0, weak 2.0
- Code: 'platen', 'platen1' or 'explicit1'

rouchon Scheme keeping the positivity of the density matrix (*smesolve* only). See eq. (4) with $\eta = 1$ of [3].

- Order strong 1.0?
- Code: 'rouchon' or 'Rouchon'

taylor1.5 Order 1.5 strong Taylor scheme. Solver with more terms of the Ito-Taylor expansion. Default solver for *smesolve* and *ssesolve*. See eq. (4.6) of chapter 10.4 of [1].

- Order strong 1.5
- Code: 'taylor1.5', 'taylor15', 1.5, or None

taylor1.5-imp Order 1.5 implicit strong Taylor scheme. Implicit Taylor 1.5 ($\alpha = 1/2$, β doesn't matter). See eq. (2.18) of chapter 12.2 of [1].

- Order strong 1.5
- Code: 'taylor1.5-imp' or 'taylor15-imp'

explicit1.5 Explicit order 1.5 strong schemes. Reproduce the order 1.5 strong Taylor scheme using finite difference instead of derivatives. Slower than *taylor15* but usable by *general_stochastic*. See eq. (2.13) of chapter 11.2 of [1].

- Order strong 1.5
- Code: 'explicit1.5', 'explicit15' or 'platen15'

taylor2.0 Order 2 strong Taylor scheme. Solver with more terms of the Stratonovich expansion. See eq. (5.2) of chapter 10.5 of [1].

- Order strong 2.0
- Code: 'taylor2.0', 'taylor20' or 2.0

All solvers, except *taylor2.0*, are usable in both *smesolve* and *ssesolve* and for both heterodyne and homodyne. *taylor2.0* only works for 1 stochastic operator independent of time with the homodyne method. *general_stochastic* only accepts the derivative-free solvers: 'euler', 'platen' and 'explicit1.5'.

Available solvers for *photocurrent_sesolve* and *photocurrent_mesolve* Photocurrent use ordinary differential equations between stochastic “jump/collapse”.

euler Euler method for ordinary differential equations between jumps. Only one jump per time interval. Default solver. See eqs. (4.19) and (4.4) of chapter 4 of [4].

- Order 1.0
- Code: 'euler'

predictor-corrector predictor-corrector method (PECE) for ordinary differential equations. Uses the Poisson distribution to obtain the number of jumps at each timestep.

- Order 2.0
- Code: 'pred-corr'

References

[1], [2], [3], [4]

Hierarchical Equations of Motion

This module provides solvers for system-bath evolution using the HEOM (hierarchy equations of motion).

See https://en.wikipedia.org/wiki/Hierarchical_equations_of_motion for a very basic introduction to the technique.

The implementation is derived from the BoFiN library (see <https://github.com/tehruhn/bofin>) which was itself derived from an earlier implementation in QuTiP itself.

For backwards compatibility with QuTiP 4.6 and below, a new version of HSolverDL (the Drude-Lorentz specific HEOM solver) is provided. It is implemented on top of the new HEOMSolver but should largely be a drop-in replacement for the old HSolverDL.

heomsolve (*H, bath, max_depth, state0, tlist, *, e_ops=None, args=None, options=None*)

Hierarchical Equations of Motion (HEOM) solver that supports multiple baths.

The baths must be all either bosonic or fermionic baths.

If you need to run many evolutions of the same system and bath, consider using *HEOMSolver* directly to avoid having to continually reconstruct the equation hierarchy for every evolution.

Parameters

H [Qobj, QobjEvo] Possibly time-dependent system Liouvillian or Hamiltonian as a Qobj or QobjEvo. list of [Qobj, Coefficient] or callable that can be made into QobjEvo are also accepted.

bath [Bath or list of Bath] A *Bath* containing the exponents of the expansion of the bath correlation function and their associated coefficients and coupling operators, or a list of baths.

If multiple baths are given, they must all be either fermionic or bosonic baths.

max_depth [int] The maximum depth of the heirarchy (i.e. the maximum number of bath exponent “excitations” to retain).

state0 [Qobj or *HierarchyADOsState* or array-like] If rho0 is a Qobj the it is the initial state of the system (i.e. a Qobj density matrix).

If it is a *HierarchyADOsState* or array-like, then rho0 gives the initial state of all ADOs.

Usually the state of the ADOs would be determine from a previous call to `.run(...)` with the solver results option `store_ados` set to True. For example, `result = solver.run(...)` could be followed by `solver.run(result.ado_states[-1], tlist)`.

If a numpy array-like is passed its shape must be `(number_of_ados, n, n)` where `(n, n)` is the system shape (i.e. shape of the system density matrix) and the ADOs must be in the same order as in `.ados.labels`.

tlist [list] An ordered list of times at which to return the value of the state.

e_ops [Qobj / QobjEvo / callable / list / dict / None, optional] A list or dictionary of operators as Qobj, QobjEvo and/or callable functions (they can be mixed) or a single operator or callable function. For an operator `op`, the result will be computed using `(state * op).tr()` and the state at each time `t`. For callable functions, `f`, the result is computed using `f(t, ado_state)`. The values are stored in the `expect` and `e_data` attributes of the result (see the return section below).

args [dict, optional {None}] Change the `args` of the RHS for the evolution.

options [dict, optional {None}] Generic solver options.

- `store_final_state` : bool Whether or not to store the final state of the evolution in the result class.
- `store_states` : bool, None Whether or not to store the state vectors or density matrices. On *None* the states will be saved if no expectation operators are given.
- `store_ados` : bool {False, True} Whether or not to store the HEOM ADOs.
- `normalize_output` : bool Normalize output state to hide ODE numerical errors.
- `progress_bar` : str {'text', 'enhanced', 'tqdm', ''} How to present the solver progress. 'tqdm' uses the python module of the same name and raise an error if not installed. Empty string or False will disable the bar.
- `progress_kwargs` : dict kwargs to pass to the `progress_bar`. Qutip's bars use `chunk_size`.
- `state_data_type`: str {'dense'} Name of the data type of the state used during the ODE evolution. Use an empty string to keep the input state type. Many integrator can only work with *Dense*.
- `method` : str ["adams", "bdf", "lsoda", "dop853", "vern9", etc.] Which differential equation integration method to use.
- `atol, rtol` : float Absolute and relative tolerance of the ODE integrator.
- `nsteps` : Maximum number of (internally defined) steps allowed in one `tlist` step.
- `max_step` : float, 0 Maximum length of one internal step. When using pulses, it should be less than half the width of the thinnest pulse.

Returns

HEOMResult The results of the simulation run, with the following important attributes:

- `times`: the times `t` (i.e. the `tlist`).
- `states`: the system state at each time `t` (only available if `e_ops` was *None* or if the solver option `store_states` was set to *True*).
- `ado_states`: the full ADO state at each time (only available if the results option `ado_return` was set to *True*). Each element is an instance of *HierarchyADOsState*. The state of a particular ADO may be extracted from `result.ado_states[i]` by calling *extract*.
- `expect`: a list containing the values of each `e_ops` at time `t`.
- `e_data`: a dictionary containing the values of each `e_ops` at time `t`. The keys are those given by `e_ops` if it was a dict, otherwise they are the indexes of the supplied `e_ops`.

See *HEOMResult* and *Result* for the complete list of attributes.

Correlation Functions

coherence_function_g1 (*H, state0, taulist, c_ops, a_op, solver='me', args={}, options={}*)

Calculate the normalized first-order quantum coherence function:

$$g^{(1)}(\tau) = \frac{\langle A^\dagger(\tau)A(0) \rangle}{\sqrt{\langle A^\dagger(\tau)A(\tau) \rangle \langle A^\dagger(0)A(0) \rangle}}$$

using the quantum regression theorem and the evolution solver indicated by the *solver* parameter.

Parameters

H [Qobj, QobjEvo] System Hamiltonian, may be time-dependent for solver choice of *me*.

state0 [Qobj] Initial state density matrix $\rho(t_0)$ or state vector $\psi(t_0)$. If 'state0' is 'None', then the steady state will be used as the initial state. The 'steady-state' is only implemented if *c_ops* are provided and the Hamiltonian is constant.

taulist [array_like] List of times for τ . *taulist* must be positive and contain the element 0.

c_ops [list of {Qobj, QobjEvo}] List of collapse operators

a_op [Qobj, QobjEvo] Operator A.

solver [str {'me', 'es'}] Choice of solver, *me* for master-equation, and *es* for exponential series. *es* is equivalent to *me* with *options*={"method": "diag"}.

options [dict, optional] Options for the solver. Only used with *me* solver.

Returns

g1, G1 [tuple] The normalized and unnormalized second-order coherence function.

coherence_function_g2 (*H, state0, taulist, c_ops, a_op, solver='me', args={}, options={}*)

Calculate the normalized second-order quantum coherence function:

$$g^{(2)}(\tau) = \frac{\langle A^\dagger(0)A^\dagger(\tau)A(\tau)A(0) \rangle}{\langle A^\dagger(\tau)A(\tau) \rangle \langle A^\dagger(0)A(0) \rangle}$$

using the quantum regression theorem and the evolution solver indicated by the *solver* parameter.

Parameters

H [Qobj, QobjEvo] System Hamiltonian, may be time-dependent for solver choice of *me*.

state0 [Qobj] Initial state density matrix $\rho(t_0)$ or state vector $\psi(t_0)$. If 'state0' is 'None', then the steady state will be used as the initial state. The 'steady-state' is only implemented if *c_ops* are provided and the Hamiltonian is constant.

taulist [array_like] List of times for τ . *taulist* must be positive and contain the element 0.

c_ops [list] List of collapse operators, may be time-dependent for solver choice of *me*.

a_op [Qobj] Operator A.

args [dict] Dictionary of arguments to be passed to solver.

solver [str {'me', 'es'}] Choice of solver, *me* for master-equation, and *es* for exponential series. *es* is equivalent to *me* with *options*={"method": "diag"}.

options [dict, optional] Options for the solver. Only used with *me* solver.

Returns

g2, G2 [tuple] The normalized and unnormalized second-order coherence function.

correlation_2op_1t (*H*, *state0*, *taulist*, *c_ops*, *a_op*, *b_op*, *solver*='me', *reverse*=False, *args*={}, *options*={})

Calculate the two-operator one-time correlation function: $\langle A(\tau)B(0) \rangle$ along one time axis using the quantum regression theorem and the evolution solver indicated by the *solver* parameter.

Parameters

H [Qobj, QobjEvo] System Hamiltonian, may be time-dependent for solver choice of *me*.

state0 [Qobj] Initial state density matrix $\rho(t_0)$ or state vector $\psi(t_0)$. If 'state0' is 'None', then the steady state will be used as the initial state. The 'steady-state' is only implemented if *c_ops* are provided and the Hamiltonian is constant.

taulist [array_like] List of times for τ . *taulist* must be positive and contain the element 0.

c_ops [list of {Qobj, QobjEvo}] List of collapse operators

a_op [Qobj, QobjEvo] Operator A.

b_op [Qobj, QobjEvo] Operator B.

reverse [bool {False}] If *True*, calculate $\langle A(t)B(t + \tau) \rangle$ instead of $\langle A(t + \tau)B(t) \rangle$.

solver [str {'me', 'es'}] Choice of solver, *me* for master-equation, and *es* for exponential series. *es* is equivalent to *me* with *options*={"method": "diag"}.

options [dict, optional] Options for the solver. Only used with *me* solver.

Returns

corr_vec [ndarray] An array of correlation values for the times specified by *taulist*.

See also:

[*correlation_3op*](#) Similar function supporting various solver types.

References

See, Gardiner, Quantum Noise, Section 5.2.

correlation_2op_2t (*H*, *state0*, *tlist*, *taulist*, *c_ops*, *a_op*, *b_op*, *solver*='me', *reverse*=False, *args*={}, *options*={})

Calculate the two-operator two-time correlation function: $\langle A(t + \tau)B(t) \rangle$ along two time axes using the quantum regression theorem and the evolution solver indicated by the *solver* parameter.

Parameters

H [Qobj, QobjEvo] System Hamiltonian, may be time-dependent for solver choice of *me*.

state0 [Qobj] Initial state density matrix $\rho(t_0)$ or state vector $\psi(t_0)$. If 'state0' is 'None', then the steady state will be used as the initial state. The 'steady-state' is only implemented if *c_ops* are provided and the Hamiltonian is constant.

tlist [array_like] List of times for t . *tlist* must be positive and contain the element 0. When taking steady-steady correlations only one *tlist* value is necessary, i.e. when $t \rightarrow \infty$. If *tlist* is None, *tlist*=[0] is assumed.

taulist [array_like] List of times for τ . *taulist* must be positive and contain the element 0.

c_ops [list of {Qobj, QobjEvo}] List of collapse operators

a_op [Qobj, QobjEvo] Operator A.

b_op [Qobj, QobjEvo] Operator B.

reverse [bool {False}] If *True*, calculate $\langle A(t)B(t + \tau) \rangle$ instead of $\langle A(t + \tau)B(t) \rangle$.

solver [str {'me', 'es'}] Choice of solver, *me* for master-equation, and *es* for exponential series. *es* is equivalent to *me* with `options={"method": "diag"}`.

options [dict, optional] Options for the solver. Only used with *me* solver.

Returns

corr_mat [ndarray] An 2-dimensional array (matrix) of correlation values for the times specified by *tlist* (first index) and *taulist* (second index).

See also:

[*correlation_3op*](#) Similar function supporting various solver types.

References

See, Gardiner, Quantum Noise, Section 5.2.

correlation_3op (*solver*, *state0*, *tlist*, *taulist*, *A=None*, *B=None*, *C=None*)

Calculate the three-operator two-time correlation function:

$$\langle A(t)B(t+\tau)C(t) \rangle.$$

from an open system Solver.

Note: it is not possible to calculate a physically meaningful correlation where $\tau < 0$.

Parameters

solver [MESolver, BRSolver] Qutip solver for an open system.

state0 [Qobj] Initial state density matrix $\rho(t_0)$ or state vector $\psi(t_0)$.

tlist [array_like] List of times for *t*. *tlist* must be positive and contain the element 0.

taulist [array_like] List of times for τ . *taulist* must be positive and contain the element 0.

A, B, C: :class:`Qobj`, :class:`QobjEvo`, optional, default=None Operators *A*, *B*, *C* from the equation $\langle A(t)B(t+\tau)C(t) \rangle$ in the Schrodinger picture. They do not need to be all provided. For example, if *A* is not provided, $\langle B(t+\tau)C(t) \rangle$ is computed.

Returns

corr_mat [array] An 2-dimensional array (matrix) of correlation values for the times specified by *tlist* (first index) and *taulist* (second index). If *tlist* is *None*, then a 1-dimensional array of correlation values is returned instead.

correlation_3op_1t (*H*, *state0*, *taulist*, *c_ops*, *a_op*, *b_op*, *c_op*, *solver='me'*, *args={}*, *options={}*)

Calculate the three-operator two-time correlation function: $\langle A(0)B(\tau)C(0) \rangle$ along one time axis using the quantum regression theorem and the evolution solver indicated by the *solver* parameter.

Note: it is not possible to calculate a physically meaningful correlation of this form where $\tau < 0$.

Parameters

H [Qobj, QobjEvo] System Hamiltonian, may be time-dependent for solver choice of *me*.

state0 [Qobj] Initial state density matrix $\rho(t_0)$ or state vector $\psi(t_0)$. If 'state0' is 'None', then the steady state will be used as the initial state. The 'steady-state' is only implemented if *c_ops* are provided and the Hamiltonian is constant.

taulist [array_like] List of times for τ . *taulist* must be positive and contain the element 0.

c_ops [list of {Qobj, QobjEvo}] List of collapse operators

a_op [Qobj, QobjEvo] Operator *A*.

b_op [Qobj, QobjEvo] Operator *B*.

c_op [Qobj, QobjEvo] Operator C.

solver [str {'me', 'es'}] Choice of solver, *me* for master-equation, and *es* for exponential series. *es* is equivalent to *me* with `options={"method": "diag"}`.

options [dict, optional] Options for the solver. Only used with *me* solver.

Returns

corr_vec [array] An array of correlation values for the times specified by *taulist*.

See also:

[*correlation_3op*](#) Similar function supporting various solver types.

References

See, Gardiner, Quantum Noise, Section 5.2.

correlation_3op_2t (*H*, *state0*, *tlist*, *taulist*, *c_ops*, *a_op*, *b_op*, *c_op*, *solver*='me', *args*={}, *options*={})

Calculate the three-operator two-time correlation function: $\langle A(t)B(t+\tau)C(t) \rangle$ along two time axes using the quantum regression theorem and the evolution solver indicated by the *solver* parameter.

Note: it is not possible to calculate a physically meaningful correlation of this form where $\tau < 0$.

Parameters

H [Qobj, QobjEvo] System Hamiltonian, may be time-dependent for solver choice of *me*.

state0 [Qobj] Initial state density matrix $\rho(t_0)$ or state vector $\psi(t_0)$. If 'state0' is 'None', then the steady state will be used as the initial state. The 'steady-state' is only implemented if *c_ops* are provided and the Hamiltonian is constant.

tlist [array_like] List of times for *t*. *tlist* must be positive and contain the element 0. When taking steady-steady correlations only one *tlist* value is necessary, i.e. when $t \rightarrow \infty$. If *tlist* is None, *tlist*=[0] is assumed.

taulist [array_like] List of times for τ . *taulist* must be positive and contain the element 0.

c_ops [list of {Qobj, QobjEvo}] List of collapse operators

a_op [Qobj, QobjEvo] Operator A.

b_op [Qobj, QobjEvo] Operator B.

c_op [Qobj, QobjEvo] Operator C.

solver [str {'me', 'es'}] Choice of solver, *me* for master-equation, and *es* for exponential series. *es* is equivalent to *me* with `options={"method": "diag"}`.

options [dict, optional] Options for the solver. Only used with *me* solver.

Returns

corr_mat [array] An 2-dimensional array (matrix) of correlation values for the times specified by *tlist* (first index) and *taulist* (second index).

See also:

[*correlation_3op*](#) Similar function supporting various solver types.

References

See, Gardiner, Quantum Noise, Section 5.2.

spectrum (*H*, *wlist*, *c_ops*, *a_op*, *b_op*, *solver*='es')

Calculate the spectrum of the correlation function $\lim_{t \rightarrow \infty} \langle A(t + \tau) B(t) \rangle$, i.e., the Fourier transform of the correlation function:

$$S(\omega) = \int_{-\infty}^{\infty} \lim_{t \rightarrow \infty} \langle A(t + \tau) B(t) \rangle e^{-i\omega\tau} d\tau.$$

using the solver indicated by the *solver* parameter. Note: this spectrum is only defined for stationary statistics (uses steady state rho0)

Parameters

H [qutip.qobj] system Hamiltonian.

wlist [array_like] List of frequencies for ω .

c_ops [list] List of collapse operators.

a_op [Qobj] Operator A.

b_op [Qobj] Operator B.

solver [str] Choice of solver (*es* for exponential series and *pi* for psuedo-inverse, *solve* for generic solver).

Returns

spectrum [array] An array with spectrum $S(\omega)$ for the frequencies specified in *wlist*.

spectrum_correlation_fft (*tlist*, *y*, *inverse*=False)

Calculate the power spectrum corresponding to a two-time correlation function using FFT.

Parameters

tlist [array_like] list/array of times *t* which the correlation function is given.

y [array_like] list/array of correlations corresponding to time delays *t*.

inverse: boolean boolean parameter for using a positive exponent in the Fourier Transform instead. Default is False.

Returns

w, S [tuple] Returns an array of angular frequencies 'w' and the corresponding two-sided power spectrum 'S(w)'.

Steady-state Solvers

pseudo_inverse (*L*, *rhoss*=None, *w*=None, *method*='splu', *, *use_rcm*=False, **kwargs)

Compute the pseudo inverse for a Liouvillian superoperator, optionally given its steady state density matrix (which will be computed if not given).

Parameters

L [Qobj] A Liouvillian superoperator for which to compute the pseudo inverse.

rhoss [Qobj] A steadystate density matrix as Qobj instance, for the Liouvillian superoperator L.

w [double] frequency at which to evaluate pseudo-inverse. Can be zero for dense systems and large sparse systems. Small sparse systems can fail for zero frequencies.

sparse [bool] Flag that indicate whether to use sparse or dense matrix methods when computing the pseudo inverse.

method [string] Method used to compute matrix inverse. Choice are ‘pinv’ to use scipy’s function of the same name, or a linear system solver. Default supported solver are:

- “solve”, “lstsq” dense solver from numpy.linalg
- “spsolve”, “gmres”, “lgmres”, “bicgstab”, “splu” sparse solver from scipy.sparse.linalg
- “mkl_spsolve”, sparse solver by mkl.

Extension to qutip, such as qutip-tensorflow, can use come with their own solver. When use these data backends, see the corresponding libraries `linalg` for available solver.

kwargs [dictionary] Additional keyword arguments for setting parameters for solver methods.

Returns

R [Qobj] Returns a Qobj instance representing the pseudo inverse of L .

Note: In general the inverse of a sparse matrix will be dense. If you are applying the inverse to a density matrix then it is better to cast the problem as an $Ax=b$ type problem where the explicit calculation of the inverse is not required. See page 67 of “Electrons in nanostructures” C. Flindt, PhD Thesis available online: https://orbit.dtu.dk/fedora/objects/orbit:82314/datastreams/file_4732600/content

Note also that the definition of the pseudo-inverse herein is different from numpy’s `pinv()` alone, as it includes pre and post projection onto the subspace defined by the projector Q .

steadystate (A , $c_ops=[]$, $*$, $method='direct'$, $solver=None$, $**kwargs$)

Calculates the steady state for quantum evolution subject to the supplied Hamiltonian or Liouvillian operator and (if given a Hamiltonian) a list of collapse operators.

If the user passes a Hamiltonian then it, along with the list of collapse operators, will be converted into a Liouvillian operator in Lindblad form.

Parameters

A [Qobj] A Hamiltonian or Liouvillian operator.

c_op_list [list] A list of collapse operators.

method [str, default='direct'] The allowed methods are composed of 2 parts, the steadystate method: - “direct”: Solving $L(\rho_{ss}) = 0$ - “eigen”: Eigenvalue problem - “svd”: Singular value decomposition - “power”: Inverse-power method

solver [str, default=None] ‘direct’ and ‘power’ methods only. Solver to use when solving the $L(\rho_{ss}) = 0$ equation. Default supported solver are:

- “solve”, “lstsq” dense solver from numpy.linalg
- “spsolve”, “gmres”, “lgmres”, “bicgstab” sparse solver from scipy.sparse.linalg
- “mkl_spsolve” sparse solver by mkl.

Extension to qutip, such as qutip-tensorflow, can use come with their own solver. When A and c_ops use these data backends, see the corresponding libraries `linalg` for available solver.

Extra options for these solver can be passed in $**kw$.

use_rcm [bool, default False] Use reverse Cuthill-McKee reordering to minimize fill-in in the LU factorization of the Liouvillian. Used with ‘direct’ or ‘power’ method.

use_wbm [bool, default False] Use Weighted Bipartite Matching reordering to make the Liouvillian diagonally dominant. This is useful for iterative preconditioners only. Used with ‘direct’ or ‘power’ method.

weight [float, optional] Sets the size of the elements used for adding the unity trace condition to the linear solvers. This is set to the average abs value of the Liouvillian elements if not specified by the user. Used with ‘direct’ method.

power_tol [float, default 1e-12] Tolerance for the solution when using the ‘power’ method.

power_maxiter [int, default 10] Maximum number of iteration to use when looking for a solution when using the ‘power’ method.

power_eps: double, default 1e-15 Small weight used in the “power” method.

sparse: bool Whether to use the sparse eigen solver with the “eigen” method (default sparse). With “direct” and “power” method, when the solver is not specified, it is used to set whether “solve” or “spsolve” is used as default solver.

****kwargs** : Extra options to pass to the linear system solver. See the documentation of the used solver in `numpy.linalg` or `scipy.sparse.linalg` to see what extra arguments are supported.

Returns

dm [qobj] Steady state density matrix.

info [dict, optional] Dictionary containing solver-specific information about the solution.

Note: The SVD method works only for dense operators (i.e. small systems).

steadystate_floquet (*H_0, c_ops, Op_t, w_d=1.0, n_it=3, sparse=False, solver=None, **kwargs*)

Calculates the effective steady state for a driven system with a time-dependent cosinusoidal term:

$$\hat{\mathcal{H}}(t) = \hat{H}_0 + \hat{O} \cos(\omega_d t)$$

Parameters

H_0 [Qobj] A Hamiltonian or Liouvillian operator.

c_ops [list] A list of collapse operators.

Op_t [Qobj] The the interaction operator which is multiplied by the cosine

w_d [float, default 1.0] The frequency of the drive

n_it [int, default 3] The number of iterations for the solver

sparse [bool, default False] Solve for the steady state using sparse algorithms.

solver [str, default=None] Solver to use when solving the linear system. Default supported solver are:

- “solve”, “lstsq” dense solver from `numpy.linalg`
- “spsolve”, “gmres”, “lgmres”, “bicgstab” sparse solver from `scipy.sparse.linalg`
- “mkl_spsolve” sparse solver by mkl.

Extensions to qutip, such as qutip-tensorflow, may provide their own solvers. When `H_0` and `c_ops` use these data backends, see their documentation for the names and details of additional solvers they may provide.

****kwargs**: Extra options to pass to the linear system solver. See the documentation of the used solver in `numpy.linalg` or `scipy.sparse.linalg` to see what extra arguments are supported.

Returns

dm [qobj] Steady state density matrix.

Note: See: Sze Meng Tan, <https://copilot.caltech.edu/documents/16743/qousersguide.pdf>, Section (10.16)

Propagators

propagator (*H*, *t*, *c_ops*=(), *args*=None, *options*=None, ***kwargs*)

Calculate the propagator $U(t)$ for the density matrix or wave function such that $\psi(t) = U(t)\psi(0)$ or $\rho_{vec}(t) = U(t)\rho_{vec}(0)$ where ρ_{vec} is the vector representation of the density matrix.

Parameters

H [Qobj, QobjEvo, QobjEvo compatible format.] Possibly time-dependent system Liouvillian or Hamiltonian as a Qobj or QobjEvo. list of [Qobj, Coefficient] or callable that can be made into QobjEvo are also accepted.

t [float or array-like] Time or list of times for which to evaluate the propagator.

c_ops [list, optional] List of Qobj or QobjEvo collapse operators.

args [dictionary, optional] Parameters to callback functions for time-dependent Hamiltonians and collapse operators.

options [dict, optional] Options for the solver.

****kwargs** : Extra parameters to use when creating the QobjEvo from a list format H.

Returns

U [qobj, list] Instance representing the propagator(s) $U(t)$. Return a single Qobj when *t* is a number or a list when *t* is a list.

propagator_steadystate (*U*)

Find the steady state for successive applications of the propagator U .

Parameters

U [qobj] Operator representing the propagator.

Returns

a [qobj] Instance representing the steady-state density matrix.

Scattering in Quantum Optical Systems

Photon scattering in quantum optical systems

This module includes a collection of functions for numerically computing photon scattering in driven arbitrary systems coupled to some configuration of output waveguides. The implementation of these functions closely follows the mathematical treatment given in K.A. Fischer, et. al., Scattering of Coherent Pulses from Quantum Optical Systems (2017, arXiv:1710.02875).

scattering_probability (*H*, *psi0*, *n_emissions*, *c_ops*, *tlist*, *system_zero_state*=None, *construct_effective_hamiltonian*=True)

Compute the integrated probability of scattering *n* photons in an arbitrary system. This function accepts a nonlinearly spaced array of times.

Parameters

H [:class: qutip.Qobj or list] System-waveguide(s) Hamiltonian or effective Hamiltonian in Qobj or list-callback format. If *construct_effective_hamiltonian* is not specified, an effective Hamiltonian is constructed from *H* and *c_ops*.

psi0 [:class: qutip.Qobj] Initial state density matrix $\rho(t_0)$ or state vector $\psi(t_0)$.

- n_emissions** [int] Number of photons emitted by the system (into any combination of waveguides).
- c_ops** [list] List of collapse operators for each waveguide; these are assumed to include spontaneous decay rates, e.g. $\sigma = \sqrt{\gamma} \cdot a$.
- tlist** [array_like] List of times for τ_i . tlist should contain 0 and exceed the pulse duration / temporal region of interest; tlist need not be linearly spaced.
- system_zero_state** [:class: qutip.Qobj] State representing zero excitations in the system. Defaults to *basis(systemDims, 0)*.
- construct_effective_hamiltonian** [bool] Whether an effective Hamiltonian should be constructed from H and c_ops: $H_{eff} = H - \frac{i}{2} \sum_n \sigma_n^\dagger \sigma_n$ Default: True.

Returns

- scattering_prob** [float] The probability of scattering n photons from the system over the time range specified.

temporal_basis_vector (*waveguide_emission_indices, n_time_bins, n_emissions=None*)
Generate a temporal basis vector for emissions at specified time bins into specified waveguides.

Parameters

- waveguide_emission_indices** [list or tuple] List of indices where photon emission occurs for each waveguide, e.g. [[t1_wg1], [t1_wg2, t2_wg2], [], [t1_wg4, t2_wg4, t3_wg4]].
- n_time_bins** [int] Number of time bins; the range over which each index can vary.

Returns

- temporal_basis_vector** [:class: qutip.Qobj] A basis vector representing photon scattering at the specified indices. If there are W waveguides, T times, and N photon emissions, then the basis vector has dimensionality $(W \cdot T)^N$.

temporal_scattered_state (*H, psi0, n_emissions, c_ops, tlist, system_zero_state=None, construct_effective_hamiltonian=True*)
Compute the scattered n-photon state projected onto the temporal basis.

Parameters

- H** [:class: qutip.Qobj or list] System-waveguide(s) Hamiltonian or effective Hamiltonian in Qobj or list-callback format. If construct_effective_hamiltonian is not specified, an effective Hamiltonian is constructed from *H* and *c_ops*.
- psi0** [:class: qutip.Qobj] Initial state density matrix $\rho(t_0)$ or state vector $\psi(t_0)$.
- n_emissions** [int] Number of photon emissions to calculate.
- c_ops** [list] List of collapse operators for each waveguide; these are assumed to include spontaneous decay rates, e.g. $\sigma = \sqrt{\gamma} \cdot a$
- tlist** [array_like] List of times for τ_i . tlist should contain 0 and exceed the pulse duration / temporal region of interest.
- system_zero_state** [:class: qutip.Qobj] State representing zero excitations in the system. Defaults to $\psi(t_0)$
- construct_effective_hamiltonian** [bool] Whether an effective Hamiltonian should be constructed from H and c_ops: $H_{eff} = H - \frac{i}{2} \sum_n \sigma_n^\dagger \sigma_n$ Default: True.

Returns

- phi_n** [:class: qutip.Qobj] The scattered bath state projected onto the temporal basis given by tlist. If there are W waveguides, T times, and N photon emissions, then the state is a tensor product state with dimensionality $T^{(W \cdot N)}$.

Permutational Invariance

Permutational Invariant Quantum Solver (PIQS)

This module calculates the Liouvillian for the dynamics of ensembles of identical two-level systems (TLS) in the presence of local and collective processes by exploiting permutational symmetry and using the Dicke basis. It also allows to characterize nonlinear functions of the density matrix.

am(*j, m*)

Calculate the operator **am** used later.

The action of **ap** is given by: $J_-|j, m\rangle = A_-(jm)|j, m-1\rangle$

Parameters

j: float The value for *j*.

m: float The value for *m*.

Returns

a_minus: float The value of a_- .

ap(*j, m*)

Calculate the coefficient **ap** by applying $J_+|j, m\rangle$.

The action of **ap** is given by: $J_+|j, m\rangle = A_+(j, m)|j, m+1\rangle$

Parameters

j, m: float The value for *j* and *m* in the dicke basis $|j, m\rangle$.

Returns

a_plus: float The value of a_+ .

block_matrix(*N, elements='ones'*)

Construct the block-diagonal matrix for the Dicke basis.

Parameters

N [int] Number of two-level systems.

elements [str] {'ones' (default), 'degeneracy' }

Returns

block_matr [ndarray] A 2D block-diagonal matrix with dimension (nds,nds), where nds is the number of Dicke states for *N* two-level systems. Filled with ones or the value of degeneracy at each matrix element.

collapse_uncoupled(*N, emission=0.0, dephasing=0.0, pumping=0.0, collective_emission=0.0, collective_dephasing=0.0, collective_pumping=0.0*)

Create the collapse operators (**c_ops**) of the Lindbladian in the uncoupled basis

These operators are in the uncoupled basis of the two-level system (TLS) SU(2) Pauli matrices.

Parameters

N: int The number of two-level systems.

emission: float Incoherent emission coefficient (also nonradiative emission). default: 0.0

dephasing: float Local dephasing coefficient. default: 0.0

pumping: float Incoherent pumping coefficient. default: 0.0

collective_emission: float Collective (superradiant) emission coefficient. default: 0.0

collective_pumping: float Collective pumping coefficient. default: 0.0

collective_dephasing: float Collective dephasing coefficient. default: 0.0

Returns

c_ops: list The list of collapse operators as *qutip.Qobj* for the system.

Notes

The collapse operator list can be given to *qutip.mesolve*. Notice that the operators are placed in a Hilbert space of dimension 2^N . Thus the method is suitable only for small N (of the order of 10).

css (*N*, *x*=0.7071067811865475, *y*=0.7071067811865475, *basis*='dicke', *coordinates*='cartesian')

Generate the density matrix of the Coherent Spin State (CSS).

It can be defined as, $|CSS\rangle = \prod_i^N (a|1\rangle_i + b|0\rangle_i)$ with $a = \sin(\frac{\theta}{2})$, $b = e^{i\phi} \cos(\frac{\theta}{2})$. The default basis is that of Dicke space $|j, m\rangle\langle j, m'|$. The default state is the symmetric CSS, $|CSS\rangle = |+\rangle$.

Parameters

N: int The number of two-level systems.

x, y: float The coefficients of the CSS state.

basis: str The basis to use. Either “dicke” or “uncoupled”.

coordinates: str Either “cartesian” or “polar”. If polar then the coefficients are constructed as $\sin(x/2)$, $\cos(x/2)e^{iy}$.

Returns

rho: :class: qutip.Qobj The CSS state density matrix.

dicke (*N*, *j*, *m*)

Generate a Dicke state as a pure density matrix in the Dicke basis.

For instance, the superradiant state given by $|j, m\rangle = |1, 0\rangle$ for $N = 2$, and the state is represented as a density matrix of size (nds, nds) or (4, 4), with the (1, 1) element set to 1.

Parameters

N: int The number of two-level systems.

j: float The eigenvalue j of the Dicke state (j, m).

m: float The eigenvalue m of the Dicke state (j, m).

Returns

rho: :class: qutip.Qobj The density matrix.

dicke_basis (*N*, *jmm1*=None)

Initialize the density matrix of a Dicke state for several (j, m, m1).

This function can be used to build arbitrary states in the Dicke basis $|j, m\rangle\langle j, m'|$. We create coefficients for each (j, m, m1) value in the dictionary *jmm1*. The mapping for the (i, k) index of the density matrix to the $|j, m\rangle$ values is given by the cythonized function *jmm1_dictionary*. A density matrix is created from the given dictionary of coefficients for each (j, m, m1).

Parameters

N: int The number of two-level systems.

jmm1: dict A dictionary of {(j, m, m1): p} that gives a density p for the (j, m, m1) matrix element.

Returns

rho: :class: qutip.Qobj The density matrix in the Dicke basis.

dicke_blocks (*rho*)

Create the list of blocks for block-diagonal density matrix in the Dicke basis.

Parameters

rho [qutip.Qobj] A 2D block-diagonal matrix of ones with dimension (nds,nds), where nds is the number of Dicke states for N two-level systems.

Returns

square_blocks: list of np.array Give back the blocks list.

dicke_blocks_full (rho)

Give the full (2^N -dimensional) list of blocks for a Dicke-basis matrix.

Parameters

rho [qutip.Qobj] A 2D block-diagonal matrix of ones with dimension (nds,nds), where nds is the number of Dicke states for N two-level systems.

Returns

full_blocks [list] The list of blocks expanded in the 2^N space for N qubits.

dicke_function_trace (f, rho)

Calculate the trace of a function on a Dicke density matrix. :param f: A Taylor-expandable function of *rho*. :type f: function :param rho: A density matrix in the Dicke basis. :type rho: qutip.Qobj

Returns

res [float] Trace of a nonlinear function on *rho*.

energy_degeneracy (N, m)

Calculate the number of Dicke states with same energy.

The use of the *Decimals* class allows to explore $N > 1000$, unlike the built-in function *scipy.special.binom*

Parameters

N: int The number of two-level systems.

m: float Total spin z-axis projection eigenvalue. This is proportional to the total energy.

Returns

degeneracy: int The energy degeneracy

entropy_vn_dicke (rho)

Von Neumann Entropy of a Dicke-basis density matrix.

Parameters

rho [qutip.Qobj] A 2D block-diagonal matrix of ones with dimension (nds,nds), where nds is the number of Dicke states for N two-level systems.

Returns

entropy_dm: float Entropy. Use degeneracy to multiply each block.

excited (N, basis='dicke')

Generate the density matrix for the excited state.

This state is given by (N/2, N/2) in the default Dicke basis. If the argument *basis* is “uncoupled” then it generates the state in a 2^N dim Hilbert space.

Parameters

N: int The number of two-level systems.

basis: str The basis to use. Either “dicke” or “uncoupled”.

Returns

state: :class: qutip.Qobj The excited state density matrix in the requested basis.

ghz (N, basis='dicke')

Generate the density matrix of the GHZ state.

If the argument *basis* is “uncoupled” then it generates the state in a 2^N -dimensional Hilbert space.

Parameters

N: int The number of two-level systems.
basis: str The basis to use. Either “dicke” or “uncoupled”.

Returns

state: :class: qutip.Qobj The GHZ state density matrix in the requested basis.

ground (*N*, *basis*='dicke')

Generate the density matrix of the ground state.

This state is given by $(N/2, -N/2)$ in the Dicke basis. If the argument *basis* is “uncoupled” then it generates the state in a 2^N -dimensional Hilbert space.

Parameters

N: int The number of two-level systems.
basis: str The basis to use. Either “dicke” or “uncoupled”

Returns

state: :class: qutip.Qobj The ground state density matrix in the requested basis.

identity_uncoupled (*N*)

Generate the identity in a 2^N -dimensional Hilbert space.

The identity matrix is formed from the tensor product of *N* TLSs.

Parameters

N: int The number of two-level systems.

Returns

identity: :class: qutip.Qobj The identity matrix.

isdiagonal (*mat*)

Check if the input matrix is diagonal.

Parameters

mat: ndarray/Qobj A 2D numpy array

Returns

diag: bool True/False depending on whether the input matrix is diagonal.

jspin (*N*, *op*=None, *basis*='dicke')

Calculate the list of collective operators of the total algebra.

The Dicke basis $|j, m\rangle\langle j, m'|$ is used by default. Otherwise with “uncoupled” the operators are in a 2^N space.

Parameters

N: int Number of two-level systems.
op: str The operator to return ‘x’, ‘y’, ‘z’, ‘+’, ‘-’. If no operator given, then output is the list of operators for [‘x’, ‘y’, ‘z’].
basis: str The basis of the operators - “dicke” or “uncoupled” default: “dicke”.

Returns

j_alg: list or :class: qutip.Qobj A list of *qutip.Qobj* representing all the operators in the “dicke” or “uncoupled” basis or a single operator requested.

m_degeneracy (*N*, *m*)

Calculate the number of Dicke states $|j, m\rangle$ with same energy.

Parameters

N: int The number of two-level systems.

m: float Total spin z-axis projection eigenvalue (proportional to the total energy).

Returns

degeneracy: int The m-degeneracy.

num_dicke_ladders (*N*)

Calculate the total number of ladders in the Dicke space.

For a collection of *N* two-level systems it counts how many different “j” exist or the number of blocks in the block-diagonal matrix.

Parameters

N: int The number of two-level systems.

Returns

Nj: int The number of Dicke ladders.

num_dicke_states (*N*)

Calculate the number of Dicke states.

Parameters

N: int The number of two-level systems.

Returns

nds: int The number of Dicke states.

num_tls (*nds*)

Calculate the number of two-level systems.

Parameters

nds: int The number of Dicke states.

Returns

N: int The number of two-level systems.

purity_dicke (*rho*)

Calculate purity of a density matrix in the Dicke basis. It accounts for the degenerate blocks in the density matrix.

Parameters

rho [*qutip.Qobj*] Density matrix in the Dicke basis of *qutip.piqs.jspin(N)*, for *N* spins.

Returns

purity [float] The purity of the quantum state. It's 1 for pure states, $0 < \text{purity} < 1$ for mixed states.

spin_algebra (*N*, *op=None*)

Create the list [*sx*, *sy*, *sz*] with the spin operators.

The operators are constructed for a collection of *N* two-level systems (TLSs). Each element of the list, i.e., *sx*, is a vector of *qutip.Qobj* objects (spin matrices), as it contains the list of the SU(2) Pauli matrices for the *N* TLSs. Each TLS operator *sx[i]*, with *i* = 0, ..., (*N*-1), is placed in a 2^N -dimensional Hilbert space.

Parameters

N: int The number of two-level systems.

Returns

spin_operators: list or :class: qutip.Qobj A list of *qutip.Qobj* operators - [*sx*, *sy*, *sz*] or the requested operator.

Notes

$sx[i]$ is $\frac{\sigma_x}{2}$ in the composite Hilbert space.

state_degeneracy (N, j)

Calculate the degeneracy of the Dicke state.

Each state $|j, m\rangle$ includes $D(N, j)$ irreducible representations $|j, m, \alpha\rangle$.

Uses Decimals to calculate higher numerator and denominators numbers.

Parameters

N: int The number of two-level systems.

j: float Total spin eigenvalue (cooperativity).

Returns

degeneracy: int The state degeneracy.

superradiant ($N, basis='dicke'$)

Generate the density matrix of the superradiant state.

This state is given by $(N/2, 0)$ or $(N/2, 0.5)$ in the Dicke basis. If the argument *basis* is “uncoupled” then it generates the state in a 2^{*N} dim Hilbert space.

Parameters

N: int The number of two-level systems.

basis: str The basis to use. Either “dicke” or “uncoupled”.

Returns

state: :class: qutip.Qobj The superradiant state density matrix in the requested basis.

tau_column (tau, k, j)

Determine the column index for the non-zero elements of the matrix for a particular row k and the value of j from the Dicke space.

Parameters

tau: str The tau function to check for this k and j .

k: int The row of the matrix M for which the non zero elements have to be calculated.

j: float The value of j for this row.

5.2.5 Visualization

Pseudoprobability Functions

qfunc ($state: \text{qutip.core.qobj.Qobj}, xvec, yvec, g: \text{float} = 1.4142135623730951, precompute_memory: \text{float} = 1024$)

Husimi-Q function of a given state vector or density matrix at phase-space points $0.5 * g * (xvec + i*yvec)$.

Parameters

state [Qobj] A state vector or density matrix. This cannot have tensor-product structure.

xvec, yvec [array_like] x- and y-coordinates at which to calculate the Husimi-Q function.

g [float, default sqrt(2)] Scaling factor for $a = 0.5 * g * (x + i*y)$. The value of g is related to the value of \hbar in the commutation relation $[x, y] = i\hbar$ via $\hbar = 2/g^2$, so the default corresponds to $\hbar = 1$.

precompute_memory [real, default 1024] Size in MB that may be used during calculations as working space when dealing with density-matrix inputs. This is ignored for state-vector inputs. The bound is not quite exact due to other, order-of-magnitude smaller, intermediaries being necessary, but is a good approximation. If you want to use the same iterative algorithm for density matrices that is used for single kets, set `precompute_memory=None`.

Returns

ndarray Values representing the Husimi-Q function calculated over the specified range `[xvec, yvec]`.

See also:

QFunc a class-based version, more efficient if you want to calculate the Husimi-Q function for several states over the same coordinates.

spin_q_function (*rho, theta, phi*)

The Husimi Q function for spins is defined as $Q(\theta, \phi) = \text{SCS.dag}() * \text{rho} * \text{SCS}$ for the spin coherent state `SCS = spin_coherent(j, theta, phi)` where `j` is the spin length. The implementation here is more efficient as it doesn't generate all of the SCS at `theta` and `phi` (see references).

The spin Q function is normal when integrated over the surface of the sphere

$$\frac{4\pi}{2j+1} \int_{\phi} \int_{\theta} Q(\theta, \phi) \sin(\theta) d\theta d\phi = 1$$

Parameters

state [qobj] A state vector or density matrix for a spin-j quantum system.

theta [array_like] Polar (colatitude) angle at which to calculate the Husimi-Q function.

phi [array_like] Azimuthal angle at which to calculate the Husimi-Q function.

Returns

Q, THETA, PHI [2d-array] Values representing the spin Husimi Q function at the values specified by `THETA` and `PHI`.

References

[1] Lee Loh, Y., & Kim, M. (2015). American J. of Phys., 83(1), 30–35. <https://doi.org/10.1119/1.4898595>

spin_wigner (*rho, theta, phi*)

Wigner function for a spin-j system.

The spin W function is normal when integrated over the surface of the sphere

$$\sqrt{\frac{4\pi}{2j+1}} \int_{\phi} \int_{\theta} W(\theta, \phi) \sin(\theta) d\theta d\phi = 1$$

Parameters

state [qobj] A state vector or density matrix for a spin-j quantum system.

theta [array_like] Polar (colatitude) angle at which to calculate the W function.

phi [array_like] Azimuthal angle at which to calculate the W function.

Returns

W, THETA, PHI [2d-array] Values representing the spin Wigner function at the values specified by `THETA` and `PHI`.

References

- [1] Agarwal, G. S. (1981). Phys. Rev. A, 24(6), 2889–2896. <https://doi.org/10.1103/PhysRevA.24.2889>
- [2] Dowling, J. P., Agarwal, G. S., & Schleich, W. P. (1994). Phys. Rev. A, 49(5), 4101–4109. <https://doi.org/10.1103/PhysRevA.49.4101>
- [3] Conversion between Wigner 3-j symbol and Clebsch-Gordan coefficients taken from Wikipedia (https://en.wikipedia.org/wiki/3-j_symbol)

wigner (*psi*, *xvec*, *yvec*, *method*='clenshaw', *g*=1.4142135623730951, *sparse*=False, *parfor*=False)

Wigner function for a state vector or density matrix at points $xvec + i * yvec$.

Parameters

state [qobj] A state vector or density matrix.

xvec [array_like] x-coordinates at which to calculate the Wigner function.

yvec [array_like] y-coordinates at which to calculate the Wigner function. Does not apply to the 'fft' method.

g [float] Scaling factor for $a = 0.5 * g * (x + iy)$, default $g = \sqrt{2}$. The value of g is related to the value of \hbar in the commutation relation $[x, y] = i * \hbar$ via $\hbar = 2/g^2$ giving the default value $\hbar = 1$.

method [string {'clenshaw', 'iterative', 'laguerre', 'fft'}] Select method 'clenshaw' 'iterative', 'laguerre', or 'fft', where 'clenshaw' and 'iterative' use an iterative method to evaluate the Wigner functions for density matrices $|m| > n|$, while 'laguerre' uses the Laguerre polynomials in scipy for the same task. The 'fft' method evaluates the Fourier transform of the density matrix. The 'iterative' method is default, and in general recommended, but the 'laguerre' method is more efficient for very sparse density matrices (e.g., superpositions of Fock states in a large Hilbert space). The 'clenshaw' method is the preferred method for dealing with density matrices that have a large number of excitations (> 50). 'clenshaw' is a fast and numerically stable method.

sparse [bool {False, True}] Tells the default solver whether or not to keep the input density matrix in sparse format. As the dimensions of the density matrix grow, setting this flag can result in increased performance.

parfor [bool {False, True}] Flag for calculating the Laguerre polynomial based Wigner function method='laguerre' in parallel using the parfor function.

Returns

W [array] Values representing the Wigner function calculated over the specified range [xvec, yvec].

yvec [array] FFT ONLY. Returns the y-coordinate values calculated via the Fourier transform.

Notes

The 'fft' method accepts only an xvec input for the x-coordinate. The y-coordinates are calculated internally.

References

Ulf Leonhardt, Measuring the Quantum State of Light, (Cambridge University Press, 1997)

Graphs and Visualization

Functions for visualizing results of quantum dynamics simulations, visualizations of quantum states and processes.

hinton (*rho*, *xlabels=None*, *ylabels=None*, *title=None*, *ax=None*, *cmap=None*, *label_top=True*, *color_style='scaled'*)

Draws a Hinton diagram for visualizing a density matrix or superoperator.

Parameters

rho [qobj] Input density matrix or superoperator.

xlabels [list of strings or False] list of x labels

ylabels [list of strings or False] list of y labels

title [string] title of the plot (optional)

ax [a matplotlib axes instance] The axes context in which the plot will be drawn.

cmap [a matplotlib colormap instance] Color map to use when plotting.

label_top [bool] If True, x-axis labels will be placed on top, otherwise they will appear below the plot.

color_style [string] Determines how colors are assigned to each square:

- If set to "scaled" (default), each color is chosen by passing the absolute value of the corresponding matrix element into *cmap* with the sign of the real part.
- If set to "threshold", each square is plotted as the maximum of *cmap* for the positive real part and as the minimum for the negative part of the matrix element; note that this generalizes "threshold" to complex numbers.
- If set to "phase", each color is chosen according to the angle of the corresponding matrix element.

Returns

fig, ax [tuple] A tuple of the matplotlib figure and axes instances used to produce the figure.

Raises

ValueError Input argument is not a quantum object.

Examples

```
>>> import qutip
>>>
>>> dm = qutip.rand_dm(4)
>>> fig, ax = qutip.hinton(dm)
>>> fig.show()
>>>
>>> qutip.settings.colorblind_safe = True
>>> fig, ax = qutip.hinton(dm, color_style="threshold")
>>> fig.show()
>>> qutip.settings.colorblind_safe = False
>>>
>>> fig, ax = qutip.hinton(dm, color_style="phase")
>>> fig.show()
```


matrix_histogram(*M*, *xlabels=None*, *ylabels=None*, *title=None*, *limits=None*, *colorbar=True*, *fig=None*, *ax=None*, *options=None*)

Draw a histogram for the matrix *M*, with the given *x* and *y* labels and title.

Parameters

M [Matrix of Qobj] The matrix to visualize

xlabels [list of strings] list of *x* labels

ylabels [list of strings] list of *y* labels

title [string] title of the plot (optional)

limits [list/array with two float numbers] The *z*-axis limits [min, max] (optional)

ax [a matplotlib axes instance] The axes context in which the plot will be drawn.

colorbar [bool (default: True)] show colorbar

options [dict] A dictionary containing extra options for the plot. The names (keys) and values of the options are described below:

‘zticks’ [list of numbers] A list of *z*-axis tick locations.

‘cmap’ [string (default: ‘jet’)] The name of the color map to use.

‘cmap_min’ [float (default: 0.0)] The lower bound to truncate the color map at. A value in range 0 - 1. The default, 0, leaves the lower bound of the map unchanged.

‘cmap_max’ [float (default: 1.0)] The upper bound to truncate the color map at. A value in range 0 - 1. The default, 1, leaves the upper bound of the map unchanged.

‘bars_spacing’ [float (default: 0.1)] spacing between bars.

‘bars_alpha’ [float (default: 1.)] transparency of bars, should be in range 0 - 1

‘bars_lw’ [float (default: 0.5)] linewidth of bars’ edges.

‘bars_edgecolor’ [color (default: ‘k’)] The colors of the bars’ edges. Examples: ‘k’, (0.1, 0.2, 0.5) or ‘#0f0f80’.

‘shade’ [bool (default: True)] Whether to shade the dark sides of the bars (True) or not (False). The shading is relative to plot’s source of light.

‘azim’ [float] The azimuthal viewing angle.

‘elev’ [float] The elevation viewing angle.

‘proj_type’ [string (default: ‘ortho’ if *ax* is not passed)] The type of projection (‘ortho’ or ‘persp’)

‘stick’ [bool (default: False)] Changes *xlim* and *ylim* in such a way that bars next to *XZ* and *YZ* planes will stick to those planes. This option has no effect if *ax* is passed as a parameter.

‘cbar_pad’ [float (default: 0.04)] The fraction of the original axes between the colorbar and the new image axes. (i.e. the padding between the 3D figure and the colorbar).

‘cbar_to_z’ [bool (default: False)] Whether to set the color of maximum and minimum *z*-values to the maximum and minimum colors in the colorbar (True) or not (False).

‘figsize’ [tuple of two numbers] The size of the figure.

Returns :

fig, ax [tuple] A tuple of the matplotlib figure and axes instances used to produce the figure.

Raises

ValueError Input argument is not valid.

matrix_histogram_complex (*M*, *xlabels=None*, *ylabels=None*, *title=None*, *limits=None*, *phase_limits=None*, *colorbar=True*, *fig=None*, *ax=None*, *threshold=None*)

Draw a histogram for the amplitudes of matrix *M*, using the argument of each element for coloring the bars, with the given *x* and *y* labels and title.

Parameters

- M** [Matrix of Qobj] The matrix to visualize
- xlabels** [list of strings] list of *x* labels
- ylabels** [list of strings] list of *y* labels
- title** [string] title of the plot (optional)
- limits** [list/array with two float numbers] The *z*-axis limits [min, max] (optional)
- phase_limits** [list/array with two float numbers] The phase-axis (colorbar) limits [min, max] (optional)
- ax** [a matplotlib axes instance] The axes context in which the plot will be drawn.
- threshold: float (None)** Threshold for when bars of smaller height should be transparent. If not set, all bars are colored according to the color map.

Returns

- fig, ax** [tuple] A tuple of the matplotlib figure and axes instances used to produce the figure.

Raises

- ValueError** Input argument is not valid.

plot_energy_levels (*H_list*, *N=0*, *labels=None*, *show_ylabels=False*, *figsize=(8, 12)*, *fig=None*, *ax=None*)

Plot the energy level diagrams for a list of Hamiltonians. Include up to *N* energy levels. For each element in *H_list*, the energy levels diagram for the cumulative Hamiltonian $\text{sum}(H_list[0:n])$ is plotted, where *n* is the index of an element in *H_list*.

Parameters

- H_list** [List of Qobj]
A list of Hamiltonians.
- labels** [List of string] A list of labels for each Hamiltonian
- show_ylabels** [Bool (default False)] Show *y* labels to the left of energy levels of the initial Hamiltonian.
- N** [int] The number of energy levels to plot
- figsize** [tuple (int,int)] The size of the figure (width, height).
- fig** [a matplotlib Figure instance] The Figure canvas in which the plot will be drawn.
- ax** [a matplotlib axes instance] The axes context in which the plot will be drawn.

Returns

- fig, ax** [tuple] A tuple of the matplotlib figure and axes instances used to produce the figure.

Raises

- ValueError** Input argument is not valid.

plot_expectation_values (*results*, *ylabels=[]*, *title=None*, *show_legend=False*, *fig=None*, *axes=None*, *figsize=(8, 4)*)

Visualize the results (expectation values) for an evolution solver. *results* is assumed to be an instance of *Result*, or a list of *Result* instances.

Parameters

results [(list of) `qutip.solver.Result`] List of results objects returned by any of the QuTiP evolution solvers.

ylabels [list of strings] The y-axis labels. List should be of the same length as *results*.

title [string] The title of the figure.

show_legend [bool] Whether or not to show the legend.

fig [a matplotlib Figure instance] The Figure canvas in which the plot will be drawn.

axes [a matplotlib axes instance] The axes context in which the plot will be drawn.

figsize [(width, height)] The size of the matplotlib figure (in inches) if it is to be created (that is, if no 'fig' and 'ax' arguments are passed).

Returns

fig, ax [tuple] A tuple of the matplotlib figure and axes instances used to produce the figure.

plot_fock_distribution (*rho*, *offset=0*, *fig=None*, *ax=None*, *figsize=(8, 6)*, *title=None*, *unit_y_range=True*)
Plot the Fock distribution for a density matrix (or ket) that describes an oscillator mode.

Parameters

rho [`qutip.Qobj`] The density matrix (or ket) of the state to visualize.

fig [a matplotlib Figure instance] The Figure canvas in which the plot will be drawn.

ax [a matplotlib axes instance] The axes context in which the plot will be drawn.

title [string] An optional title for the figure.

figsize [(width, height)] The size of the matplotlib figure (in inches) if it is to be created (that is, if no 'fig' and 'ax' arguments are passed).

Returns

fig, ax [tuple] A tuple of the matplotlib figure and axes instances used to produce the figure.

plot_qubism (*ket*, *theme='light'*, *how='pairs'*, *grid_iteration=1*, *legend_iteration=0*, *fig=None*, *ax=None*, *figsize=(6, 6)*)
Qubism plot for pure states of many qudits. Works best for spin chains, especially with even number of particles of the same dimension. Allows to see entanglement between first 2k particles and the rest.

Parameters

ket [`Qobj`] Pure state for plotting.

theme ['light' (default) or 'dark'] Set coloring theme for mapping complex values into colors. See: `complex_array_to_rgb`.

how ['pairs' (default), 'pairs_skewed' or 'before_after'] Type of Qubism plotting. Options:

- 'pairs' - typical coordinates,
- 'pairs_skewed' - for ferromagnetic/antiferromagnetic plots,
- 'before_after' - related to Schmidt plot (see also: `plot_schmidt`).

grid_iteration [int (default 1)] Helper lines to be drawn on plot. Show tiles for $2 \times \text{grid_iteration}$ particles vs all others.

legend_iteration [int (default 0) or 'grid_iteration' or 'all'] Show labels for first $2 \times \text{legend_iteration}$ particles. Option 'grid_iteration' sets the same number of particles as for `grid_iteration`. Option 'all' makes label for all particles. Typically it should be 0, 1, 2 or perhaps 3.

fig [a matplotlib figure instance] The figure canvas on which the plot will be drawn.

ax [a matplotlib axis instance] The axis context in which the plot will be drawn.

figsize [(width, height)] The size of the matplotlib figure (in inches) if it is to be created (that is, if no 'fig' and 'ax' arguments are passed).

Returns

fig, ax [tuple] A tuple of the matplotlib figure and axes instances used to produce the figure.

Notes

See also [1].

References

[1]

plot_schmidt (*ket*, *splitting=None*, *labels_iteration=(3, 2)*, *theme='light'*, *fig=None*, *ax=None*, *figsize=(6, 6)*)

Plotting scheme related to Schmidt decomposition. Converts a state into a matrix ($A_{ij} \rightarrow A_i^j$), where rows are first particles and columns - last.

See also: `plot_qubism` with `how='before_after'` for a similar plot.

Parameters

ket [Qobj] Pure state for plotting.

splitting [int] Plot for a number of first particles versus the rest. If not given, it is (number of particles + 1) // 2.

theme ['light' (default) or 'dark'] Set coloring theme for mapping complex values into colors. See: `complex_array_to_rgb`.

labels_iteration [int or pair of ints (default (3,2))] Number of particles to be shown as tick labels, for first (vertical) and last (horizontal) particles, respectively.

fig [a matplotlib figure instance] The figure canvas on which the plot will be drawn.

ax [a matplotlib axis instance] The axis context in which the plot will be drawn.

figsize [(width, height)] The size of the matplotlib figure (in inches) if it is to be created (that is, if no 'fig' and 'ax' arguments are passed).

Returns

fig, ax [tuple] A tuple of the matplotlib figure and axes instances used to produce the figure.

plot_spin_distribution_2d (*P*, *THETA*, *PHI*, *fig=None*, *ax=None*, *figsize=(8, 8)*)

Plot a spin distribution function (given as meshgrid data) with a 2D projection where the surface of the unit sphere is mapped on the unit disk.

Parameters

P [matrix] Distribution values as a meshgrid matrix.

THETA [matrix] Meshgrid matrix for the theta coordinate.

PHI [matrix] Meshgrid matrix for the phi coordinate.

fig [a matplotlib figure instance] The figure canvas on which the plot will be drawn.

ax [a matplotlib axis instance] The axis context in which the plot will be drawn.

figsize [(width, height)] The size of the matplotlib figure (in inches) if it is to be created (that is, if no 'fig' and 'ax' arguments are passed).

Returns

fig, ax [tuple] A tuple of the matplotlib figure and axes instances used to produce the figure.

plot_spin_distribution_3d (*P, THETA, PHI, fig=None, ax=None, figsize=(8, 6)*)

Plots a matrix of values on a sphere

Parameters

P [matrix] Distribution values as a meshgrid matrix.

THETA [matrix] Meshgrid matrix for the theta coordinate.

PHI [matrix] Meshgrid matrix for the phi coordinate.

fig [a matplotlib figure instance] The figure canvas on which the plot will be drawn.

ax [a matplotlib axis instance] The axis context in which the plot will be drawn.

figsize [(width, height)] The size of the matplotlib figure (in inches) if it is to be created (that is, if no 'fig' and 'ax' arguments are passed).

Returns

fig, ax [tuple] A tuple of the matplotlib figure and axes instances used to produce the figure.

plot_wigner (*rho, fig=None, ax=None, figsize=(6, 6), cmap=None, alpha_max=7.5, colorbar=False, method='clenshaw', projection='2d'*)

Plot the the Wigner function for a density matrix (or ket) that describes an oscillator mode.

Parameters

rho [qutip.Qobj] The density matrix (or ket) of the state to visualize.

fig [a matplotlib Figure instance] The Figure canvas in which the plot will be drawn.

ax [a matplotlib axes instance] The axes context in which the plot will be drawn.

figsize [(width, height)] The size of the matplotlib figure (in inches) if it is to be created (that is, if no 'fig' and 'ax' arguments are passed).

cmap [a matplotlib cmap instance] The colormap.

alpha_max [float] The span of the x and y coordinates (both [-alpha_max, alpha_max]).

colorbar [bool] Whether (True) or not (False) a colorbar should be attached to the Wigner function graph.

method [string {'clenshaw', 'iterative', 'laguerre', 'fft'}] The method used for calculating the wigner function. See the documentation for qutip.wigner for details.

projection: string {'2d', '3d'} Specify whether the Wigner function is to be plotted as a contour graph ('2d') or surface plot ('3d').

Returns

fig, ax [tuple] A tuple of the matplotlib figure and axes instances used to produce the figure.

plot_wigner_fock_distribution (*rho, fig=None, axes=None, figsize=(8, 4), cmap=None, alpha_max=7.5, colorbar=False, method='iterative', projection='2d'*)

Plot the Fock distribution and the Wigner function for a density matrix (or ket) that describes an oscillator mode.

Parameters

rho [qutip.Qobj] The density matrix (or ket) of the state to visualize.

fig [a matplotlib Figure instance] The Figure canvas in which the plot will be drawn.

axes [a list of two matplotlib axes instances] The axes context in which the plot will be drawn.

figsize [(width, height)] The size of the matplotlib figure (in inches) if it is to be created (that is, if no 'fig' and 'ax' arguments are passed).

cmap [a matplotlib cmap instance] The colormap.

alpha_max [float] The span of the x and y coordinates (both $[-\alpha_{\max}, \alpha_{\max}]$).

colorbar [bool] Whether (True) or not (False) a colorbar should be attached to the Wigner function graph.

method [string { 'iterative', 'laguerre', 'fft' }] The method used for calculating the wigner function. See the documentation for `qutip.wigner` for details.

projection: string { '2d', '3d' } Specify whether the Wigner function is to be plotted as a contour graph ('2d') or surface plot ('3d').

Returns

fig, ax [tuple] A tuple of the matplotlib figure and axes instances used to produce the figure.

plot_wigner_sphere (*fig, ax, wigner, reflections*)

Plots a coloured Bloch sphere.

Parameters

fig [matplotlib.figure.Figure] An instance of Figure.

ax [matplotlib.axes.Axes] An axes instance in the given figure.

wigner [list of float] The wigner transformation at *steps* different theta and phi.

reflections [bool] If the reflections of the sphere should be plotted as well.

Notes

Special thanks to Russell P Rundle for writing this function.

sphereplot (*theta, phi, values, fig=None, ax=None, save=False*)

Plots a matrix of values on a sphere

Parameters

theta [float] Angle with respect to z-axis

phi [float] Angle in x-y plane

values [array] Data set to be plotted

fig [a matplotlib Figure instance] The Figure canvas in which the plot will be drawn.

ax [a matplotlib axes instance] The axes context in which the plot will be drawn.

save [bool {False, True}] Whether to save the figure or not

Returns

fig, ax [tuple] A tuple of the matplotlib figure and axes instances used to produce the figure.

orbital (*theta, phi, *args*)

Calculates an angular wave function on a sphere. `psi = orbital(theta, phi, ket1, ket2, ...)` calculates the angular wave function on a sphere at the mesh of points defined by theta and phi which is $\sum_{lm} c_{lm} Y_{lm}(\theta, \phi)$ where C_{lm} are the coefficients specified by the list of kets. Each ket has $2l+1$ components for some integer l . The first entry of the ket defines the coefficient $c_{\{l,-l\}}$, while the last entry of the ket defines the coefficient $c_{\{l,l\}}$.

Parameters

theta [int/float/list/array] Polar angles in $[0, \pi]$

phi [int/float/list/array] Azimuthal angles in $[0, 2\pi]$

args [list/array] list of ket vectors.

Returns

array for angular wave function evaluated at all possible combinations of theta and phi

This module contains utility functions that enhance Matplotlib in one way or another.

complex_phase_cmap ()

Create a cyclic colormap for representing the phase of complex variables

Returns

cmap : A matplotlib linear segmented colormap.

wigner_cmap (W, levels=1024, shift=0, max_color='#09224F', mid_color='#FFFFFF', min_color='#530017', neg_color='#FF97D4', invert=False)

A custom colormap that emphasizes negative values by creating a nonlinear colormap.

Parameters

W [array] Wigner function array, or any array.

levels [int] Number of color levels to create.

shift [float] Shifts the value at which Wigner elements are emphasized. This parameter should typically be negative and small (i.e -1e-5).

max_color [str] String for color corresponding to maximum value of data. Accepts any string format compatible with the Matplotlib.colors.ColorConverter.

mid_color [str] Color corresponding to zero values. Accepts any string format compatible with the Matplotlib.colors.ColorConverter.

min_color [str] Color corresponding to minimum data values. Accepts any string format compatible with the Matplotlib.colors.ColorConverter.

neg_color [str] Color that starts highlighting negative values. Accepts any string format compatible with the Matplotlib.colors.ColorConverter.

invert [bool] Invert the color scheme for negative values so that smaller negative values have darker color.

Returns

Returns a Matplotlib colormap instance for use in plotting.

Notes

The 'shift' parameter allows you to vary where the colormap begins to highlight negative colors. This is beneficial in cases where there are small negative Wigner elements due to numerical round-off and/or truncation.

Quantum Process Tomography

qpt (U, op_basis_list)

Calculate the quantum process tomography chi matrix for a given (possibly nonunitary) transformation matrix U, which transforms a density matrix in vector form according to:

$$\text{vec}(\rho) = U * \text{vec}(\rho_0)$$

or

$$\rho = \text{unstack_columns}(U * \text{stack_columns}(\rho_0))$$

U can be calculated for an open quantum system using the QuTiP propagator function.

Parameters

U [Qobj] Transformation operator. Can be calculated using QuTiP propagator function.

op_basis_list [list] A list of Qobj's representing the basis states.

Returns

chi [array] QPT chi matrix

qpt_plot (*chi, lbls_list, title=None, fig=None, axes=None*)

Visualize the quantum process tomography chi matrix. Plot the real and imaginary parts separately.

Parameters

chi [array] Input QPT chi matrix.

lbls_list [list] List of labels for QPT plot axes.

title [string] Plot title.

fig [figure instance] User defined figure instance used for generating QPT plot.

axes [list of figure axis instance] User defined figure axis instance (list of two axes) used for generating QPT plot.

Returns

fig, ax [tuple] A tuple of the matplotlib figure and axes instances used to produce the figure.

qpt_plot_combined (*chi, lbls_list, title=None, fig=None, ax=None, figsize=(8, 6), threshold=None*)

Visualize the quantum process tomography chi matrix. Plot bars with height and color corresponding to the absolute value and phase, respectively.

Parameters

chi [array] Input QPT chi matrix.

lbls_list [list] List of labels for QPT plot axes.

title [string] Plot title.

fig [figure instance] User defined figure instance used for generating QPT plot.

ax [figure axis instance] User defined figure axis instance used for generating QPT plot (alternative to the fig argument).

threshold: float (None) Threshold for when bars of smaller height should be transparent. If not set, all bars are colored according to the color map.

Returns

fig, ax [tuple] A tuple of the matplotlib figure and axes instances used to produce the figure.

5.2.6 Non-Markovian Solvers

This module contains an implementation of the non-Markovian transfer tensor method (TTM), introduced in [1].

[1] Javier Cerrillo and Jianshu Cao, Phys. Rev. Lett 112, 110401 (2014)

ttmsolve (*dynmaps, rho0, times, e_ops=[], learningtimes=None, tensors=None, **kwargs*)

Solve time-evolution using the Transfer Tensor Method, based on a set of precomputed dynamical maps.

Parameters

dynmaps [list of qutip.Qobj] List of precomputed dynamical maps (superoperators), or a callback function that returns the superoperator at a given time.

rho0 [qutip.Qobj] Initial density matrix or state vector (ket).

times [array_like] list of times t_n at which to compute $\rho(t_n)$. Must be uniformly spaced.

e_ops [list of qutip.Qobj / callback function] single operator or list of operators for which to evaluate expectation values.

learningtimes [array_like] list of times t_k for which we have knowledge of the dynamical maps $E(t_k)$.

tensors [array_like] optional list of precomputed tensors T_k

kwargs [dictionary] Optional keyword arguments. See `qutip.nonmarkov.transfertensor.TTMSolverOptions`.

Returns

output: `qutip.solver.Result` An instance of the class `qutip.solver.Result`.

5.2.7 Optimal control

Wrapper functions that will manage the creation of the objects, build the configuration, and execute the algorithm required to optimise a set of ctrl pulses for a given (quantum) system. The fidelity error is some measure of distance of the system evolution from the given target evolution in the time allowed for the evolution. The functions minimise this fidelity error wrt the piecewise control amplitudes in the timeslots

There are currently two quantum control pulse optimisations algorithms implemented in this library. There are accessible through the methods in this module. Both the algorithms use the `scipy.optimize` methods to minimise the fidelity error with respect to variables that define the pulse.

GRAPE

The default algorithm (as it was implemented here first) is GRAPE GRAdient Ascent Pulse Engineering [1][2]. It uses a gradient based method such as BFGS to minimise the fidelity error. This makes convergence very quick when an exact gradient can be calculated, but this limits the factors that can taken into account in the fidelity.

CRAB

The CRAB [3][4] algorithm was developed at the University of Ulm. In full it is the Chopped RANdom Basis algorithm. The main difference is that it reduces the number of optimisation variables by defining the control pulses by expansions of basis functions, where the variables are the coefficients. Typically a Fourier series is chosen, i.e. the variables are the Fourier coefficients. Therefore it does not need to compute an explicit gradient. By default it uses the Nelder-Mead method for fidelity error minimisation.

References

1. N Khaneja et. al. Optimal control of coupled spin dynamics: Design of NMR pulse sequences by gradient ascent algorithms. J. Magn. Reson. 172, 296–305 (2005).
2. Shai Machnes et.al DYNAMO - Dynamic Framework for Quantum Optimal Control arXiv.1011.4874
3. Doria, P., Calarco, T. & Montangero, S. Optimal Control Technique for Many-Body Quantum Dynamics. Phys. Rev. Lett. 106, 1–4 (2011).
4. Caneva, T., Calarco, T. & Montangero, S. Chopped random-basis quantum optimization. Phys. Rev. A - At. Mol. Opt. Phys. 84, (2011).

```
create_pulse_optimizer (drift, ctrls, initial, target, num_tslots=None, evo_time=None, tau=None,
amp_lbound=None, amp_ubound=None, fid_err_targ=1e-10,
min_grad=1e-10, max_iter=500, max_wall_time=180, alg='GRAPE',
alg_params=None, optim_params=None, optim_method='DEF',
method_params=None, optim_alg=None, max_metric_corr=None, ac-
curacy_factor=None, dyn_type='GEN_MAT', dyn_params=None,
prop_type='DEF', prop_params=None, fid_type='DEF',
fid_params=None, phase_option=None, fid_err_scale_factor=None,
tslot_type='DEF', tslot_params=None, amp_update_mode=None,
init_pulse_type='DEF', init_pulse_params=None, pulse_scaling=1.0,
pulse_offset=0.0, ramping_pulse_type=None, ramp-
ing_pulse_params=None, log_level=0, gen_stats=False)
```

Generate the objects of the appropriate subclasses required for the pulse optimisation based on the parameters given. Note this method may be preferable to calling `optimize_pulse` if more detailed configuration is required before running the optimisation algorithm, or the algorithm will be run many times, for instances when trying to find the global optimum or minimum time optimisation.

Parameters

drift [Qobj or list of Qobj] The underlying dynamics generator of the system can provide a list (of length `num_tslots`) for time dependent drift.

ctrls [List of Qobj or array like [num_tslots, evo_time]] A list of control dynamics generators. These are scaled by the amplitudes to alter the overall dynamics. Array-like input can be provided for time dependent control generators.

initial [Qobj] Starting point for the evolution. Typically the identity matrix.

target [Qobj] Target transformation, e.g. gate or state, for the time evolution.

num_tslots [integer or None] Number of timeslots. `None` implies that timeslots will be given in the `tau` array.

evo_time [float or None] Total time for the evolution. `None` implies that timeslots will be given in the `tau` array.

tau [array[num_tslots] of floats or None] Durations for the timeslots. If this is given then `num_tslots` and `evo_time` are derived from it. `None` implies that timeslot durations will be equal and calculated as `evo_time/num_tslots`.

amp_lbound [float or list of floats] Lower boundaries for the control amplitudes. Can be a scalar value applied to all controls or a list of bounds for each control.

amp_ubound [float or list of floats] Upper boundaries for the control amplitudes. Can be a scalar value applied to all controls or a list of bounds for each control.

fid_err_targ [float] Fidelity error target. Pulse optimisation will terminate when the fidelity error falls below this value.

min_grad [float] Minimum gradient. When the sum of the squares of the gradients wrt to the control amplitudes falls below this value, the optimisation terminates, assuming local minima.

max_iter [integer] Maximum number of iterations of the optimisation algorithm.

max_wall_time [float] Maximum allowed elapsed time for the optimisation algorithm.

alg [string] Algorithm to use in pulse optimisation. Options are:

- 'GRAPE' (default) - Gradient Ascent Pulse Engineering
- 'CRAB' - Chopped Random Basis

alg_params [Dictionary] options that are specific to the algorithm see above

optim_params [Dictionary] The key value pairs are the attribute name and value used to set attribute values. Note: attributes are created if they do not exist already, and are over-

written if they do. Note: `method_params` are applied afterwards and so may override these.

optim_method [string] a `scipy.optimize.minimize` method that will be used to optimise the pulse for minimum fidelity error Note that `FMIN`, `FMIN_BFGS` & `FMIN_L_BFGS_B` will all result in calling these specific `scipy.optimize` methods Note the `LBFGSB` is equivalent to `FMIN_L_BFGS_B` for backwards compatibility reasons. Supplying `DEF` will given alg dependent result:

- GRAPE - Default `optim_method` is `FMIN_L_BFGS_B`
- CRAB - Default `optim_method` is Nelder-Mead

method_params [dict] Parameters for the `optim_method`. Note that where there is an attribute of the `Optimizer` object or the `termination_conditions` matching the key that attribute. Otherwise, and in some case also, they are assumed to be `method_options` for the `scipy.optimize.minimize` method.

optim_alg [string] Deprecated. Use `optim_method`.

max_metric_corr [integer] Deprecated. Use `method_params` instead

accuracy_factor [float] Deprecated. Use `method_params` instead

dyn_type [string] Dynamics type, i.e. the type of matrix used to describe the dynamics. Options are `UNIT`, `GEN_MAT`, `SYMP` (see Dynamics classes for details)

dyn_params [dict] Parameters for the Dynamics object The key value pairs are assumed to be attribute name value pairs They applied after the object is created

prop_type [string] Propagator type i.e. the method used to calculate the propagators and propagator gradient for each timeslot options are `DEF`, `APPROX`, `DIAG`, `FRECHET`, `AUG_MAT` `DEF` will use the default for the specific `dyn_type` (see PropagatorComputer classes for details)

prop_params [dict] Parameters for the PropagatorComputer object The key value pairs are assumed to be attribute name value pairs They applied after the object is created

fid_type [string] Fidelity error (and fidelity error gradient) computation method Options are `DEF`, `UNIT`, `TRACEDIFF`, `TD_APPROX` `DEF` will use the default for the specific `dyn_type` (See FidelityComputer classes for details)

fid_params [dict] Parameters for the FidelityComputer object The key value pairs are assumed to be attribute name value pairs They applied after the object is created

phase_option [string] Deprecated. Pass in `fid_params` instead.

fid_err_scale_factor [float] Deprecated. Use `scale_factor` key in `fid_params` instead.

tslot_type [string] Method for computing the dynamics generators, propagators and evolution in the timeslots. Options: `DEF`, `UPDATE_ALL`, `DYNAMIC` `UPDATE_ALL` is the only one that currently works (See TimeslotComputer classes for details)

tslot_params [dict] Parameters for the TimeslotComputer object. The key value pairs are assumed to be attribute name value pairs. They applied after the object is created.

amp_update_mode [string] Deprecated. Use `tslot_type` instead.

init_pulse_type [string] type / shape of pulse(s) used to initialise the the control amplitudes. Options (GRAPE) include:

`RND`, `LIN`, `ZERO`, `SINE`, `SQUARE`, `TRIANGLE`, `SAW` `DEF` is `RND`

(see PulseGen classes for details) For the CRAB the this the `guess_pulse_type`.

init_pulse_params [dict] Parameters for the initial / guess pulse generator object. The key value pairs are assumed to be attribute name value pairs. They applied after the object is created.

pulse_scaling [float] Linear scale factor for generated initial / guess pulses By default initial pulses are generated with amplitudes in the range (-1.0, 1.0). These will be scaled by this parameter

pulse_offset [float] Linear offset for the pulse. That is this value will be added to any initial / guess pulses generated.

ramping_pulse_type [string] Type of pulse used to modulate the control pulse. It's intended use for a ramping modulation, which is often required in experimental setups. This is only currently implemented in CRAB. GAUSSIAN_EDGE was added for this purpose.

ramping_pulse_params [dict] Parameters for the ramping pulse generator object. The key value pairs are assumed to be attribute name value pairs. They applied after the object is created

log_level [integer] level of messaging output from the logger. Options are attributes of `qutip.logging_utils`, in decreasing levels of messaging, are: `DEBUG_INTENSE`, `DEBUG_VERBOSE`, `DEBUG`, `INFO`, `WARN`, `ERROR`, `CRITICAL` Anything `WARN` or above is effectively 'quiet' execution, assuming everything runs as expected. The default `NOTSET` implies that the level will be taken from the QuTiP settings file, which by default is `WARN`

gen_stats [boolean] if set to `True` then statistics for the optimisation run will be generated - accessible through attributes of the stats object

Returns

opt [Optimizer] Instance of an Optimizer, through which the Config, Dynamics, PulseGen, and TerminationConditions objects can be accessed as attributes. The PropagatorComputer, FidelityComputer and TimeslotComputer objects can be accessed as attributes of the Dynamics object, e.g. `optimizer.dynamics.fid_computer` The optimisation can be run through the `optimizer.run_optimization`

opt_pulse_crab (*drift, ctrls, initial, target, num_slots=None, evo_time=None, tau=None, amp_lbound=None, amp_ubound=None, fid_err_targ=1e-05, max_iter=500, max_wall_time=180, alg_params=None, num_coeffs=None, init_coeff_scaling=1.0, optim_params=None, optim_method='fmin', method_params=None, dyn_type='GEN_MAT', dyn_params=None, prop_type='DEF', prop_params=None, fid_type='DEF', fid_params=None, tslot_type='DEF', tslot_params=None, guess_pulse_type=None, guess_pulse_params=None, guess_pulse_scaling=1.0, guess_pulse_offset=0.0, guess_pulse_action='MODULATE', ramping_pulse_type=None, ramping_pulse_params=None, log_level=0, out_file_ext=None, gen_stats=False*)

Optimise a control pulse to minimise the fidelity error. The dynamics of the system in any given timeslot are governed by the combined dynamics generator, i.e. the sum of the `drift+ctrl_amp[j]*ctrls[j]` The control pulse is an `[n_ts, n_ctrls]` array of piecewise amplitudes. The CRAB algorithm uses basis function coefficients as the variables to optimise. It does NOT use any gradient function. A multivariable optimisation algorithm attempts to determines the optimal values for the control pulse to minimise the fidelity error The fidelity error is some measure of distance of the system evolution from the given target evolution in the time allowed for the evolution.

Parameters

drift [Qobj or list of Qobj] the underlying dynamics generator of the system can provide list (of length `num_slots`) for time dependent drift

ctrls [List of Qobj or array like `[num_slots, evo_time]`] a list of control dynamics generators. These are scaled by the amplitudes to alter the overall dynamics Array like input can be provided for time dependent control generators

initial [Qobj] Starting point for the evolution. Typically the identity matrix.

target [Qobj] Target transformation, e.g. gate or state, for the time evolution.

num_slots [integer or None] Number of timeslots. `None` implies that timeslots will be given in the `tau` array.

evo_time [float or None] Total time for the evolution. `None` implies that timeslots will be given in the `tau` array.

tau [array[num_slots] of floats or None] Durations for the timeslots. If this is given then `num_slots` and `evo_time` are derived from it. `None` implies that timeslot durations will be equal and calculated as `evo_time/num_slots`.

amp_lbound [float or list of floats] Lower boundaries for the control amplitudes. Can be a scalar value applied to all controls or a list of bounds for each control.

amp_ubound [float or list of floats] Upper boundaries for the control amplitudes. Can be a scalar value applied to all controls or a list of bounds for each control.

fid_err_targ [float] Fidelity error target. Pulse optimisation will terminate when the fidelity error falls below this value.

max_iter [integer] Maximum number of iterations of the optimisation algorithm.

max_wall_time [float] Maximum allowed elapsed time for the optimisation algorithm.

alg_params [Dictionary] Options that are specific to the algorithm see above.

optim_params [Dictionary] The key value pairs are the attribute name and value used to set attribute values. Note: attributes are created if they do not exist already, and are overwritten if they do. Note: `method_params` are applied afterwards and so may override these.

coeff_scaling [float] Linear scale factor for the random basis coefficients. By default these range from -1.0 to 1.0. Note this is overridden by `alg_params` (if given there).

num_coeffs [integer] Number of coefficients used for each basis function. Note this is calculated automatically based on the dimension of the dynamics if not given. It is crucial to the performance of the algorithm that it is set as low as possible, while still giving high enough frequencies. Note this is overridden by `alg_params` (if given there).

optim_method [string] Multi-variable optimisation method. The only tested options are 'fmin' and 'Nelder-mead'. In theory any non-gradient method implemented in `scipy.optimize.minimize` could be used.

method_params [dict] Parameters for the `optim_method`. Note that where there is an attribute of the `Optimizer` object or the termination_conditions matching the key that attribute. Otherwise, and in some case also, they are assumed to be `method_options` for the `scipy.optimize.minimize` method. The commonly used parameter are:

- `xtol` - limit on variable change for convergence
- `ftol` - limit on fidelity error change for convergence

dyn_type [string] Dynamics type, i.e. the type of matrix used to describe the dynamics. Options are `UNIT`, `GEN_MAT`, `SYMP` (see Dynamics classes for details).

dyn_params [dict] Parameters for the `qutip.control.dynamics.Dynamics` object. The key value pairs are assumed to be attribute name value pairs. They applied after the object is created.

prop_type [string] Propagator type i.e. the method used to calculate the propagators and propagator gradient for each timeslot options are `DEF`, `APPROX`, `DIAG`, `FRECHET`, `AUG_MAT` `DEF` will use the default for the specific `dyn_type` (see `PropagatorComputer` classes for details).

prop_params [dict] Parameters for the `PropagatorComputer` object. The key value pairs are assumed to be attribute name value pairs. They applied after the object is created.

- fid_type** [string] Fidelity error (and fidelity error gradient) computation method. Options are DEF, UNIT, TRACEDIFF, TD_APPROX. DEF will use the default for the specific dyn_type. (See *FidelityComputer* classes for details).
- fid_params** [dict] Parameters for the *FidelityComputer* object. The key value pairs are assumed to be attribute name value pairs. They applied after the object is created.
- tslot_type** [string] Method for computing the dynamics generators, propagators and evolution in the timeslots. Options: DEF, UPDATE_ALL, DYNAMIC UPDATE_ALL is the only one that currently works. (See *TimeslotComputer* classes for details).
- tslot_params** [dict] Parameters for the *TimeslotComputer* object. The key value pairs are assumed to be attribute name value pairs. They applied after the object is created.
- guess_pulse_type** [string, default None] Type / shape of pulse(s) used modulate the control amplitudes. Options include: RND, LIN, ZERO, SINE, SQUARE, TRIANGLE, SAW, GAUSSIAN.
- guess_pulse_params** [dict] Parameters for the guess pulse generator object. The key value pairs are assumed to be attribute name value pairs. They applied after the object is created.
- guess_pulse_action** [string, default 'MODULATE'] Determines how the guess pulse is applied to the pulse generated by the basis expansion. Options are: MODULATE, ADD.
- pulse_scaling** [float] Linear scale factor for generated guess pulses. By default initial pulses are generated with amplitudes in the range (-1.0, 1.0). These will be scaled by this parameter.
- pulse_offset** [float] Linear offset for the pulse. That is this value will be added to any guess pulses generated.
- ramping_pulse_type** [string] Type of pulse used to modulate the control pulse. It's intended use for a ramping modulation, which is often required in experimental setups. This is only currently implemented in CRAB. GAUSSIAN_EDGE was added for this purpose.
- ramping_pulse_params** [dict] Parameters for the ramping pulse generator object. The key value pairs are assumed to be attribute name value pairs. They applied after the object is created.
- log_level** [integer] level of messaging output from the logger. Options are attributes of `qutip.logging_utils`, in decreasing levels of messaging, are: DEBUG_INTENSE, DEBUG_VERBOSE, DEBUG, INFO, WARN, ERROR, CRITICAL. Anything WARN or above is effectively 'quiet' execution, assuming everything runs as expected. The default NOTSET implies that the level will be taken from the QuTiP settings file, which by default is WARN.
- out_file_ext** [string or None] Files containing the initial and final control pulse. Amplitudes are saved to the current directory. The default name will be postfixed with this extension. Setting this to None will suppress the output of files.
- gen_stats** [boolean] If set to True then statistics for the optimisation run will be generated - accessible through attributes of the stats object.

Returns

- opt** [OptimResult] Returns instance of OptimResult, which has attributes giving the reason for termination, final fidelity error, final evolution final amplitudes, statistics etc

```
opt_pulse_crab_unitary(H_d, H_c, U_0, U_targ, num_slots=None, evo_time=None,  
                        tau=None, amp_lbound=None, amp_ubound=None, fid_err_targ=1e-05,  
                        max_iter=500, max_wall_time=180, alg_params=None,  
                        num_coeffs=None, init_coeff_scaling=1.0, optim_params=None,  
                        optim_method='fmin', method_params=None, phase_option='PSU',  
                        dyn_params=None, prop_params=None, fid_params=None,  
                        tslot_type='DEF', tslot_params=None, guess_pulse_type=None,  
                        guess_pulse_params=None, guess_pulse_scaling=1.0,  
                        guess_pulse_offset=0.0, guess_pulse_action='MODULATE', ramp-  
ing_pulse_type=None, ramping_pulse_params=None, log_level=0,  
                        out_file_ext=None, gen_stats=False)
```

Optimise a control pulse to minimise the fidelity error, assuming that the dynamics of the system are generated by unitary operators. This function is simply a wrapper for `optimize_pulse`, where the appropriate options for unitary dynamics are chosen and the parameter names are in the format familiar to unitary dynamics. The dynamics of the system in any given timeslot are governed by the combined Hamiltonian, i.e. the sum of the $H_d + \text{ctrl_amp}[j] * H_c[j]$. The control pulse is an $[n_{ts}, n_{ctrls}]$ array of piecewise amplitudes.

The CRAB algorithm uses basis function coefficients as the variables to optimise. It does NOT use any gradient function. A multivariable optimisation algorithm attempts to determine the optimal values for the control pulse to minimise the fidelity error. The fidelity error is some measure of distance of the system evolution from the given target evolution in the time allowed for the evolution.

Parameters

H_d [Qobj or list of Qobj] Drift (aka system) the underlying Hamiltonian of the system can provide list (of length `num_slots`) for time dependent drift.

H_c [List of Qobj or array like $[num_slots, evo_time]$] A list of control Hamiltonians. These are scaled by the amplitudes to alter the overall dynamics. Array like input can be provided for time dependent control generators.

U_0 [Qobj] Starting point for the evolution. Typically the identity matrix.

U_targ [Qobj] Target transformation, e.g. gate or state, for the time evolution.

num_slots [integer or None] Number of timeslots. `None` implies that timeslots will be given in the `tau` array.

evo_time [float or None] Total time for the evolution. `None` implies that timeslots will be given in the `tau` array.

tau [array $[num_slots]$ of floats or None] Durations for the timeslots. If this is given then `num_slots` and `evo_time` are derived from it. `None` implies that timeslot durations will be equal and calculated as `evo_time/num_slots`.

amp_lbound [float or list of floats] Lower boundaries for the control amplitudes. Can be a scalar value applied to all controls or a list of bounds for each control.

amp_ubound [float or list of floats] Upper boundaries for the control amplitudes. Can be a scalar value applied to all controls or a list of bounds for each control.

fid_err_targ [float] Fidelity error target. Pulse optimisation will terminate when the fidelity error falls below this value.

max_iter [integer] Maximum number of iterations of the optimisation algorithm.

max_wall_time [float] Maximum allowed elapsed time for the optimisation algorithm.

alg_params [Dictionary] Options that are specific to the algorithm see above.

optim_params [Dictionary] The key value pairs are the attribute name and value used to set attribute values. Note: attributes are created if they do not exist already, and are overwritten if they do. Note: `method_params` are applied afterwards and so may override these.

coeff_scaling [float] Linear scale factor for the random basis coefficients. By default these range from -1.0 to 1.0. Note this is overridden by `alg_params` (if given there).

num_coeffs [integer] Number of coefficients used for each basis function. Note this is calculated automatically based on the dimension of the dynamics if not given. It is crucial to the performance of the algorithm that it is set as low as possible, while still giving high enough frequencies. Note this is overridden by `alg_params` (if given there).

optim_method [string] Multi-variable optimisation method. The only tested options are 'fmin' and 'Nelder-mead'. In theory any non-gradient method implemented in `scipy.optimize.minimize` could be used.

method_params [dict] Parameters for the `optim_method`. Note that where there is an attribute of the `Optimizer` object or the termination_conditions matching the key that attribute. Otherwise, and in some case also, they are assumed to be method_options for the `scipy.optimize.minimize` method. The commonly used parameter are:

- xtol - limit on variable change for convergence
- ftol - limit on fidelity error change for convergence

phase_option [string] Determines how global phase is treated in fidelity calculations (`fid_type='UNIT'` only). Options:

- PSU - global phase ignored
- SU - global phase included

dyn_params [dict] Parameters for the `Dynamics` object. The key value pairs are assumed to be attribute name value pairs. They applied after the object is created.

prop_params [dict] Parameters for the `PropagatorComputer` object. The key value pairs are assumed to be attribute name value pairs. They applied after the object is created.

fid_params [dict] Parameters for the `FidelityComputer` object. The key value pairs are assumed to be attribute name value pairs. They applied after the object is created.

tslot_type [string] Method for computing the dynamics generators, propagators and evolution in the timeslots. Options: DEF, UPDATE_ALL, DYNAMIC. UPDATE_ALL is the only one that currently works. (See `TimeslotComputer` classes for details).

tslot_params [dict] Parameters for the `TimeslotComputer` object. The key value pairs are assumed to be attribute name value pairs. They applied after the object is created.

guess_pulse_type [string, optional] Type / shape of pulse(s) used modulate the control amplitudes. Options include: RND, LIN, ZERO, SINE, SQUARE, TRIANGLE, SAW, GAUSSIAN.

guess_pulse_params [dict] Parameters for the guess pulse generator object. The key value pairs are assumed to be attribute name value pairs. They applied after the object is created.

guess_pulse_action [string, 'MODULATE'] Determines how the guess pulse is applied to the pulse generated by the basis expansion. Options are: MODULATE, ADD.

pulse_scaling [float] Linear scale factor for generated guess pulses. By default initial pulses are generated with amplitudes in the range (-1.0, 1.0). These will be scaled by this parameter.

pulse_offset [float] Linear offset for the pulse. That is this value will be added to any guess pulses generated.

ramping_pulse_type [string] Type of pulse used to modulate the control pulse. It's intended use for a ramping modulation, which is often required in experimental setups. This is only currently implemented in CRAB. GAUSSIAN_EDGE was added for this purpose.

ramping_pulse_params [dict] Parameters for the ramping pulse generator object. The key value pairs are assumed to be attribute name value pairs. They applied after the object is created.

log_level [integer] Level of messaging output from the logger. Options are attributes of `qutip.logging_utils`, in decreasing levels of messaging, are: `DEBUG_INTENSE`, `DEBUG_VERBOSE`, `DEBUG`, `INFO`, `WARN`, `ERROR`, `CRITICAL`. Anything `WARN` or above is effectively ‘quiet’ execution, assuming everything runs as expected. The default `NOTSET` implies that the level will be taken from the QuTiP settings file, which by default is `WARN`.

out_file_ext [string or None] Files containing the initial and final control pulse amplitudes are saved to the current directory. The default name will be postfixed with this extension. Setting this to `None` will suppress the output of files.

gen_stats [boolean] If set to `True` then statistics for the optimisation run will be generated - accessible through attributes of the stats object.

Returns

opt [OptimResult] Returns instance of *OptimResult*, which has attributes giving the reason for termination, final fidelity error, final evolution final amplitudes, statistics etc.

optimize_pulse (*drift*, *ctrls*, *initial*, *target*, *num_tslots=None*, *evo_time=None*, *tau=None*, *amp_lbound=None*, *amp_ubound=None*, *fid_err_targ=1e-10*, *min_grad=1e-10*, *max_iter=500*, *max_wall_time=180*, *alg='GRAPE'*, *alg_params=None*, *optim_params=None*, *optim_method='DEF'*, *method_params=None*, *optim_alg=None*, *max_metric_corr=None*, *accuracy_factor=None*, *dyn_type='GEN_MAT'*, *dyn_params=None*, *prop_type='DEF'*, *prop_params=None*, *fid_type='DEF'*, *fid_params=None*, *phase_option=None*, *fid_err_scale_factor=None*, *tslot_type='DEF'*, *tslot_params=None*, *amp_update_mode=None*, *init_pulse_type='DEF'*, *init_pulse_params=None*, *pulse_scaling=1.0*, *pulse_offset=0.0*, *ramping_pulse_type=None*, *ramping_pulse_params=None*, *log_level=0*, *out_file_ext=None*, *gen_stats=False*)

Optimise a control pulse to minimise the fidelity error. The dynamics of the system in any given timeslot are governed by the combined dynamics generator, i.e. the sum of the `drift + ctrl_amp[j]*ctrls[j]`.

The control pulse is an `[n_ts, n_ctrls]` array of piecewise amplitudes Starting from an initial (typically random) pulse, a multivariable optimisation algorithm attempts to determines the optimal values for the control pulse to minimise the fidelity error. The fidelity error is some measure of distance of the system evolution from the given target evolution in the time allowed for the evolution.

Parameters

drift [Qobj or list of Qobj] The underlying dynamics generator of the system can provide list (of length `num_tslots`) for time dependent drift.

ctrls [List of Qobj or array like `[num_tslots, evo_time]`] A list of control dynamics generators. These are scaled by the amplitudes to alter the overall dynamics. Array-like input can be provided for time dependent control generators.

initial [Qobj] Starting point for the evolution. Typically the identity matrix.

target [Qobj] Target transformation, e.g. gate or state, for the time evolution.

num_tslots [integer or None] Number of timeslots. `None` implies that timeslots will be given in the `tau` array.

evo_time [float or None] Total time for the evolution. `None` implies that timeslots will be given in the `tau` array.

tau [array[`num_tslots`] of floats or None] Durations for the timeslots. If this is given then `num_tslots` and `evo_time` are derived from it. `None` implies that timeslot durations will be equal and calculated as `evo_time/num_tslots`.

- amp_lbound** [float or list of floats] Lower boundaries for the control amplitudes. Can be a scalar value applied to all controls or a list of bounds for each control.
- amp_ubound** [float or list of floats] Upper boundaries for the control amplitudes. Can be a scalar value applied to all controls or a list of bounds for each control.
- fid_err_targ** [float] Fidelity error target. Pulse optimisation will terminate when the fidelity error falls below this value.
- mim_grad** [float] Minimum gradient. When the sum of the squares of the gradients wrt to the control amplitudes falls below this value, the optimisation terminates, assuming local minima.
- max_iter** [integer] Maximum number of iterations of the optimisation algorithm.
- max_wall_time** [float] Maximum allowed elapsed time for the optimisation algorithm.
- alg** [string] Algorithm to use in pulse optimisation. Options are:
- ‘GRAPE’ (default) - GRadient Ascent Pulse Engineering
 - ‘CRAB’ - Chopped RAndom Basis
- alg_params** [Dictionary] Options that are specific to the algorithm see above.
- optim_params** [Dictionary] The key value pairs are the attribute name and value used to set attribute values. Note: attributes are created if they do not exist already, and are overwritten if they do. Note: `method_params` are applied afterwards and so may override these.
- optim_method** [string] A `scipy.optimize.minimize` method that will be used to optimise the pulse for minimum fidelity error. Note that `FMIN`, `FMIN_BFGS` & `FMIN_L_BFGS_B` will all result in calling these specific `scipy.optimize` methods. Note the `LBFGSB` is equivalent to `FMIN_L_BFGS_B` for backwards compatibility reasons. Supplying `DEF` will given alg dependent result:
- GRAPE - Default `optim_method` is `FMIN_L_BFGS_B`
 - CRAB - Default `optim_method` is `FMIN`
- method_params** [dict] Parameters for the `optim_method`. Note that where there is an attribute of the `Optimizer` object or the `termination_conditions` matching the key that attribute. Otherwise, and in some case also, they are assumed to be `method_options` for the `scipy.optimize.minimize` method.
- optim_alg** [string] Deprecated. Use `optim_method`.
- max_metric_corr** [integer] Deprecated. Use `method_params` instead.
- accuracy_factor** [float] Deprecated. Use `method_params` instead.
- dyn_type** [string] Dynamics type, i.e. the type of matrix used to describe the dynamics. Options are `UNIT`, `GEN_MAT`, `SYMPL` (see *Dynamics* classes for details).
- dyn_params** [dict] Parameters for the *Dynamics* object. The key value pairs are assumed to be attribute name value pairs. They applied after the object is created.
- prop_type** [string] Propagator type i.e. the method used to calculate the propagators and propagator gradient for each timeslot options are `DEF`, `APPROX`, `DIAG`, `FRECHET`, `AUG_MAT`. `DEF` will use the default for the specific `dyn_type` (see *PropagatorComputer* classes for details).
- prop_params** [dict] Parameters for the *PropagatorComputer* object. The key value pairs are assumed to be attribute name value pairs. They applied after the object is created.
- fid_type** [string] Fidelity error (and fidelity error gradient) computation method. Options are `DEF`, `UNIT`, `TRACEDIFF`, `TD_APPROX`. `DEF` will use the default for the specific `dyn_type` (See *FidelityComputer* classes for details).

- fid_params** [dict] Parameters for the *FidelityComputer* object. The key value pairs are assumed to be attribute name value pairs. They applied after the object is created.
- phase_option** [string] Deprecated. Pass in `fid_params` instead.
- fid_err_scale_factor** [float] Deprecated. Use `scale_factor` key in `fid_params` instead.
- tslot_type** [string] Method for computing the dynamics generators, propagators and evolution in the timeslots. Options: DEF, UPDATE_ALL, DYNAMIC. UPDATE_ALL is the only one that currently works. (See *TimeslotComputer* classes for details.)
- tslot_params** [dict] Parameters for the *TimeslotComputer* object. The key value pairs are assumed to be attribute name value pairs. They applied after the object is created.
- amp_update_mode** [string] Deprecated. Use `tslot_type` instead.
- init_pulse_type** [string] Type / shape of pulse(s) used to initialise the control amplitudes. Options (GRAPE) include: RND, LIN, ZERO, SINE, SQUARE, TRIANGLE, SAW. Default is RND. (see *PulseGen* classes for details). For the CRAB the this the `guess_pulse_type`.
- init_pulse_params** [dict] Parameters for the initial / guess pulse generator object. The key value pairs are assumed to be attribute name value pairs. They applied after the object is created.
- pulse_scaling** [float] Linear scale factor for generated initial / guess pulses. By default initial pulses are generated with amplitudes in the range (-1.0, 1.0). These will be scaled by this parameter.
- pulse_offset** [float] Linear offset for the pulse. That is this value will be added to any initial / guess pulses generated.
- ramping_pulse_type** [string] Type of pulse used to modulate the control pulse. It's intended use for a ramping modulation, which is often required in experimental setups. This is only currently implemented in CRAB. GAUSSIAN_EDGE was added for this purpose.
- ramping_pulse_params** [dict] Parameters for the ramping pulse generator object. The key value pairs are assumed to be attribute name value pairs. They applied after the object is created.
- log_level** [integer] Level of messaging output from the logger. Options are attributes of `qutip.logging_utils`, in decreasing levels of messaging, are: DEBUG_INTENSE, DEBUG_VERBOSE, DEBUG, INFO, WARN, ERROR, CRITICAL. Anything WARN or above is effectively 'quiet' execution, assuming everything runs as expected. The default NOTSET implies that the level will be taken from the QuTiP settings file, which by default is WARN.
- out_file_ext** [string or None] Files containing the initial and final control pulse amplitudes are saved to the current directory. The default name will be postfixed with this extension. Setting this to None will suppress the output of files.
- gen_stats** [boolean] If set to True then statistics for the optimisation run will be generated - accessible through attributes of the stats object.

Returns

- opt** [OptimResult] Returns instance of *OptimResult*, which has attributes giving the reason for termination, final fidelity error, final evolution final amplitudes, statistics etc.

```
optimize_pulse_unitary (H_d, H_c, U_0, U_targ, num_tslots=None, evo_time=None, tau=None,
amp_lbound=None, amp_ubound=None, fid_err_targ=1e-10,
min_grad=1e-10, max_iter=500, max_wall_time=180, alg='GRAPE',
alg_params=None, optim_params=None, optim_method='DEF',
method_params=None, optim_alg=None, max_metric_corr=None,
accuracy_factor=None, phase_option='PSU', dyn_params=None,
prop_params=None, fid_params=None, tslot_type='DEF',
tslot_params=None, amp_update_mode=None, init_pulse_type='DEF',
init_pulse_params=None, pulse_scaling=1.0, pulse_offset=0.0, ramping_pulse_type=None,
ramping_pulse_params=None, log_level=0, out_file_ext=None, gen_stats=False)
```

Optimise a control pulse to minimise the fidelity error, assuming that the dynamics of the system are generated by unitary operators. This function is simply a wrapper for `optimize_pulse`, where the appropriate options for unitary dynamics are chosen and the parameter names are in the format familiar to unitary dynamics. The dynamics of the system in any given timeslot are governed by the combined Hamiltonian, i.e. the sum of the $H_d + \text{ctrl_amp}[j] * H_c[j]$. The control pulse is an $[n_{\text{ts}}, n_{\text{ctrls}}]$ array of piecewise amplitudes. Starting from an initial (typically random) pulse, a multivariable optimisation algorithm attempts to determine the optimal values for the control pulse to minimise the fidelity error. The maximum fidelity for a unitary system is 1, i.e. when the time evolution resulting from the pulse is equivalent to the target. And therefore the fidelity error is $1 - \text{fidelity}$.

Parameters

H_d [Qobj or list of Qobj] Drift (aka system) the underlying Hamiltonian of the system can provide list (of length `num_tslots`) for time dependent drift.

H_c [List of Qobj or array like $[\text{num_tslots}, \text{evo_time}]$] A list of control Hamiltonians. These are scaled by the amplitudes to alter the overall dynamics. Array-like input can be provided for time dependent control generators.

U_0 [Qobj] Starting point for the evolution. Typically the identity matrix.

U_targ [Qobj] Target transformation, e.g. gate or state, for the time evolution.

num_tslots [integer or None] Number of timeslots. `None` implies that timeslots will be given in the `tau` array.

evo_time [float or None] Total time for the evolution. `None` implies that timeslots will be given in the `tau` array.

tau [array[`num_tslots`] of floats or None] Durations for the timeslots. If this is given then `num_tslots` and `evo_time` are derived from it. `None` implies that timeslot durations will be equal and calculated as `evo_time/num_tslots`.

amp_lbound [float or list of floats] Lower boundaries for the control amplitudes. Can be a scalar value applied to all controls or a list of bounds for each control.

amp_ubound [float or list of floats] Upper boundaries for the control amplitudes. Can be a scalar value applied to all controls or a list of bounds for each control.

fid_err_targ [float] Fidelity error target. Pulse optimisation will terminate when the fidelity error falls below this value.

min_grad [float] Minimum gradient. When the sum of the squares of the gradients wrt to the control amplitudes falls below this value, the optimisation terminates, assuming local minima.

max_iter [integer] Maximum number of iterations of the optimisation algorithm.

max_wall_time [float] Maximum allowed elapsed time for the optimisation algorithm.

alg [string] Algorithm to use in pulse optimisation. Options are:

- 'GRAPE' (default) - GRAdient Ascent Pulse Engineering
- 'CRAB' - Chopped Random Basis

alg_params [Dictionary] options that are specific to the algorithm see above

optim_params [Dictionary] The key value pairs are the attribute name and value used to set attribute values. Note: attributes are created if they do not exist already, and are overwritten if they do. Note: method_params are applied afterwards and so may override these.

optim_method [string] A `scipy.optimize.minimize` method that will be used to optimise the pulse for minimum fidelity error Note that `FMIN`, `FMIN_BFGS` & `FMIN_L_BFGS_B` will all result in calling these specific `scipy.optimize` methods Note the `LBFGSB` is equivalent to `FMIN_L_BFGS_B` for backwards compatibility reasons. Supplying `DEF` will given algorithm-dependent result:

- GRAPE - Default `optim_method` is `FMIN_L_BFGS_B`
- CRAB - Default `optim_method` is `FMIN`

method_params [dict] Parameters for the `optim_method`. Note that where there is an attribute of the *Optimizer* object or the `termination_conditions` matching the key that attribute. Otherwise, and in some case also, they are assumed to be method_options for the `scipy.optimize.minimize` method.

optim_alg [string] Deprecated. Use `optim_method`.

max_metric_corr [integer] Deprecated. Use `method_params` instead.

accuracy_factor [float] Deprecated. Use `method_params` instead.

phase_option [string] Determines how global phase is treated in fidelity calculations (`fid_type='UNIT'` only). Options:

- PSU - global phase ignored
- SU - global phase included

dyn_params [dict] Parameters for the *Dynamics* object. The key value pairs are assumed to be attribute name value pairs. They applied after the object is created.

prop_params [dict] Parameters for the *PropagatorComputer* object. The key value pairs are assumed to be attribute name value pairs. They applied after the object is created.

fid_params [dict] Parameters for the *FidelityComputer* object. The key value pairs are assumed to be attribute name value pairs. They applied after the object is created.

tslot_type [string] Method for computing the dynamics generators, propagators and evolution in the timeslots. Options: `DEF`, `UPDATE_ALL`, `DYNAMIC`. `UPDATE_ALL` is the only one that currently works. (See *TimeslotComputer* classes for details.)

tslot_params [dict] Parameters for the *TimeslotComputer* object. The key value pairs are assumed to be attribute name value pairs. They applied after the object is created.

amp_update_mode [string] Deprecated. Use `tslot_type` instead.

init_pulse_type [string] Type / shape of pulse(s) used to initialise the control amplitudes. Options (GRAPE) include: `RND`, `LIN`, `ZERO`, `SINE`, `SQUARE`, `TRIANGLE`, `SAW`. `DEF` is `RND`. (see *PulseGen* classes for details.) For the CRAB the this the `guess_pulse_type`.

init_pulse_params [dict] Parameters for the initial / guess pulse generator object. The key value pairs are assumed to be attribute name value pairs. They applied after the object is created.

pulse_scaling [float] Linear scale factor for generated initial / guess pulses. By default initial pulses are generated with amplitudes in the range `(-1.0, 1.0)`. These will be scaled by this parameter.

pulse_offset [float] Linear offset for the pulse. That is this value will be added to any initial / guess pulses generated.

ramping_pulse_type [string] Type of pulse used to modulate the control pulse. It's intended use for a ramping modulation, which is often required in experimental setups. This is only currently implemented in CRAB. GAUSSIAN_EDGE was added for this purpose.

ramping_pulse_params [dict] Parameters for the ramping pulse generator object. The key value pairs are assumed to be attribute name value pairs. They applied after the object is created.

log_level [integer] Level of messaging output from the logger. Options are attributes of `qutip.logging_utils` in decreasing levels of messaging, are: DEBUG_INTENSE, DEBUG_VERBOSE, DEBUG, INFO, WARN, ERROR, CRITICAL. Anything WARN or above is effectively 'quiet' execution, assuming everything runs as expected. The default NOTSET implies that the level will be taken from the QuTiP settings file, which by default is WARN.

out_file_ext [string or None] Files containing the initial and final control pulse amplitudes are saved to the current directory. The default name will be postfixed with this extension. Setting this to None will suppress the output of files.

gen_stats [boolean] If set to True then statistics for the optimisation run will be generated - accessible through attributes of the stats object.

Returns

opt [OptimResult] Returns instance of *OptimResult*, which has attributes giving the reason for termination, final fidelity error, final evolution final amplitudes, statistics etc.

Pulse generator - Generate pulses for the timeslots Each class defines a `gen_pulse` function that produces a float array of size `num_tsots`. Each class produces a differ type of pulse. See the class and `gen_pulse` function descriptions for details

create_pulse_gen (*pulse_type='RND', dyn=None, pulse_params=None*)

Create and return a pulse generator object matching the given type. The pulse generators each produce a different type of pulse, see the `gen_pulse` function description for details. These are the random pulse options:

RND - Independent random value in each timeslot RNDFOURIER - Fourier series with random coefficients RNDWAVES - Summation of random waves RNDWALK1 - Random change in amplitude each timeslot RNDWALK2 - Random change in amp gradient each timeslot

These are the other non-periodic options:

LIN - Linear, i.e. constant gradient over the time ZERO - special case of the LIN pulse, where the gradient is 0

These are the periodic options

SINE - Sine wave SQUARE - Square wave SAW - Saw tooth wave TRIANGLE - Triangular wave

If a Dynamics object is passed in then this is used to instantiate the PulseGen, meaning that some timeslot and amplitude properties are copied over.

5.2.8 Utility Functions

Utility Functions

This module contains utility functions that are commonly needed in other qutip modules.

clebsch (*j1, j2, j3, m1, m2, m3*)

Calculates the Clebsch-Gordon coefficient for coupling (*j1, m1*) and (*j2, m2*) to give (*j3, m3*).

Parameters

- j1** [float] Total angular momentum 1.
- j2** [float] Total angular momentum 2.
- j3** [float] Total angular momentum 3.
- m1** [float] z-component of angular momentum 1.
- m2** [float] z-component of angular momentum 2.
- m3** [float] z-component of angular momentum 3.

Returns

- cg_coeff** [float] Requested Clebsch-Gordan coefficient.

convert_unit (*value, orig='meV', to='GHz'*)

Convert an energy from unit *orig* to unit *to*.

Parameters

- value** [float / array] The energy in the old unit.
- orig** [string] The name of the original unit ("J", "eV", "meV", "GHz", "mK")
- to** [string] The name of the new unit ("J", "eV", "meV", "GHz", "mK")

Returns

- value_new_unit** [float / array] The energy in the new unit.

n_thermal (*w, w_th*)

Return the number of photons in thermal equilibrium for an harmonic oscillator mode with frequency 'w', at the temperature described by 'w_th' where $\omega_{th} = k_B T / \hbar$.

Parameters

- w** [float or array] Frequency of the oscillator.
- w_th** [float] The temperature in units of frequency (or the same units as *w*).

Returns

- n_avg** [float or array] Return the number of average photons in thermal equilibrium for a an oscillator with the given frequency and temperature.

File I/O Functions

file_data_read (*filename, sep=None*)

Retrieves an array of data from the requested file.

Parameters

- filename** [str or pathlib.Path] Name of file containing requested data.
- sep** [str] Separator used to store data.

Returns

- data** [array_like] Data from selected file.

file_data_store (*filename, data, numtype='complex', numformat='decimal', sep=','*)
Stores a matrix of data to a file to be read by an external program.

Parameters

filename [str or pathlib.Path] Name of data file to be stored, including extension.
data: array_like Data to be written to file.
numtype [str { 'complex', 'real' }] Type of numerical data.
numformat [str { 'decimal', 'exp' }] Format for written data.
sep [str] Single-character field separator. Usually a tab, space, comma, or semicolon.

qload (*name*)
Loads data file from file named 'filename.qu' in current directory.

Parameters

name [str or pathlib.Path] Name of data file to be loaded.

Returns

qobject [instance / array_like] Object retrieved from requested file.

qsave (*data, name='qutip_data'*)
Saves given data to file named 'filename.qu' in current directory.

Parameters

data [instance/array_like] Input Python object to be stored.
filename [str or pathlib.Path] Name of output data file.

Parallelization

This module provides functions for parallel execution of loops and function mappings, using the builtin Python module multiprocessing or the loky parallel execution library.

parallel_map (*task, values, task_args=None, task_kwargs=None, reduce_func=None, map_kw=None, progress_bar=None, progress_bar_kwargs={}*)
Parallel execution of a mapping of *values* to the function *task*. This is functionally equivalent to:

```
result = [task(value, *task_args, **task_kwargs) for value in values]
```

Parameters

task [a Python function] The function that is to be called for each value in *task_vec*.
values [array / list] The list or array of values for which the *task* function is to be evaluated.
task_args [list / dictionary] The optional additional argument to the *task* function.
task_kwargs [list / dictionary] The optional additional keyword argument to the *task* function.
reduce_func [func (optional)] If provided, it will be called with the output of each tasks instead of storing a them in a list. Note that the order in which results are passed to *reduce_func* is not defined.
progress_bar [string] Progress bar options's string for showing progress.
progress_bar_kwargs [dict] Options for the progress bar.
map_kw: dict (optional) Dictionary containing entry for: - *timeout*: float, Maximum time (sec) for the whole map. - *job_timeout*: float, Maximum time (sec) for each job in the

`map`. - `num_cpus`: int, Number of job to run at once. - `fail_fast`: bool, Raise an error at the first.

Returns

result [list] The result list contains the value of `task(value, *task_args, **task_kwargs)` for each value in `values`. If a `reduce_func` is provided, and empty list will be returned.

serial_map (*task, values, task_args=None, task_kwargs=None, reduce_func=None, map_kw=None, progress_bar=None, progress_bar_kwargs={}*)
Serial mapping function with the same call signature as `parallel_map`, for easy switching between serial and parallel execution. This is functionally equivalent to:

```
result = [task(value, *task_args, **task_kwargs) for value in values]
```

This function work as a drop-in replacement of `qutip.parallel_map`.

Parameters

task [a Python function] The function that is to be called for each value in `task_vec`.
values [array / list] The list or array of values for which the `task` function is to be evaluated.
task_args [list / dictionary] The optional additional argument to the `task` function.
task_kwargs [list / dictionary] The optional additional keyword argument to the `task` function.
reduce_func [func (optional)] If provided, it will be called with the output of each tasks instead of storing a them in a list.
progress_bar [string] Progress bar options's string for showing progress.
progress_bar_kwargs [dict] Options for the progress bar.
map_kw: dict (optional) Dictionary containing: - `timeout`: float, Maximum time (sec) for the whole map. - `fail_fast`: bool, Raise an error at the first.

Returns

result [list] The result list contains the value of `task(value, *task_args, **task_kwargs)` for each value in `values`. If a `reduce_func` is provided, and empty list will be returned.

Semidefinite Programming

IPython Notebook Tools

This module contains utility functions for using QuTiP with IPython notebooks.

parallel_map (*task, values, task_args=None, task_kwargs=None, client=None, view=None, progress_bar=None, show_scheduling=False, **kwargs*)
Call the function `task` for each value in `values` using a cluster of IPython engines. The function `task` should have the signature `task(value, *args, **kwargs)`.

The `client` and `view` are the `IPython.parallel` client and load-balanced view that will be used in the parfor execution. If these are `None`, new instances will be created.

Parameters

task: a Python function The function that is to be called for each value in `task_vec`.
values: array / list The list or array of values for which the `task` function is to be evaluated.

task_args: list / dictionary The optional additional argument to the `task` function.

task_kwargs: list / dictionary The optional additional keyword argument to the `task` function.

client: `IPython.parallel.Client` The `IPython.parallel` Client instance that will be used in the `parfor` execution.

view: a `IPython.parallel.Client` view The view that is to be used in scheduling the tasks on the `IPython` cluster. Preferably a load-balanced view, which is obtained from the `IPython.parallel.Client` instance `client` by calling, `view = client.load_balanced_view()`.

show_scheduling: bool {False, True}, default False Display a graph showing how the tasks (the evaluation of `task` for for the value in `task_vec1`) was scheduled on the `IPython` engine cluster.

show_progressbar: bool {False, True}, default False Display a HTML-based progress bar during the execution of the `parfor` loop.

Returns

result [list] The result list contains the value of `task(value, task_args, task_kwargs)` for each value in `values`.

version_table (*verbose=False*)

Print an HTML-formatted table with version numbers for QuTiP and its dependencies. Use it in a `IPython` notebook to show which versions of different packages that were used to run the notebook. This should make it possible to reproduce the environment and the calculation later on.

Returns

version_table: string Return an HTML-formatted string containing version information for QuTiP dependencies.

Miscellaneous

about ()

About box for QuTiP. Gives version numbers for QuTiP, NumPy, SciPy, Cython, and Matplotlib.

simdiag (*ops, evals: bool = True, *, tol: float = 1e-14, safe_mode: bool = True*)

Simultaneous diagonalization of commuting Hermitian matrices.

Parameters

ops [list/array] list or array of qobjs representing commuting Hermitian operators.

evals [bool [True]] Whether to return the eigenvalues for each ops and eigenvectors or just the eigenvectors.

tol [float [1e-14]] Tolerance for detecting degenerate eigenstates.

safe_mode [bool [True]] Whether to check that all ops are Hermitian and commuting. If set to `False` and operators are not commuting, the eigenvectors returned will often be eigenvectors of only the first operator.

Returns

eigs [tuple] Tuple of arrays representing eigvecs and eigvals of quantum objects corresponding to simultaneous eigenvectors and eigenvalues for each operator.

Chapter 6

Change Log

6.1 Version 5.0.0a1 (February 7, 2023)

QuTiP 5 is a redesign of many of the core components of QuTiP (`Qobj`, `QobjEvo`, solvers) to make them more consistent and more flexible.

`Qobj` may now be stored in either sparse or dense representations, and the two may be mixed sensibly as needed. `QobjEvo` is now used consistently throughout QuTiP, and the implementation has been substantially cleaned up. A new `Coefficient` class is used to represent the time-dependent factors inside `QobjEvo`.

The solvers have been rewritten to work well with the new data layer and the concept of `Integrators` which solve ODEs has been introduced. In future, new data layers may provide their own `Integrators` specialized to their representation of the underlying data.

Much of the user-facing API of QuTiP remains familiar, but there have had to be many small breaking changes. If we can make changes to easy migrating code from QuTiP 4 to QuTiP 5, please let us know.

Any extensive list of changes follows.

6.1.1 Contributors

QuTiP 5 has been a large effort by many people over the last three years.

In particular:

- Jake Lishman led the implementation of the new data layer and coefficients.
- Eric Giguère led the implementation of the new `QobjEvo` interface and solvers.
- Boxi Li led the updating of QuTiP's QIP support and the creation of `qutip_qip`.

Other members of the QuTiP Admin team have been heavily involved in reviewing, testing and designing QuTiP 5:

- Alexander Pitchford
- Asier Galicia
- Nathan Shammah
- Shahnawaz Ahmed
- Neill Lambert
- Simon Cross

Two Google Summer of Code contributors updated the tutorials and benchmarks to QuTiP 5:

- Christian Staufienbiel updated many of the tutorials (<<https://github.com/qutip/qutip-tutorials/>>).

- Xavier Sproken update the benchmarks (<https://github.com/qutip/qutip-benchmark/>).

Four experimental data layers backends were written either as part of Google Summer of Code or as separate projects. While these are still alpha quality, they helped significantly to test the data layer API:

- `qutip-tensorflow`: a TensorFlow backend by Asier Galicia (<https://github.com/qutip/qutip-tensorflow>)
- `qutip-cupy`: a CuPy GPU backend by Felipe Bivort Haiek (<https://github.com/qutip/qutip-cupy/>)
- `qutip-tensornetwork`: a TensorNetwork backend by Asier Galicia (<https://github.com/qutip/qutip-tensornetwork>)
- `qutip-jax`: a JAX backend by Eric Giguère (<https://github.com/qutip/qutip-jax/>)

We have also had many other contributors, whose specific contributions are detailed below:

- Pieter Eendebak (updated the required SciPy to 1.4+, #1982 <https://github.com/qutip/qutip/pull/1982>).
- Pieter Eendebak (reduced import times by setting logger names, #1981 <https://github.com/qutip/qutip/pull/1981>)
- Xavier Sproken (included C header files in the source distribution, #1971 <https://github.com/qutip/qutip/pull/1971>)
- Christian Staufenbiel (added support for multiple collapse operators to the Floquet solver, #1962 <https://github.com/qutip/qutip/pull/1962>)
- Christian Staufenbiel (fixed the basis used in the Floquet Master Equation solver, #1952 <https://github.com/qutip/qutip/pull/1952>)
- Christian Staufenbiel (allowed the `bloch_redfield_tensor` function to accept strings and callables for `a_ops`, #1951 <https://github.com/qutip/qutip/pull/1951>)
- Henrique Silvéro (allowed `qutip_qip` to be imported as `qutip.qip`, #1920 <https://github.com/qutip/qutip/pull/1920>)
- Florian Hopfmueller (added a vastly improved implementations of `process_fidelity` and `average_gate_fidelity`, #1712 <https://github.com/qutip/qutip/pull/1712>, #1748 <https://github.com/qutip/qutip/pull/1748>, #1788 <https://github.com/qutip/qutip/pull/1788>)
- Felipe Bivort Haiek (fixed inaccuracy in docstring of the dense implementation of negation, #1608 <https://github.com/qutip/qutip/pull/1608>)
- Rajath Shetty (added support for specifying colors for individual points, vectors and states display by `qutip.Bloch`, #1335 <https://github.com/qutip/qutip/pull/1335>)

6.1.2 Qobj changes

Previously `Qobj` data was stored in a SciPy-like sparse matrix. Now the representation is flexible. Implementations for dense and sparse formats are included in QuTiP and custom implementations are possible. QuTiP's performance on dense states and operators is significantly improved as a result.

Some highlights:

- The data is still accessible via the `.data` attribute, but is now an instance of the underlying data type instead of a SciPy-like sparse matrix. The operations available in `qutip.core.data` may be used on `.data`, regardless of the data type.
- `Qobj` with different data types may be mixed in arithmetic and other operations. A sensible output type will be automatically determined.
- The new `.to(...)` method may be used to convert a `Qobj` from one data type to another. E.g. `.to("dense")` will convert to the dense representation and `.to("csr")` will convert to the sparse type.
- Many `Qobj` methods and methods that create `Qobj` now accepted a `dtype` parameter that allows the data type of the returned `Qobj` to be specified.

- The new `&` operator may be used to obtain the tensor product.
- The new `@` operator may be used to obtain the matrix / operator product. `bar @ ket` returns a scalar.
- The new `.contract()` method will collapse 1D subspaces of the dimensions of the `Qobj`.
- The new `.logm()` method returns the matrix logarithm of an operator.
- The methods `.set_data`, `.get_data`, `.extract_state`, `.eliminate_states`, `.evaluate` and `.check_isunitary` have been removed.

6.1.3 QobjEvo changes

The `QobjEvo` type for storing time-dependent quantum objects has been significantly expanded, standardized and extended. The time-dependent coefficients are now represented using a new `Coefficient` type that may be independently created and manipulated if required.

Some highlights:

- The `.compile()` method has been removed. Coefficients specified as strings are automatically compiled if possible and the compilation is cached across different Python runs and instances.
- Mixing coefficient types within a single `Qobj` is now supported.
- Many new attributes were added to `QobjEvo` for convenience. Examples include `.dims`, `.shape`, `.superrep` and `.isconstant`.
- Many old attributes such as `.cte`, `.use_cython`, `.type`, `.const`, and `.coeff_file` were removed.
- A new `Spline` coefficient supports spline interpolations of different orders. The old `Cubic_Spline` coefficient has been removed.
- The new `.arguments(...)` method allows additional arguments to the underlying coefficient functions to be updated.
- The `_step_func_coeff` argument has been replaced by the `order` parameter. `_step_func_coeff=False` is equivalent to `order=3`. `_step_func_coeff=True` is equivalent to `order=0`. Higher values of `order` gives spline interpolations of higher orders.

6.1.4 Solver changes

The solvers in QuTiP have been heavily reworked and standardized. Under the hood solvers now make use of swappable ODE Integrators. Many Integrators are included (see the list below) and custom implementations are possible. Solvers now consistently accept a `QobjEvo` instance at the Hamiltonian or Liouvillian, or any object which can be passed to the `QobjEvo` constructor.

A breakdown of highlights follows.

All solvers:

- Solver options are now supplied in an ordinary Python dict. `qutip.Options` is deprecated and returns a dict for backwards compatibility.
- A specific ODE integrator may be selected by supplying a `method` option.
- Each solver provides a class interface. Creating an instance of the class allows a solver to be run multiple times for the same system without having to repeatedly reconstruct the right-hand side of the ODE to be integrated.
- A `QobjEvo` instance is accepted for most operators, e.g., `H`, `c_ops`, `e_ops`, `a_ops`.
- The progress bar is now selected using the `progress_bar` option. A new progress bar using the `tqdm` Python library is provided.
- Dynamic arguments, where the value of an operator depends on the current state of the evolution, have been removed. They may be re-implemented later if there is demand for them.

Integrators:

- The SciPy `zode` integrator is available with the BDF and Adams methods as `bdf` and `adams`.
- The SciPy `dop853` integrator (an eighth order Runge-Kutta method by Dormand & Prince) is available as `dop853`.
- The SciPy `lsoda` integrator is available as `lsoda`.
- QuTiP's own implementation of Verner's "most efficient" Runge-Kutta methods of order 7 and 9 are available as `vern7` and `vern9`. See <http://people.math.sfu.ca/~jverner/> for a description of the methods.
- QuTiP's own implementation of a solver that directly diagonalizes the system to be integrated is available as `diag`. It only works on time-independent systems and is slow to setup, but once the diagonalization is complete, it generates solutions very quickly.
- QuTiP's own implementation of an approximate Krylov subspace integrator is available as `krylov`. This integrator is only usable with `sesolve`.

Result class:

- A new `.e_data` attribute provides expectation values as a dictionary. Unlike `.expect`, the values are provided in a Python list rather than a numpy array, which better supports non-numeric types.
- The contents of the `.stats` attribute changed significantly and is now more consistent across solvers.

Monte-Carlo Solver (mcsolve):

- The system, `H`, may now be a super-operator.
- The `seed` parameter now supports supplying numpy `SeedSequence` or `Generator` types.
- The new `timeout` and `target_tol` parameters allow the solver to exit early if a timeout or target tolerance is reached.
- The `ntraj` option no longer supports a list of numbers of trajectories. Instead, just run the solver multiple times and use the class `MCSolver` if setting up the solver uses a significant amount of time.
- The `map_func` parameter has been replaced by the `map` option. In addition to the existing `serial` and `parallel` values, the value `loky` may be supplied to use the `loky` package to parallelize trajectories.
- The result returned by `mcsolve` now supports calculating photocurrents and calculating the steady state over `N` trajectories.
- The old `parfor` parallel execution function has been removed from `qutip.parallel`. Use `parallel_map` or `loky_map` instead.

Bloch-Redfield Master Equation Solver (brmesolve):

- The `a_ops` and `spectra` support implementations have been heavily reworked to reuse the techniques from the new `Coefficient` and `QobjEvo` classes.
- The `use_secular` parameter has been removed. Use `sec_cutoff=-1` instead.
- The required tolerance is now read from `qutip.settings`.

Krylov Subspace Solver (krylovsolve):

- The Krylov solver is now implemented using `SESolver` and the `krylov` ODE integrator. The function `krylovsolve` is maintained for convenience and now supports many more options.
- The `sparse` parameter has been removed. Supply a sparse `Qobj` for the Hamiltonian instead.

Floquet Solver (fsesolve and fmmesolve):

- The Floquet solver has been rewritten to use a new `FloquetBasis` class which manages the transformations from `lab` to Floquet basis and back.
- Many of the internal methods used by the old Floquet solvers have been removed. The Floquet tensor may still be retrieved using the function `floquet_tensor`.

- The Floquet Markov Master Equation solver has had many changes and new options added. The environment temperature may be specified using `w_th`, and the result states are stored in the lab basis and optionally in the Floquet basis using `store_floquet_state`.
- The spectra functions supplied to `fmmsolve` must now be vectorized (i.e. accept and return numpy arrays for frequencies and densities) and must accept negative frequency (i.e. usually include a $w > 0$ factor so that the returned densities are zero for negative frequencies).
- The number of sidebands to keep, `kmax` may only be supplied when using the `FMESolver`
- The `Tsteps` parameter has been removed from both `fsesolve` and `fmmsolve`. The `precompute` option to `FloquetBasis` may be used instead.

Evolution of State Solver (`essolve`):

- The function `essolve` has been removed. Use the `diag` integration method with `sesolve` or `mesolve` instead.

Steady-state solvers (`steadystate` module):

- The `method` parameter and `solver` parameters have been separated. Previously they were mixed together in the `method` parameter.
- The previous options are now passed as parameters to the steady state solver and mostly passed through to the underlying SciPy functions.
- The logging and statistics have been removed.

Correlation functions (`correlation` module):

- A new `correlation_3op` function has been added. It supports `MESolver` or `BRMESolver`.
- The `correlation`, `correlation_4op`, and `correlation_ss` functions have been removed.
- Support for calculating correlation with `mcsolve` has been removed.

Propagators (`propagator` module):

- A class interface, `qutip.Propagator`, has been added for propagators.
- Propagation of time-dependent systems is now supported using `QobjEvo`.
- The `unitary_mode` and `parallel` options have been removed.

Correlation spectra (`spectrum` module):

- The functions `spectrum_ss` and `spectrum_pi` have been removed and are now internal functions.
- The `use_pinv` parameter for `spectrum` has been removed and the functionality merged into the `solver` parameter. Use `solver="pi"` instead.

6.1.5 QuTiP core

There have been numerous other small changes to core QuTiP features:

- `qft(...)` the function that returns the quantum Fourier transform operator was moved from `qutip.qip.algorithm` into `qutip`.
- The Bloch-Redfield solver tensor, `brtensor`, has been moved into `qutip.core`. See the section above on the Bloch-Redfield solver for details.
- The functions `mat2vec` and `vec2mat` for transforming states to and from super-operator states have been renamed to `stack_columns` and `unstack_columns`.
- The function `liouvillian_ref` has been removed. Used `liouvillian` instead.
- The `superoperator` transforms `super_to_choi`, `choi_to_super`, `choi_to_kraus`, `choi_to_chi` and `chi_to_choi` have been removed. Used `to_choi`, `to_super`, `to_kraus` and `to_chi` instead.

- All of the random object creation functions now accepted a numpy `Generator` as a seed.
- The `dims` parameter of all random object creation functions has been removed. Supply the dimensions as the first parameter if explicit dimensions are required.
- The function `rand_unitary_haar` has been removed. Use `rand_unitary(distribution="haar")` instead.
- The functions `rand_dm_hs` and `rand_dm_ginibre` have been removed. Use `rand_dm(distribution="hs")` and `rand_dm(distribution="ginibre")` instead.
- The function `rand_ket_haar` has been removed. Use `rand_ket(distribution="haar")` instead.
- The measurement functions have had the `target` parameter for expanding the measurement operator removed. Used `expand_operator` to expand the operator instead.
- `qutip.Bloch` now supports applying colours per-point, state or vector in `add_point`, `add_states`, and `add_vectors`.

6.1.6 QuTiP settings

Previously `qutip.settings` was an ordinary module. Now `qutip.settings` is an instance of a settings class. All the runtime modifiable settings for core operations are in `qutip.settings.core`. The other settings are not modifiable at runtime.

- Removed `load`, `reset` and `save` functions.
- Removed `.debug`, `.fortran`, `.openmp_thresh`.
- New `.compile` stores the compilation options for compiled coefficients.
- New `.core["rtol"]` core option gives the default relative tolerance used by QuTiP.
- The absolute tolerance setting `.atol` has been moved to `.core["atol"]`.

6.1.7 Package reorganization

- `qutip.qip` has been moved into its own package, `qutip-qip`. Once installed, `qutip-qip` is available as either `qutip.qip` or `qutip_qip`. Some widely useful gates have been retained in `qutip.gates`.
- `qutip.lattice` has been moved into its own package, `qutip-lattice`. It is available from <https://github.com/qutip/qutip-lattice>.
- `qutip.sparse` has been removed. It contained the old sparse matrix representation and is replaced by the new implementation in `qutip.data`.
- `qutip.piqs` functions are no longer available from the `qutip` namespace. They are accessible from `qutip.piqs` instead.

6.1.8 Miscellaneous

- Support has been added for 64-bit integer sparse matrix indices, allowing sparse matrices with up to 2^{63} rows and columns. This support needs to be enabled at compilation time by calling `setup.py` and passing `--with-idxint-64`.

6.1.9 Feature removals

- Support for OpenMP has been removed. If there is enough demand and a good plan for how to organize it, OpenMP support may return in a future QuTiP release.
- The `qutip.parfor` function has been removed. Use `qutip.parallel_map` instead.
- `qutip.graph` has been removed and replaced by SciPy's graph functions.
- `qutip.topology` has been removed. It contained only one function `berry_curvature`.
- The `~/qutip/qutiprc` config file is no longer supported. It contained settings for the OpenMP support.

6.2 Version 4.7.1 (December 11, 2022)

This is a bugfix release for QuTiP 4.7.X. In addition to the minor fixes listed below, the release adds builds for Python 3.11 and support for packaging 22.0.

6.2.1 Features

- Improve `qutip` import times by setting logger names explicitly. (#1980)

6.2.2 Bug Fixes

- Change `floquet_master_equation_rates(...)` to use an adaptive number of time steps scaled by the number of sidebands, `kmax`. (#1961)
- Change `fidelity(A, B)` to use the reduced fidelity formula for pure states which is more numerically efficient and accurate. (#1964)
- Change `brmesolve` to raise an exception when ode integration is not successful. (#1965)
- Backport fix for IPython helper `Bloch._repr_svg_` from dev.major. Previously the `print_figure` function returned bytes, but since `ipython/ipython#5452` (in 2014) it returns a Unicode string. This fix updates QuTiP's helper to match. (#1970)
- Fix correlation for case where only the collapse operators are time dependent. (#1979)
- Fix the hinton visualization method to plot the matrix instead of its transpose. (#2011)
- Fix the hinton visualization method to take into account all the matrix coefficients to set the squares scale, instead of only the diagonal coefficients. (#2012)
- Fix parsing of package versions in `setup.py` to support packaging 22.0. (#2037)
- Add back `.qu` suffix to objects saved with `qsave` and loaded with `qload`. The suffix was accidentally removed in QuTiP 4.7.0. (#2038)
- Add a default `max_step` to processors. (#2040)

6.2.3 Documentation

- Add towncrier for managing the changelog. (#1927)
- Update the version of numpy used to build documentation to 1.22.0. (#1940)
- Clarify returned objects from `bloch_redfield_tensor()`. (#1950)
- Update Floquet Markov solver docs. (#1958)
- Update the roadmap and ideas to show completed work as of August 2022. (#1967)

6.2.4 Miscellaneous

- Return `TypeError` instead of `Exception` for type error in `sesolve` argument. (#1924)
- Add towncrier draft build of changelog to CI tests. (#1946)
- Add Python 3.11 to builds. (#2041)
- Simplify version parsing by using `packaging.version.Version`. (#2043)
- Update builds to use `cibuildwheel 2.11`, and to build with `manylinux2014` on Python 3.8 and 3.9, since `numpy` and `SciPy` no longer support `manylinux2010` on those versions of Python. (#2047)

6.3 Version 4.7.0 (April 13, 2022)

This release sees the addition of two new solvers – `qutip.krylovsolve` based on the Krylov subspace approximation and `qutip.nonmarkov.heom` that reimplements the BoFiN HEOM solver.

Bloch sphere rendering gained support for drawing arcs and lines on the sphere, and for setting the transparency of rendered points and vectors, Hinton plots gained support for specifying a coloring style, and matrix histograms gained better default colors and more flexible styling options.

Other significant improvements include better scaling of the Floquet solver, support for passing `Path` objects when saving and loading files, support for passing callable functions as `e_ops` to `mesolve` and `sesolve`, and faster state number enumeration and Husimi Q functions.

Import bugfixes include some bugs affecting plotting with `matplotlib 3.5` and fixing support for qutrits (and other non-qubit) quantum circuits.

The many other small improvements, bug fixes, documentation enhancements, and behind the scenes development changes are included in the list below.

QuTiP 4.7.X will be the last series of releases for QuTiP 4. Patch releases will continue for the 4.7.X series but the main development effort will move to QuTiP 5.

The many, many contributors who filed issues, submitted or reviewed pull requests, and improved the documentation for this release are listed next to their contributions below. Thank you to all of you.

6.3.1 Improvements

- **MAJOR** Added `krylovsolve` as a new solver based on krylov subspace approximation. (#1739 by Emiliano Fortes)
- **MAJOR** Imported BoFiN HEOM (<https://github.com/tehruhn/bofin/>) into QuTiP and replaced the HEOM solver with a compatibility wrapper around BoFiN bosonic solver. (#1601, #1726, and #1724 by Simon Cross, Tarun Raheja and Neill Lambert)
- **MAJOR** Added support for plotting lines and arcs on the Bloch sphere. (#1690 by Gaurav Saxena, Asier Galicia and Simon Cross)

- Added transparency parameter to the `add_point`, `add_vector` and `add_states` methods in the `Bloch` and `Bloch3d` classes. (#1837 by Xavier Spronken)
- Support `Path` objects in `qutip.fileio`. (#1813 by Adrià Labay)
- Improved the weighting in steadystate solver, so that the default weight matches the documented behaviour and the dense solver applies the weights in the same manner as the sparse solver. (#1275 and #1802 by NS2 Group at LPS and Simon Cross)
- Added a `color_style` option to the `hinton` plotting function. (#1595 by Cassandra Granade)
- Improved the scaling of `floquet_master_equation_rates` and `floquet_master_equation_tensor` and fixed transposition and basis change errors in `floquet_master_equation_tensor` and `floquet_markov_mesolve`. (#1248 by Camille Le Calonnec, Jake Lishman and Eric Giguère)
- Removed `linspace_with` and `view_methods` from `qutip.utilities`. For the former it is far better to use `numpy.linspace` and for the later Python's in-built help function or other tools. (#1680 by Eric Giguère)
- Added support for passing callable functions as `e_ops` to `mesolve` and `sesolve`. (#1655 by Marek Narożniak)
- Added the function `steadystate_floquet`, which returns the “effective” steadystate of a periodic driven system. (#1660 by Alberto Mercurio)
- Improved `mcsolve` memory efficiency by not storing final states when they are not needed. (#1669 by Eric Giguère)
- Improved the default colors and styling of `matrix_histogram` and provided additional styling options. (#1573 and #1628 by Mahdi Aslani)
- Sped up `state_number_enumerate`, `state_number_index`, `state_index_number`, and added some error checking. `enr_state_dictionaries` now returns a list for `idx2state`. (#1604 by Johannes Feist)
- Added new Husimi Q algorithms, improving the speed for density matrices, and giving a near order-of-magnitude improvement when calculating the Q function for many different states, using the new `qutip.QFunc` class, instead of the `qutip.qfunc` function. (#934 and #1583 by Daniel Weigand and Jake Lishman)
- Updated licence holders with regards to new governance model, and remove extraneous licensing information from source files. (#1579 by Jake Lishman)
- Removed the vendored copy of LaTeX's `qccircuit` package which is GPL licensed. We now rely on the package being installed by user. It is installed by default with `TeXLive`. (#1580 by Jake Lishman)
- The signatures of `rand_ket` and `rand_ket_haar` were changed to allow `N` (the size of the random ket) to be determined automatically when `dims` are specified. (#1509 by Purva Thakre)

6.3.2 Bug Fixes

- Fix circuit index used when plotting circuits with non-reversed states. (#1847 by Christian Staufenbiel)
- Changed implementation of `qutip.orbital` to use `scipy.special.spy_harm` to remove bugs in angle interpretation. (#1844 by Christian Staufenbiel)
- Fixed `QobjEvo.tidyup` to use `settings.auto_tidyup_atol` when removing small elements in sparse matrices. (#1832 by Eric Giguère)
- Ensured that `tidyup`'s default tolerance is read from settings at each call. (#1830 by Eric Giguère)
- Fixed `scipy.sparse` deprecation warnings raised by `qutip.fast_csr_matrix`. (#1827 by Simon Cross)
- Fixed rendering of vectors on the Bloch sphere when using `matplotlib` 3.5 and above. (#1818 by Simon Cross)

- Fixed the displaying of `LatticeId` instances and their unit cells. Previously calling them raised exceptions in simple cases. (#1819, #1697 and #1702 by Simon Cross and Saumya Biswas)
- Fixed the displaying of the title for `hinton` and `matrix_histogram` plots when a title is given. Previously the supplied title was not displayed. (#1707 by Vladimir Vargas-Calderón)
- Removed an incorrect check on the initial state dimensions in the `QubitCircuit` constructor. This allows, for example, the construction of `qutrit` circuits. (#1807 by Boxi Li)
- Fixed the checking of `method` and `offset` parameters in `coherent` and `coherent_dm`. (#1469 and #1741 by Joseph Fox-Rabinovitz and Simon Cross)
- Removed the Hamiltonian saved in the `sesolve` solver results. (#1689 by Eric Giguère)
- Fixed a bug in `rand_herm` with `pos_def=True` and `density>0.5` where the diagonal was incorrectly filled. (#1562 by Eric Giguère)

6.3.3 Documentation Improvements

- Added contributors image to the documentation. (#1828 by Leonard Assis)
- Fixed the Theory of Quantum Information bibliography link. (#1840 by Anto Luketina)
- Fixed minor grammar errors in the dynamics guide. (#1822 by Victor Omole)
- Fixed many small documentation typos. (#1569 by Ashish Panigrahi)
- Added `Pulser` to the list of libraries that use QuTiP. (#1570 by Ashish Panigrahi)
- Corrected typo in the states and operators guide. (#1567 by Laurent Ajdnik)
- Converted `http` links to `https`. (#1555 by Jake Lishamn)

6.3.4 Developer Changes

- Add GitHub actions test run on windows-latest. (#1853 and #1855 by Simon Cross)
- Bumped the version of `pillow` used to build documentation from 9.0.0 to 9.0.1. (#1835 by dependabot)
- Migrated the `qutip.superop_reps` tests to `pytest`. (#1825 by Felipe Bivort Haiek)
- Migrated the `qutip.steadystates` tests to `pytest`. (#1679 by Eric Giguère)
- Changed the `README.md` CI badge to the GitHub Actions badge. (#1581 by Jake Lishman)
- Updated `CodeClimate` configuration to treat our Python source files as Python 3. (#1577 by Jake Lishman)
- Reduced cyclomatic complexity in `qutip._mkl`. (#1576 by Jake Lishman)
- Fixed PEP8 warnings in `qutip.control`, `qutip.mcsolve`, `qutip.random_objects`, and `qutip.stochastic`. (#1575 by Jake Lishman)
- Bumped the version of `urllib3` used to build documentation from 1.26.4 to 1.26.5. (#1563 by dependabot)
- Moved tests to GitHub Actions. (#1551 by Jake Lishman)
- The GitHub contributing guidelines were re-added and updated to point to the more complete guidelines in the documentation. (#1549 by Jake Lishman)
- The release documentation was reworked after the initial 4.6.1 to match the actual release process. (#1544 by Jake Lishman)

6.4 Version 4.6.3 (February 9, 2022)

This minor release adds support for numpy 1.22 and Python 3.10 and removes some blockers for running QuTiP on the Apple M1.

The performance of the `enr_destroy`, `state_number_enumerate` and `hadamard_transform` functions was drastically improved (up to 70x or 200x faster in some common cases), and support for the drift Hamiltonian was added to the `qutip.qip.Processor`.

The `qutip.hardware_info` module was removed as part of adding support for the Apple M1. We hope the removal of this little-used module does not adversely affect many users – it was largely unrelated to QuTiP’s core functionality and its presence was a continual source of blockers to importing `qutip` on new or changed platforms.

A new check on the dimensions of `Qobj`’s were added to prevent segmentation faults when invalid shape and dimension combinations were passed to Cython code.

In addition, there were many small bugfixes, documentation improvements, and improvements to our building and testing processes.

6.4.1 Improvements

- The `enr_destroy` function was made ~200x faster in many simple cases. ([#1593](#) by Johannes Feist)
- The `state_number_enumerate` function was made significantly faster. ([#1594](#) by Johannes Feist)
- Added the missing drift Hamiltonian to the method `run_analytically` of `Processor`. ([#1603](#) Boxi Li)
- The `hadamard_transform` was made much faster, e.g., ~70x faster for $N=10$. ([#1688](#) by Asier Galicia)
- Added support for computing the power of a scalar-like `Qobj`. ([#1692](#) by Asier Galicia)
- Removed the `hardware_info` module. This module wasn’t used inside QuTiP and regularly broke when new operating systems were released, and in particular prevented importing QuTiP on the Apple M1. ([#1754](#), [#1758](#) by Eric Giguère)

6.4.2 Bug Fixes

- Fixed support for calculating the propagator of a density matrix with collapse operators. QuTiP 4.6.2 introduced extra sanity checks on the dimensions of inputs to `mesolve` (Fix `mesolve` segfault with bad initial state [#1459](#)), but the propagator function’s calls to `mesolve` violated these checks by supplying initial states with the dimensions incorrectly set. `propagator` now calls `mesolve` with the correct dimensions set on the initial state. ([#1588](#) by Simon Cross)
- Fixed support for calculating the propagator for a superoperator without collapse operators. This functionality was not tested by the test suite and appears to have broken sometime during 2019. Tests have now been added and the code breakages fixed. ([#1588](#) by Simon Cross)
- Fixed the ignoring of the random number seed passed to `rand_dm` in the case where `pure` was set to true. ([#1600](#) Pontus Wikstahl)
- Fixed `qutip.control.optimize_pulse` support for sparse eigenvector decomposition with the `Qobj` `oper_dtype` (the `Qobj` `oper_dtype` is the default for large systems). ([#1621](#) by Simon Cross)
- Removed `qutip.control.optimize_pulse` support for `scipy.sparse.csr_matrix` and generic ndarray-like matrices. Support for these was non-functional. ([#1621](#) by Simon Cross)
- Fixed errors in the calculation of the Husimi spin `q_function` and spin `wigner` functions and added tests for them. ([#1632](#) by Mark Johnson)
- Fixed setting of OpenMP compilation flag on Linux. Previously when compiling the OpenMP functions were compiled without parallelization. ([#1693](#) by Eric Giguère)

- Fixed tracking the state of the Bloch sphere figure and axes to prevent exceptions during rendering. ([#1619](#) by Simon Cross)
- Fixed compatibility with numpy configuration in numpy's 1.22.0 release. ([#1752](#) by Matthew Treinish)
- Added dims checks for e_ops passed to solvers to prevent hanging the calling process when e_ops of the wrong dimensions were passed. ([#1778](#) by Eric Giguère)
- Added a check in Qobj constructor that the respective members of data.shape cannot be larger than what the corresponding dims could contain to prevent a segmentation fault caused by inconsistencies between dims and shapes. ([#1783](#), [#1785](#), [#1784](#) by Lajos Palanki & Eric Giguère)

6.4.3 Documentation Improvements

- Added docs for the num_cbits parameter of the QubitCircuit class. ([#1652](#) by Jon Crall)
- Fixed the parameters in the call to fsolve in the Floquet guide. ([#1675](#) by Simon Cross)
- Fixed the description of random number usage in the Monte Carlo solver guide. ([#1677](#) by Ian Thorvaldson)
- Fixed the rendering of equation numbers in the documentation (they now appear on the right as expected, not above the equation). ([#1678](#) by Simon Cross)
- Updated the installation requirements in the documentation to match what is specified in setup.py. ([#1715](#) by Asier Galicia)
- Fixed a typo in the `chi_to_choi` documentation. Previously the documentation mixed up chi and choi. ([#1731](#) by Pontus Wikstahl)
- Improved the documentation for the stochastic equation solvers. Added links to notebooks with examples, API documentation and external references. ([#1743](#) by Leonardo Assis)
- Fixed a typo in `qutip.settings` in the settings guide. ([#1786](#) by Mahdi Aslani)
- Made numerous small improvements to the text of the QuTiP basics guide. ([#1768](#) by Anna Naden)
- Made a small phrasing improvement to the README. ([#1790](#) by Rita Abani)

6.4.4 Developer Changes

- Improved test coverage of states and operators functions. ([#1578](#) by Eric Giguère)
- Fixed test_interpolate mcsolve use ([#1645](#) by Eric Giguère)
- Ensured figure plots are explicitly closed during tests so that the test suite passes when run headless under Xvfb. ([#1648](#) by Simon Cross)
- Bumped the version of pillow used to build documentation from 8.2.0 to 9.0.0. ([#1654](#), [#1760](#) by dependabot)
- Bumped the version of babel used to build documentation from 2.9.0 to 2.9.1. ([#1695](#) by dependabot)
- Bumped the version of numpy used to build documentation from 1.19.5 to 1.21.0. ([#1767](#) by dependabot)
- Bumped the version of ipython used to build documentation from 7.22.0 to 7.31.1. ([#1780](#) by dependabot)
- Rename qutip.bib to CITATION.bib to enable GitHub's citation support. ([#1662](#) by Ashish Panigrahi)
- Added tests for simdiags. ([#1681](#) by Eric Giguère)
- Added support for specifying the numpy version in the CI test matrix. ([#1696](#) by Simon Cross)
- Fixed the skipping of the dnorm metric tests if cvxpy is not installed. Previously all metrics tests were skipped by accident. ([#1704](#) by Florian Hopfmueller)
- Added bug report, feature request and other options to the GitHub issue reporting template. ([#1728](#) by Aryaman Kolhe)

- Updated the build process to support building on Python 3.10 by removing the build requirement for numpy < 1.20 and replacing it with a requirement on oldest-supported-numpy. (#1747 by Simon Cross)
- Updated the version of cibuildwheel used to build wheels to 2.3.0. (#1747, #1751 by Simon Cross)
- Added project urls to linking to the source repository, issue tracker and documentation to setup.cfg. (#1779 by Simon Cross)
- Added a numpy 1.22 and Python 3.10 build to the CI test matrix. (#1777 by Simon Cross)
- Ignore deprecation warnings from SciPy 1.8.0 `scipy.sparse.X` imports in CI tests. (#1797 by Simon Cross)
- Add building of wheels for Python 3.10 to the cibuildwheel job. (#1796 by Simon Cross)

6.5 Version 4.6.2 (June 2, 2021)

This minor release adds a function to calculate the quantum relative entropy, fixes a corner case in handling time-dependent Hamiltonians in `mesolve` and adds back support for a wider range of matplotlib versions when plotting or animating Bloch spheres.

It also adds a section in the README listing the papers which should be referenced while citing QuTiP.

6.5.1 Improvements

- Added a “Citing QuTiP” section to the README, containing a link to the QuTiP papers. (#1554)
- Added `entropy_relative` which returns the quantum relative entropy between two density matrices. (#1553)

6.5.2 Bug Fixes

- Fixed Bloch sphere distortion when using Matplotlib >= 3.3.0. (#1496)
- Removed use of integer-like floats in `math.factorial` since it is deprecated as of Python 3.9. (#1550)
- Simplified call to `ffmpeg` used in the the Bloch sphere animation tutorial to work with recent versions of `ffmpeg`. (#1557)
- Removed blitting in Bloch sphere `FuncAnimation` example. (#1558)
- Added a version checking condition to handle specific functionalities depending on the matplotlib version. (#1556)
- Fixed `mesolve` handling of time-dependent Hamiltonian with a custom `tlist` and `c_ops`. (#1561)

6.5.3 Developer Changes

- Read documentation version and release from the VERSION file.

6.6 Version 4.6.1 (May 4, 2021)

This minor release fixes bugs in QIP gate definitions, fixes building from the source tarball when git is not installed and works around an MKL bug in versions of SciPy ≤ 1.4 .

It also adds the `[full]` pip install target so that `pip install qutip[full]` installs qutip and all of its optional and developer dependencies.

6.6.1 Improvements

- Add the `[full]` pip install target (by **Jake Lishman**)

6.6.2 Bug Fixes

- Work around pointer MKL eigh bug in SciPy ≤ 1.4 (by **Felipe Bivort Haiek**)
- Fix berkeley, swapalpha and cz gate operations (by **Boxi Li**)
- Expose the CPHASE control gate (by **Boxi Li**)
- Fix building from the sdist when git is not installed (by **Jake Lishman**)

6.6.3 Developer Changes

- Move the qutip-doc documentation into the qutip repository (by **Jake Lishman**)
- Fix warnings in documentation build (by **Jake Lishman**)
- Fix warnings in pytest runs and make pytest treat warnings as errors (by **Jake Lishman**)
- Add Simon Cross as author (by **Simon Cross**)

6.7 Version 4.6.0 (April 11, 2021)

This release brings improvements for qubit circuits, including a pulse scheduler, measurement statistics, reading/writing OpenQASM and optimisations in the circuit simulations.

This is the first release to have full binary wheel releases on pip; you can now do `pip install qutip` on almost any machine to get a correct version of the package without needing any compilers set up. The support for Numpy 1.20 that was first added in QuTiP 4.5.3 is present in this version as well, and the same build considerations mentioned there apply here too. If building using the now-supported PEP 517 mechanisms (e.g. `python -mbuild /path/to/qutip`), all build dependencies will be correctly satisfied.

6.7.1 Improvements

- **MAJOR** Add saving, loading and resetting functionality to `qutip.settings` for easy re-configuration. (by **Eric Giguère**)
- **MAJOR** Add a quantum gate scheduler in `qutip.qip.scheduler`, to help parallelise the operations of quantum gates. This supports two scheduling modes: as late as possible, and as soon as possible. (by **Boxi Li**)
- **MAJOR** Improved qubit circuit simulators, including OpenQASM support and performance optimisations. (by **Sidhant Saraogi**)
- **MAJOR** Add tools for quantum measurements and their statistics. (by **Simon Cross** and **Sidhant Saraogi**)

- Add support for Numpy 1.20. QuTiP should be compiled against a version of Numpy $\geq 1.16.6$ and < 1.20 (note: does `_not_` include 1.20 itself), but such an installation is compatible with any modern version of Numpy. Source installations from `pip` understand this constraint.
- Improve the error message when circuit plotting fails. (by **Boxi Li**)
- Add support for parsing M1 Mac hardware information. (by **Xiaoliang Wu**)
- Add more single-qubit gates and controlled gates. (by **Mateo Laguna** and **Martín Sande Costa**)
- Support decomposition of X, Y and Z gates in circuits. (by **Boxi Li**)
- Refactor `QubitCircuit.resolve_gate()` (by **Martín Sande Costa**)

6.7.2 Bug Fixes

- Fix dims in the returns from `Qobj.eigenstates` on superoperators. (by **Jake Lishman**)
- Calling Numpy ufuncs on `Qobj` will now correctly raise a `TypeError` rather than returning a nonsense ndarray. (by **Jake Lishman**)
- Convert segfault into Python exception when creating too-large tensor products. (by **Jake Lishman**)
- Correctly set `num_collapse` in the output of `mesolve`. (by **Jake Lishman**)
- Fix `ptrace` when all subspaces are being kept, or the subspaces are passed in order. (by **Jake Lishman**)
- Fix sorting bug in `Bloch3d.add_points()`. (by **pschindler**)
- Fix invalid string literals in docstrings and some unclosed files. (by **Élie Gouzien**)
- Fix Hermiticity tests for matrices with values that are within the tolerance of 0. (by **Jake Lishman**)
- Fix the trace norm being incorrectly reported as 0 for small matrices. (by **Jake Lishman**)
- Fix issues with `dnorm` when using CVXPY 1.1 with sparse matrices. (by **Felipe Bivort Haiek**)
- Fix segfaults in `mesolve` when passed a bad initial `Qobj` as the state. (by **Jake Lishman**)
- Fix sparse matrix construction in PIQS when using Scipy 1.6.1. (by **Drew Parsons**)
- Fix `zspmv_openmp.cpp` missing from the pip sdist. (by **Christoph Gohlke**)
- Fix correlation functions throwing away imaginary components. (by **Asier Galicia Martinez**)
- Fix `QubitCircuit.add_circuit()` for SWAP gate. (by **Canoming**)
- Fix the broken LaTeX image conversion. (by **Jake Lishman**)
- Fix gate resolution of the FREDKIN gate. (by **Bo Yang**)
- Fix broken formatting in docstrings. (by **Jake Lishman**)

6.7.3 Deprecations

- `eseries`, `essolve` and `ode2es` are all deprecated, pending removal in QuTiP 5.0. These are legacy functions and classes that have been left unmaintained for a long time, and their functionality is now better achieved with `QobjEvo` or `mesolve`.

6.7.4 Developer Changes

- **MAJOR** Overhaul of setup and packaging code to make it satisfy PEP 517, and move the build to a matrix on GitHub Actions in order to release binary wheels on pip for all major platforms and supported Python versions. (by **Jake Lishman**)
- Default arguments in `Qobj` are now `None` rather than mutable types. (by **Jake Lishman**)
- Fixed consumable iterators being used to parametrise some tests, preventing the testing suite from being re-run within the same session. (by **Jake Lishman**)
- Remove unused imports, simplify some floats and remove unnecessary list conversions. (by **jakobjakobson13**)
- Improve Travis jobs matrix for specifying the testing containers. (by **Jake Lishman**)
- Fix coverage reporting on Travis. (by **Jake Lishman**)
- Added a `pyproject.toml` file. (by **Simon Humpohl** and **Eric Giguère**)
- Add doctests to documentation. (by **Sidhant Saraogi**)
- Fix all warnings in the documentation build. (by **Jake Lishman**)

6.8 Version 4.5.3 (February 19, 2021)

This patch release adds support for Numpy 1.20, made necessary by changes to how array-like objects are handled. There are no other changes relative to version 4.5.2.

Users building from source should ensure that they build against Numpy versions $\geq 1.16.6$ and < 1.20 (not including 1.20 itself), but after that or for those installing from conda, an installation will support any current Numpy version $\geq 1.16.6$.

6.8.1 Improvements

- Add support for Numpy 1.20. QuTiP should be compiled against a version of Numpy $\geq 1.16.6$ and < 1.20 (note: does `_not_` include 1.20 itself), but such an installation is compatible with any modern version of Numpy. Source installations from `pip` understand this constraint.

6.9 Version 4.5.2 (July 14, 2020)

This is predominantly a hot-fix release to add support for Scipy 1.5, due to changes in private sparse matrix functions that QuTiP also used.

6.9.1 Improvements

- Add support for Scipy 1.5. (by **Jake Lishman**)
- Improved speed of `zcsr_inner`, which affects `Qobj.overlap`. (by **Jake Lishman**)
- Better error messages when installation requirements are not satisfied. (by **Eric Giguère**)

6.9.2 Bug Fixes

- Fix `zcsr_proj` acting on matrices with unsorted indices. (by **Jake Lishman**)
- Fix errors in Milstein's heterodyne. (by **Eric Giguère**)
- Fix datatype bug in `qutip.lattice` module. (by **Boxi Li**)
- Fix issues with `eigh` on Mac when using OpenBLAS. (by **Eric Giguère**)

6.9.3 Developer Changes

- Converted more of the codebase to PEP 8.
- Fix several instances of unsafe mutable default values and unsafe `is` comparisons.

6.10 Version 4.5.1 (May 15, 2020)

6.10.1 Improvements

- `husimi` and `wigner` now accept half-integer spin (by **maij**)
- Better error messages for failed string coefficient compilation. (issue raised by **nohchangshuk**)

6.10.2 Bug Fixes

- Safer naming for temporary files. (by **Eric Giguère**)
- Fix `clebsch` function for half-integer (by **Thomas Walker**)
- Fix `randint`'s dtype to `uint32` for compatibility with Windows. (issue raised by **Boxi Li**)
- Corrected stochastic's heterodyne's `m_ops` (by **eliegeno**)
- Mac pool use spawn. (issue raised by **goerz**)
- Fix typos in `QobjEvo._shift`. (by **Eric Giguère**)
- Fix warning on Travis CI. (by **Ivan Carvalho**)

6.10.3 Deprecations

- `qutip.graph` functions will be deprecated in QuTiP 5.0 in favour of `scipy.sparse.csgraph`.

6.10.4 Developer Changes

- Add Boxi Li to authors. (by **Alex Pitchford**)
- Skip some tests that cause segfaults on Mac. (by **Nathan Shammah** and **Eric Giguère**)
- Use Python 3.8 for testing on Mac and Linux. (by **Simon Cross** and **Eric Giguère**)

6.11 Version 4.5.0 (January 31, 2020)

6.11.1 Improvements

- **MAJOR FEATURE:** Added *qip.noise*, a module with pulse level description of quantum circuits allowing to model various types of noise and devices (by **Boxi Li**).
- **MAJOR FEATURE:** Added *qip.lattice*, a module for the study of lattice dynamics in 1D (by **Saumya Biswas**).
- Migrated testing from Nose to PyTest (by **Tarun Raheja**).
- Optimized testing for PyTest and removed duplicated test runners (by **Jake Lishman**).
- Deprecated importing *qip* functions to the qutip namespace (by **Boxi Li**).
- Added the possibility to define non-square superoperators relevant for quantum circuits (by **Arne Grimsmo** and **Josh Combes**).
- Implicit tensor product for *qeye*, *qzero* and *basis* (by **Jake Lishman**).
- QObjEvo no longer requires Cython for string coefficient (by **Eric Giguère**).
- Added marked tests for faster tests in *testing.run()* and made faster OpenMP benchmarking in CI (by **Eric Giguère**).
- Added entropy and purity for Dicke density matrices, refactored into more general *dicke_trace* (by **Nathan Shammah**).
- Added option for specifying resolution in Bloch.save function (by **Tarun Raheja**).
- Added information related to the value of \hbar in *wigner* and *continuous_variables* (by **Nicolas Quesada**).
- Updated requirements for *scipy 1.4* (by **Eric Giguère**).
- Added previous lead developers to the qutip.about() message (by **Nathan Shammah**).
- Added improvements to *Qobj* introducing the *inv* method and making the partial trace, *ptrace*, faster, keeping both sparse and dense methods (by **Eric Giguère**).
- Allowed general callable objects to define a time-dependent Hamiltonian (by **Eric Giguère**).
- Added feature so that *QobjEvo* no longer requires Cython for string coefficients (by **Eric Giguère**).
- Updated authors list on Github and added *my binder* link (by **Nathan Shammah**).

6.11.2 Bug Fixes

- Fixed *PolyDataMapper* construction for *Bloch3d* (by **Sam Griffiths**).
- Fixed error checking for null matrix in *essolve* (by **Nathan Shammah**).
- Fixed name collision for parallel propagator (by **Nathan Shammah**).
- Fixed dimensional incongruence in *propagator* (by **Nathan Shammah**).
- Fixed bug by rewriting *clebsch* function based on long integer fraction (by **Eric Giguère**).
- Fixed bugs in *QobjEvo*'s args depending on state and added solver tests using them (by **Eric Giguère**).
- Fixed bug in *sesolve* calculation of average states when summing the timeslot states (by **Alex Pitchford**).
- Fixed bug in *steadystate* solver by removing separate arguments for MKL and Scipy (by **Tarun Raheja**).
- Fixed *Bloch.add_points* by setting *edgecolor = None* in *plot_points* (by **Nathan Shammah**).
- Fixed error checking for null matrix in *essolve* solver affecting also *ode2es* (by **Peter Kirton**).
- Removed unnecessary shebangs in .pyx and .pxd files (by **Samesh Lakhota**).

- Fixed *sesolve* and import of *os* in *codegen* (by **Alex Pitchford**).
- Updated *plot_fock_distribution* by removing the offset value 0.4 in the plot (by **Rajiv-B**).

6.12 Version 4.4.1 (August 29, 2019)

6.12.1 Improvements

- QobjEvo do not need to start from 0 anymore (by **Eric Giguère**).
- Add a quantum object purity function (by **Nathan Shammah** and **Shahnawaz Ahmed**).
- Add step function interpolation for array time-coefficient (by **Boxi Li**).
- Generalize *expand_oper* for arbitrary dimensions, and new method for cyclic permutations of given target qubits (by **Boxi Li**).

6.12.2 Bug Fixes

- Fixed the pickling but that made solver unable to run in parallel on Windows (Thank **Irunze** for reporting)
- Removed warning when *mesolve* fall back on *sesolve* (by **Michael Goerz**).
- Fixed dimension check and confusing documentation in random ket (by **Yariv Yanay**).
- Fixed Qobj isherm not working after using Qobj.permute (Thank **Ilorz1207** for reporting).
- Correlation functions call now properly handle multiple time dependant functions (Thank **taw181** for reporting).
- Removed mutable default values in *mesolve*/*sesolve* (by **Michael Goerz**).
- Fixed simdiag bug (Thank **Croydon-Brixton** for reporting).
- Better support of constant QobjEvo (by **Boxi Li**).
- Fixed potential cyclic import in the control module (by **Alexander Pitchford**).

6.13 Version 4.4.0 (July 03, 2019)

6.13.1 Improvements

- **MAJOR FEATURE:** Added methods and techniques to the stochastic solvers (by **Eric Giguère**) which allows to use a much broader set of solvers and much more efficiently.
- **MAJOR FEATURE:** Optimization of the montecarlo solver (by **Eric Giguère**). Computation are faster in many cases. Collapse information available to time dependant information.
- Added the QObjEvo class and methods (by **Eric Giguère**), which is used behind the scenes by the dynamical solvers, making the code more efficient and tidier. More built-in function available to string coefficients.
- The coefficients can be made from interpolated array with variable timesteps and can obtain state information more easily. Time-dependant collapse operator can have multiple terms.
- New wigner_transform and plot_wigner_sphere function. (by **Nithin Ramu**).
- ptrace is faster and work on bigger systems, from 15 Qbits to 30 Qbits.
- QIP module: added the possibility for user-defined gates, added the possibility to remove or add gates in any point of an already built circuit, added the molmer_sorensen gate, and fixed some bugs (by **Boxi Li**).
- Added the quantum Hellinger distance to qutip.metrics (by **Wojciech Rzadkowski**).

- Implemented possibility of choosing a random seed (by **Marek Marekgygdrasil**).
- Added a code of conduct to Github.

6.13.2 Bug Fixes

- Fixed bug that made QuTiP incompatible with SciPy 1.3.

6.14 Version 4.3.0 (July 14, 2018)

6.14.1 Improvements

- **MAJOR FEATURE:** Added the Permutational Invariant Quantum Solver (PIQS) module (by **Nathan Shammah** and **Shahnawaz Ahmed**) which allows the simulation of large TLSs ensembles including collective and local Lindblad dissipation. Applications range from superradiance to spin squeezing.
- **MAJOR FEATURE:** Added a photon scattering module (by **Ben Bartlett**) which can be used to study scattering in arbitrary driven systems coupled to some configuration of output waveguides.
- Cubic_Spline functions as time-dependent arguments for the collapse operators in mesolve are now allowed.
- Added a faster version of bloch_redfield_tensor, using components from the time-dependent version. About 3x+ faster for secular tensors, and 10x+ faster for non-secular tensors.
- Computing Q.overlap() [inner product] is now ~30x faster.
- Added projector method to Qobj class.
- Added fast projector method, Q.proj().
- Computing matrix elements, Q.matrix_element is now ~10x faster.
- Computing expectation values for ket vectors using expect is now ~10x faster.
- Q.tr() is now faster for small Hilbert space dimensions.
- Unitary operator evolution added to sesolve
- Use OPENMP for tidyup if installed.

6.14.2 Bug Fixes

- Fixed bug that stopped simdiag working for python 3.
- Fixed semidefinite cvxpy Variable and Parameter.
- Fixed iterative lu solve atol keyword issue.
- Fixed unitary op evolution rhs matrix in ssesolve.
- Fixed interpolating function to return zero outside range.
- Fixed dnorm complex casting bug.
- Fixed control.io path checking issue.
- Fixed ENR fock dimension.
- Fixed hard coded options in propagator 'batch' mode
- Fixed bug in trace-norm for non-Hermitian operators.
- Fixed bug related to args not being passed to coherence_function_g2
- Fixed MKL error checking dict key error

6.15 Version 4.2.0 (July 28, 2017)

6.15.1 Improvements

- **MAJOR FEATURE:** Initial implementation of time-dependent Bloch-Redfield Solver.
- Qobj tidyup is now an order of magnitude faster.
- Time-dependent codegen now generates output NumPy arrays faster.
- Improved calculation for analytic coefficients in coherent states (Sebastian Kramer).
- Input array to correlation FFT method now checked for validity.
- Function-based time-dependent mesolve and sesolve routines now faster.
- Codegen now makes sure that division is done in C, as opposed to Python.
- Can now set different controls for a each timeslot in quantum optimization. This allows time-varying controls to be used in pulse optimisation.

6.15.2 Bug Fixes

- rcsolve importing old Odeoptions Class rather than Options.
- Non-int issue in spin Q and Wigner functions.
- Qobj's should tidyup before determining isherm.
- Fixed time-dependent RHS function loading on Win.
- Fixed several issues with compiling with Cython 0.26.
- Liouvillian superoperators were hard setting isherm=True by default.
- Fixed an issue with the solver safety checks when inputting a list with Python functions as time-dependence.
- Fixed non-int issue in Wigner_cmap.
- MKL solver error handling not working properly.

6.16 Version 4.1.0 (March 10, 2017)

6.16.1 Improvements

Core libraries

- **MAJOR FEATURE:** QuTiP now works for Python 3.5+ on Windows using Visual Studio 2015.
- **MAJOR FEATURE:** Cython and other low level code switched to C++ for MS Windows compatibility.
- **MAJOR FEATURE:** Can now use interpolating cubic splines as time-dependent coefficients.
- **MAJOR FEATURE:** Sparse matrix - vector multiplication now parallel using OPENMP.
- Automatic tuning of OPENMP threading threshold.
- Partial trace function is now up to 100x+ faster.
- Hermitian verification now up to 100x+ faster.
- Internal Qobj objects now created up to 60x faster.
- Inplace conversion from COO -> CSR sparse formats (e.g. Memory efficiency improvement.)
- Faster reverse Cuthill-Mckee and sparse one and inf norms.

6.16.2 Bug Fixes

- Cleanup of temp. Cython files now more robust and working under Windows.

6.17 Version 4.0.2 (January 5, 2017)

6.17.1 Bug Fixes

- td files no longer left behind by correlation tests
- Various fast sparse fixes

6.18 Version 4.0.0 (December 22, 2016)

6.18.1 Improvements

Core libraries

- **MAJOR FEATURE:** Fast sparse: New subclass of `csr_matrix` added that overrides commonly used methods to avoid certain checks that incur execution cost. All `Qobj.data` now `fast_csr_matrix`
- HEOM performance enhancements
- `spmv` now faster
- `mcsolve` codegen further optimised

Control modules

- Time dependent drift (through list of pwc dynamics generators)
- memory optimisation options provided for `control.dynamics`

6.18.2 Bug Fixes

- recompilation of `pyx` files on first import removed
- `tau` array in `control.pulseoptim` funcs now works

6.19 Version 3.2.0 (Never officially released)

6.19.1 New Features

Core libraries

- **MAJOR FEATURE:** Non-Markovian solvers: Hierarchy (**Added by Neill Lambert**), Memory-Cascade, and Transfer-Tensor methods.
- **MAJOR FEATURE:** Default steady state solver now up to 100x faster using the Intel Pardiso library under the Anaconda and Intel Python distributions.
- The default Wigner function now uses a Clenshaw summation algorithm to evaluate a polynomial series that is applicable for any number of excitations (previous limitation was ~50 quanta), and is ~3x faster than before. (**Added by Denis Vasilyev**)
- Can now define a given eigen spectrum for random Hermitian and density operators.

- The `Qobj.expm` method now uses the equivalent SciPy routine, and performs a much faster `exp` operation if the matrix is diagonal.
- One can now build zero operators using the `qzero` function.

Control modules

- **MAJOR FEATURE:** CRAB algorithm added This is an alternative to the GRAPE algorithm, which allows for analytical control functions, which means that experimental constraints can more easily be added into optimisation. See tutorial notebook for full information.

6.19.2 Improvements

Core libraries

- Two-time correlation functions can now be calculated for fully time-dependent Hamiltonians and collapse operators. (**Added by Kevin Fischer**)
- The code for the inverse-power method for the steady state solver has been simplified.
- Bloch-Redfield tensor creation is now up to an order of magnitude faster. (**Added by Johannes Feist**)
- `Q.transform` now works properly for arrays directly from `sp_eigs` (or `eig`).
- `Q.groundstate` now checks for degeneracy.
- Added `sinm` and `cosm` methods to the `Qobj` class.
- Added `charge` and `tunneling` operators.
- Time-dependent Cython code is now easier to read and debug.

Control modules

- The internal state / quantum operator data type can now be either `Qobj` or `ndarray` Previous only `ndarray` was possible. This now opens up possibility of using `Qobj` methods in fidelity calculations The attributes and functions that return these operators are now preceded by an underscore, to indicate that the data type could change depending on the configuration options. In most cases these functions were for internal processing only anyway, and should have been ‘private’. Accessors to the properties that could be useful outside of the library have been added. These always return `Qobj`. If the internal operator data type is not `Qobj`, then there could be significant overhead in the conversion, and so this should be avoided during pulse optimisation. If custom sub-classes are developed that use `Qobj` properties and methods (e.g. partial trace), then it is very likely that it will be more efficient to set the internal data type to `Qobj`. The internal operator data will be chosen automatically based on the size and sparsity of the dynamics generator. It can be forced by setting `dynamics.oper_dtype = <type>` Note this can be done by passing `dyn_params={'oper_dtype': <type>}` in any of the pulseoptim functions.

Some other properties and methods were renamed at the same time. A full list is given here.

- All modules - function: `set_log_level` -> property: `log_level`
- dynamics functions
 - * `_init_lists` now `_init_evo`
 - * `get_num_ctrls` now property: `num_ctrls`
 - * `get_owd_evo_target` now property: `onto_evo_target`
 - * `combine_dyn_gen` now `_combine_dyn_gen` (no longer returns a value)
 - * `get_dyn_gen` now `_get_phased_dyn_gen`
 - * `get_ctrl_den_gen` now `_get_phased_ctrl_dyn_gen`
 - * `ensure_decomp_curr` now `_ensure_decomp_curr`
 - * `spectral_decomp` now `_spectral_decomp`
- dynamics properties

- * `evo_init2t` now `_fwd_evo` (`fwd_evo` as `Qobj`)
- * `evo_t2end` now `_onwd_evo` (`onwd_evo` as `Qobj`)
- * `evo_t2targ` now `_onto_evo` (`onto_evo` as `Qobj`)
- `fidcomp` properties
 - * `uses_evo_t2end` now `uses_onwd_evo`
 - * `uses_evo_t2targ` now `uses_onto_evo`
 - * `set_phase_option` function now property `phase_option`
- `propcomp` properties
 - * `grad_exact` (now read only)
- `propcomp` functions
 - * `compute_propagator` now `_compute_propagator`
 - * `compute_diff_prop` now `_compute_diff_prop`
 - * `compute_prop_grad` now `_compute_prop_grad`
- `tslotcomp` functions
 - * `get_timeslot_for_fidelity_calc` now `_get_timeslot_for_fidelity_calc`

Miscellaneous

- QuTiP Travis CI tests now use the Anaconda distribution.
- The `about` box and `ipynb` `version_table` now display addition system information.
- Updated Cython cleanup to remove depreciation warning in `sysconfig`.
- Updated `ipynb_parallel` to look for `ipyparallel` module in V4 of the notebooks.

6.19.3 Bug Fixes

- Fixes for `countstat` and `psuedo-inverse` functions
- Fixed `Qobj` division tests on 32-bit systems.
- Removed extra call to Python in time-dependent Cython code.
- Fixed issue with repeated Bloch sphere saving.
- Fixed `T_0` triplet state not normalized properly. **(Fixed by Eric Hontz)**
- Simplified compiler flags (support for ARM systems).
- Fixed a decoding error in `qload`.
- Fixed issue using `complex.h` math and `np.kind_t` variables.
- Corrected output states mismatch for `ntraj=1` in the `mcf90` solver.
- `Qobj` data is now copied by default to avoid a bug in multiplication. **(Fixed by Richard Brierley)**
- Fixed bug overwriting `hardware_info` in `__init__`. **(Fixed by Johannes Feist)**
- Restored ability to explicitly set `Q.isherm`, `Q.type`, and `Q.superrep`.
- Fixed integer depreciation warnings from NumPy.
- `Qobj * (dense vec)` would result in a recursive loop.
- Fixed `args=None` -> `args={}` in correlation functions to be compatible with `mesolve`.
- Fixed depreciation warnings in `mcsolve`.
- Fixed neagative only real parts in `rand_ket`.

- Fixed a complicated list-cast-map-list antipattern in super operator reps. (**Fixed by Stefan Krastanov**)
- Fixed incorrect `isherm` for `sigmam` spin operator.
- Fixed the dims when using `final_state_output` in `mesolve` and `sesolve`.

6.20 Version 3.1.0 (January 1, 2015)

6.20.1 New Features

- **MAJOR FEATURE:** New module for quantum control (`qutip.control`).
- **NAMESPACE CHANGE:** QuTiP no longer exports symbols from NumPy and matplotlib, so those modules must now be explicitly imported when required.
- New module for counting statistics.
- Stochastic solvers now run trajectories in parallel.
- New superoperator and tensor manipulation functions (`super_tensor`, `composite`, `tensor_contract`).
- New logging module for debugging (`qutip.logging`).
- New user-available API for parallelization (`parallel_map`).
- New enhanced (optional) text-based progressbar (`qutip.ui.EnhancedTextProgressBar`)
- Faster Python based monte carlo solver (`mcsolve`).
- Support for progress bars in propagator function.
- Time-dependent Cython code now calls complex `cmath` functions.
- Random numbers seeds can now be reused for successive calls to `mcsolve`.
- The Bloch-Redfield master equation solver now supports optional Lindblad type collapse operators.
- Improved handling of ODE integration errors in `mesolve`.
- Improved correlation function module (for example, improved support for time-dependent problems).
- Improved parallelization of `mcsolve` (can now be interrupted easily, support for `IPython.parallel`, etc.)
- Many performance improvements, and much internal code restructuring.

6.20.2 Bug Fixes

- Cython build files for time-dependent string format now removed automatically.
- Fixed incorrect solution time from inverse-power method steady state solver.
- `mcsolve` now supports `Options(store_states=True)`
- Fixed bug in *hadamard* gate function.
- Fixed compatibility issues with NumPy 1.9.0.
- Progressbar in `mcsolve` can now be suppressed.
- Fixed bug in `gate_expand_3toN`.
- Fixed bug for time-dependent problem (list string format) with multiple terms in coefficient to an operator.

6.21 Version 3.0.1 (Aug 5, 2014)

6.21.1 Bug Fixes

- Fix bug in `create()`, which returned a `Qobj` with CSC data instead of CSR.
- Fix several bugs in `mcsolve`: Incorrect storing of collapse times and collapse operator records. Incorrect averaging of expectation values for different trajectories when using only 1 CPU.
- Fix bug in parsing of time-dependent Hamiltonian/collapse operator arguments that occurred when the `args` argument is not a dictionary.
- Fix bug in internal `_version2int` function that cause a failure when parsing the version number of the Cython package.
-

6.22 Version 3.0.0 (July 17, 2014)

6.22.1 New Features

- New module `qutip.stochastic` with stochastic master equation and stochastic Schrödinger equation solvers.
- Expanded steady state solvers. The function `steady` has been deprecated in favor of `steadystate`. The `steadystate` solver no longer use `umfpack` by default. New pre-processing methods for reordering and balancing the linear equation system used in direct solution of the steady state.
- New module `qutip.qip` with utilities for quantum information processing, including pre-defined quantum gates along with functions for expanding arbitrary 1, 2, and 3 qubit gates to N qubit registers, circuit representations, library of quantum algorithms, and basic physical models for some common QIP architectures.
- New module `qutip.distributions` with unified API for working with distribution functions.
- New format for defining time-dependent Hamiltonians and collapse operators, using a pre-calculated numpy array that specifies the values of the `Qobj`-coefficients for each time step.
- New functions for working with different superoperator representations, including Kraus and Chi representation.
- New functions for visualizing quantum states using Qubism and Schimdt plots: `plot_qubism` and `plot_schmidt`.
- Dynamics solver now support taking argument `e_ops` (expectation value operators) in dictionary form.
- Public plotting functions from the `qutip.visualization` module are now prefixed with `plot_` (e.g., `plot_fock_distribution`). The `plot_wigner` and `plot_wigner_fock_distribution` now supports 3D views in addition to contour views.
- New API and new functions for working with spin operators and states, including for example `spin_Jx`, `spin_Jy`, `spin_Jz` and `spin_state`, `spin_coherent`.
- The `expect` function now supports a list of operators, in addition to the previously supported list of states.
- Simplified creation of qubit states using `ket` function.
- The module `qutip.cyQ` has been renamed to `qutip.cy` and the sparse matrix-vector functions `spmv` and `spmvld` has been combined into one function `spmv`. New functions for operating directly on the underlying sparse CSR data have been added (e.g., `spmv_csr`). Performance improvements. New and improved Cython functions for calculating expectation values for state vectors, density matrices in matrix and vector form.
- The `concurrence` function now supports both pure and mixed states. Added function for calculating the entangling power of a two-qubit gate.

- Added function for generating (generalized) Lindblad dissipator superoperators.
- New functions for generating Bell states, and singlet and triplet states.
- QuTiP no longer contains the demos GUI. The examples are now available on the QuTiP web site. The `qutip.gui` module has been renamed to `qutip.ui` and does no longer contain graphical UI elements. New text-based and HTML-based progressbar classes.
- Support for harmonic oscillator operators/states in a Fock state basis that does not start from zero (e.g., in the range $[M, N+1]$). Support for eliminating and extracting states from Qobj instances (e.g., removing one state from a two-qubit system to obtain a three-level system).
- Support for time-dependent Hamiltonian and Liouvillian callback functions that depend on the instantaneous state, which for example can be used for solving master equations with mean field terms.

6.22.2 Improvements

- Restructured and optimized implementation of Qobj, which now has significantly lower memory footprint due to avoiding excessive copying of internal matrix data.
- The classes `OdeData`, `Odeoptions`, `Odeconfig` are now called `Result`, `Options`, and `Config`, respectively, and are available in the module `qutip.solver`.
- The `squeez` function has been renamed to `squeeze`.
- Better support for sparse matrices when calculating propagators using the `propagator` function.
- Improved Bloch sphere.
- Restructured and improved the module `qutip.sparse`, which now only operates directly on sparse matrices (not on Qobj instances).
- Improved and simplified implement of the `tensor` function.
- Improved performance, major code cleanup (including namespace changes), and numerous bug fixes.
- Benchmark scripts improved and restructured.
- QuTiP is now using continuous integration tests (TravisCI).

6.23 Version 2.2.0 (March 01, 2013)

6.23.1 New Features

- **Added Support for Windows**
- New `Bloch3d` class for plotting 3D Bloch spheres using Mayavi.
- Bloch sphere vectors now look like arrows.
- Partial transpose function.
- Continuous variable functions for calculating correlation and covariance matrices, the Wigner covariance matrix and the logarithmic negativity for multimode fields in Fock basis.
- The master-equation solver (`mesolve`) now accepts pre-constructed Liouvillian terms, which makes it possible to solve master equations that are not on the standard Lindblad form.
- Optional Fortran Monte Carlo solver (`mcsolve_f90`) by Arne Grimsmo.
- A module of tools for using QuTiP in IPython notebooks.
- Increased performance of the steady state solver.
- New Wigner colormap for highlighting negative values.
- More graph styles to the visualization module.

6.23.2 Bug Fixes

- Function based time-dependent Hamiltonians now keep the correct phase.
- mcsolve no longer prints to the command line if ntraj=1.

6.24 Version 2.1.0 (October 05, 2012)

6.24.1 New Features

- New method for generating Wigner functions based on Laguerre polynomials.
- `coherent()`, `coherent_dm()`, and `thermal_dm()` can now be expressed using analytic values.
- Unittests now use nose and can be run after installation.
- Added `iswap` and `sqrt-iswap` gates.
- Functions for quantum process tomography.
- Window icons are now set for Ubuntu application launcher.
- The propagator function can now take a list of times as argument, and returns a list of corresponding propagators.

6.24.2 Bug Fixes

- `mesolver` now correctly uses the user defined `rhs_filename` in `Odeoptions()`.
- `rhs_generate()` now handles user defined filenames properly.
- Density matrix returned by `propagator_steadystate` is now Hermitian.
- `eseries_value` returns real list if all imag parts are zero.
- `mcsolver` now gives correct results for strong damping rates.
- `Odeoptions` now prints `mc_avg` correctly.
- Do not check for `PyObj` in `mcsolve` when `gui=False`.
- `Eseries` now correctly handles purely complex rates.
- `thermal_dm()` function now uses truncated operator method.
- Cython based time-dependence now Python 3 compatible.
- Removed call to `NSAutoPool` on mac systems.
- Progress bar now displays the correct number of CPU's used.
- `Qobj.diag()` returns reals if operator is Hermitian.
- Text for progress bar on Linux systems is no longer cutoff.

6.25 Version 2.0.0 (June 01, 2012)

The second version of QuTiP has seen many improvements in the performance of the original code base, as well as the addition of several new routines supporting a wide range of functionality. Some of the highlights of this release include:

6.25.1 New Features

- QuTiP now includes solvers for both Floquet and Bloch-Redfield master equations.
- The Lindblad master equation and Monte Carlo solvers allow for time-dependent collapse operators.
- It is possible to automatically compile time-dependent problems into c-code using Cython (if installed).
- Python functions can be used to create arbitrary time-dependent Hamiltonians and collapse operators.
- Solvers now return Odata objects containing all simulation results and parameters, simplifying the saving of simulation results.

Important: This breaks compatibility with QuTiP version 1.x.

- `mesolve` and `mcsolve` can reuse Hamiltonian data when only the initial state, or time-dependent arguments, need to be changed.
- QuTiP includes functions for creating random quantum states and operators.
- The generation and manipulation of quantum objects is now more efficient.
- Quantum objects have basis transformation and matrix element calculations as built-in methods.
- The quantum object eigensolver can use sparse solvers.
- The partial-trace (`ptrace`) function is up to 20x faster.
- The Bloch sphere can now be used with the Matplotlib animation function, and embedded as a subplot in a figure.
- QuTiP has built-in functions for saving quantum objects and data arrays.
- The steady-state solver has been further optimized for sparse matrices, and can handle much larger system Hamiltonians.
- The steady-state solver can use the iterative bi-conjugate gradient method instead of a direct solver.
- There are three new entropy functions for concurrence, mutual information, and conditional entropy.
- Correlation functions have been combined under a single function.
- The operator norm can now be set to trace, Frobius, one, or max norm.
- Global QuTiP settings can now be modified.
- QuTiP includes a collection of unit tests for verifying the installation.
- Demos window now lets you copy and paste code from each example.

6.26 Version 1.1.4 (May 28, 2012)

6.26.1 Bug Fixes

- Fixed bug pointed out by Brendan Abolins.
- `Qobj.tr()` returns zero-dim ndarray instead of float or complex.
- Updated factorial import for scipy version 0.10+

6.27 Version 1.1.3 (November 21, 2011)

6.27.1 New Functions

- Allow custom naming of Bloch sphere.

6.27.2 Bug Fixes

- Fixed text alignment issues in AboutBox.
- Added fix for SciPy V>0.10 where factorial was moved to `scipy.misc` module.
- Added tidyup function to tensor function output.
- Removed openmp flags from `setup.py` as new Mac Xcode compiler does not recognize them.
- `Qobj.diag` method now returns real array if all imaginary parts are zero.
- Examples GUI now links to new documentation.
- Fixed zero-dimensional array output from metrics module.

6.28 Version 1.1.2 (October 27, 2011)

6.28.1 Bug Fixes

- Fixed issue where Monte Carlo states were not output properly.

6.29 Version 1.1.1 (October 25, 2011)

THIS POINT-RELEASE INCLUDES VASTLY IMPROVED TIME-INDEPENDENT MCSOLVE AND ODESOLVE PERFORMANCE

6.29.1 New Functions

- Added linear entropy function.
- Number of CPU's can now be changed.

6.29.2 Bug Fixes

- Metrics no longer use dense matrices.
- Fixed Bloch sphere grid issue with matplotlib 1.1.
- Qobj trace operation uses only sparse matrices.
- Fixed issue where GUI windows do not raise to front.

6.30 Version 1.1.0 (October 04, 2011)

THIS RELEASE NOW REQUIRES THE GCC COMPILER TO BE INSTALLED

6.30.1 New Functions

- tidyup function to remove small elements from a Qobj.
- Added concurrence function.
- Added simdiag for simultaneous diagonalization of operators.
- Added eigenstates method returning eigenstates and eigenvalues to Qobj class.
- Added fileio for saving and loading data sets and/or Qobj's.
- Added hinton function for visualizing density matrices.

6.30.2 Bug Fixes


- Switched Examples to new Signals method used in PySide 1.0.6+.
- Switched ProgressBar to new Signals method.
- Fixed memory issue in expm functions.
- Fixed memory bug in isherm.
- Made all Qobj data complex by default.
- Reduced ODE tolerance levels in Odeoptions.
- Fixed bug in ptrace where dense matrix was used instead of sparse.
- Fixed issue where PyQt4 version would not be displayed in about box.
- Fixed issue in Wigner where xvec was used twice (in place of yvec).

6.31 Version 1.0.0 (July 29, 2011)

- **Initial release.**

Chapter 7

Developers



7.1 Lead Developers

- Alex Pitchford
- Nathan Shammah
- Shahnawaz Ahmed
- Neill Lambert
- Eric Giguère
- Boxi Li
- Jake Lishman
- Simon Cross

7.2 Past Lead Developers

- Robert Johansson (RIKEN)
- Paul Nation (Korea University)
- Chris Granade
- Arne Grimsmo

7.3 Contributors

Note: Anyone is welcome to contribute to QuTiP. If you are interested in helping, please let us know!

- Abhisek Upadhyaya
- Adriaan
- Alexander Pitchford
- Alexios-xi
- Amit
- Anubhav Vardhan
- Arie van Deursen
- Arne Grimsmo
- Arne Hamann
- Asier Galicia Martinez
- Ben Bartlett
- Ben Criger
- Ben Jones
- Bo Yang
- Boxi Li
- Canoming
- Christoph Gohlke

- Christopher Granade
- Craig Gidney
- Denis Vasilyev
- Dominic Meiser
- Drew Parsons
- Eric Giguère
- Eric Hontz
- Felipe Bivort Haiek
- Florestan Ziem
- Gilbert Shih
- Harry Adams
- Ivan Carvalho
- Jake Lishman
- Jevon Longdell
- Johannes Feist
- Jonas Hoersch
- Jonas Neergaard-Nielsen
- Jonathan A. Gross
- Julian Iacoponi
- Kevin Fischer
- Laurence Stant
- Louis Tessler
- Lucas Verney
- Marco David
- Marek Narozniak
- Markus Baden
- Martín Sande
- Mateo Laguna
- Matthew O’Brien
- Michael Goerz
- Michael V. DePalatis
- Moritz Oberhauser
- Nathan Shammah
- Neill Lambert
- Nicolas Quesada
- Nikolas Tezak
- Nithin Ramu
- Paul Nation
- Peter Kirton

- Philipp Schindler
- Piotr Migdal
- Rajiv-B
- Ray Ganardi
- Reinier Heeres
- Richard Brierley
- Robert Johansson
- Sam Griffiths
- Samesh Lakhota
- Sebastian Krämer
- Shahnawaz Ahmed
- Sidhant Saraogi
- Simon Cross
- Simon Humpohl
- Simon Whalen
- Stefan Krastanov
- Tarun Raheja
- Thomas Walker
- Viacheslav Ostroukh
- Vlad Negnevitsky
- Wojciech Rządowski
- Xiaodong Qi
- Xiaoliang Wu
- Yariv Yanay
- YouWei Zhao
- alex
- eliegeois
- essence-of-waqf
- fhenneke
- gecrooks
- jakobjakobson13
- maij
- sbisw002
- [yuri@FreeBSD](#)
- Élie Gouzien

Chapter 8

Development Documentation

This chapter covers the development of QuTiP and its subpackages, including a roadmap for upcoming releases and ideas for future improvements.

8.1 Contributing to QuTiP Development

8.1.1 Quick Start

QuTiP is developed through wide collaboration using the `git` version-control system, with the main repositories hosted in the [qutip organisation on GitHub](#). You will need to be familiar with `git` as a tool, and the [GitHub Flow](#) workflow for branching and making pull requests. The exact details of environment set-up, build process and testing vary by repository and are discussed below, however in overview, the steps to contribute are:

1. Consider creating an issue on the GitHub page of the relevant repository, describing the change you think should be made and why, so we can discuss details with you and make sure it is appropriate.
2. (If this is your first contribution.) Make a fork of the relevant repository on GitHub and clone it to your local computer. Also add our copy as a remote (`git remote add qutip https://github.com/qutip/<repo>`).
3. Begin on the master branch (`git checkout master`), and pull in changes from the main QuTiP repository to make sure you have an up-to-date copy (`git pull qutip master`).
4. Switch to a new git branch (`git checkout -b <branch-name>`).
5. Make the changes you want to make, then create some commits with short, descriptive names (`git add <files>` then `git commit`).
6. Follow the build process for this repository to build the final result so you can check your changes work sensibly.
7. Run the tests for the repository (if it has them).
8. Push the changes to your fork (`git push -u origin <branch-name>`). You won't be able to push to the main QuTiP repositories directly.
9. Go to the GitHub website for the repository you are contributing to, click on the "Pull Requests" tab, click the "New Pull Request" button, and follow the instructions there.

Once the pull request is created, some members of the QuTiP admin team will review the code to make sure it is suitable for inclusion in the library, to check the programming, and to ensure everything meets our standards. For some repositories, several automated tests will run whenever you create or modify a pull request; in general these will be the same tests you can run locally, and all tests are required to pass online before your changes are merged. There may be some feedback and possibly some requested changes. You can add more commits to address these, and push them to the relevant branch of your fork to update the pull request.

The rest of this document covers programming standards, and particular considerations for some of the more complicated repositories.

8.1.2 Core Library: `qutip/qutip`

The core library is in the [qutip/qutip repository on GitHub](#).

Building

Building the core library from source is typically a bit more difficult than simply installing the package for regular use. You will most likely want to do this in a clean Python environment so that you do not compromise a working installation of a release version, for example by starting from

```
conda create -n qutip-dev python
```

Complete instructions for the build are elsewhere in this guide, however beware that you will need to follow the *installation from source using setuptools section*, not the general installation. You will need all the *build* and *tests* “optional” requirements for the package. The build requirements can be found in the `pyproject.toml` file, and the testing requirements are in the `tests` key of the `options.extras_require` section of `setup.cfg`. You will also need the requirements for any optional features you want to test as well.

Refer to the main instructions for the most up-to-date version, however as of version 4.6 the requirements can be installed into a conda environment with

```
conda install setuptools wheel numpy scipy cython packaging pytest pytest-  
→rerunfailures
```

Note that `qutip` should *not* be installed with `conda install`.

Note: If you prefer, you can also use `pip` to install all the dependencies. We typically recommend `conda` when doing main-library development because it is easier to switch low-level packages around like BLAS implementations, but if this doesn’t mean anything to you, feel free to use `pip`.

You will need to make sure you have a functioning C++ compiler to build QuTiP. If you are on Linux or Mac, this is likely already done for you, however if you are on Windows, refer to the *Windows installation* section of the installation guide.

The command to build QuTiP in editable mode is

```
python setup.py develop
```

from the repository directory. If you now load up a Python interpreter, you should be able to `import qutip` from anywhere as long as the correct Python environment is active. Any changes you make to the Python files in the git repository should be immediately present if you restart your Python interpreter and re-import `qutip`.

On the first run, the `setup` command will compile many C++ extension modules built from Cython sources (files ending `.pxd` and `.pyx`). Generally the low-level linear algebra routines that QuTiP uses are written in these files, not in pure Python. Unlike Python files, changes you make to Cython files will not appear until you run `python setup.py develop` again; you will only need to re-run this if you are changing Cython files. Cython will detect and compile only the files that have been changed, so this command will be faster on subsequent runs.

Note: When undertaking Cython development, the reason we use `python setup.py develop` instead of `pip install -e .` is because Cython’s changed-file detection does not reliably work in the latter. `pip` tends to build in temporary virtual environments, which often makes Cython think its core library files have been updated, triggering a complete, slow rebuild of everything.

Note: QuTiP follows [NEP29](#) when selecting the supported version of its dependencies. To see which versions are planned to be supported in the next release, please refer to the [QuTiP major release roadmap](#). These coincide with the versions employed for testing in continuous integration.

In the event of a feature requiring a version upgrade of python or a dependency, it will be considered appropriately in the pull request. In any case, python and dependency upgrades will only happen in mayor or minor versions of QuTiP, not in a patch.

Code Style

The biggest concern you should always have is to make it easy for your code to be read and understood by the person who comes next.

All new contributions must follow [PEP 8 style](#); all pull requests will be passed through a linter that will complain if you violate it. You should use the `pycodestyle` package locally (available on `pip`) to test you satisfy the requirements before you push your commits, since this is rather faster than pushing 10 different commits trying to fix minor niggles. Keep in mind that there is quite a lot of freedom in this style, especially when it comes to line breaks. If a line is too long, consider the *best* way to split it up with the aim of making the code readable, not just the first thing that doesn't generate a warning.

Try to stay consistent with the style of the surrounding code. This includes using the same variable names, especially if they are function arguments, even if these “break” PEP 8 guidelines. *Do not* change existing parameter, attribute or method names to “match” PEP 8; these are breaking user-facing changes, and cannot be made except in a new major release of QuTiP.

Other than this, general “good-practice” Python standards apply: try not to duplicate code; try to keep functions short, descriptively-named and side-effect free; provide a docstring for every new function; and so on.

Documenting

When you make changes in the core library, you should update the relevant documentation if needed. If you are making a bug fix, or other relatively minor changes, you will probably only need to make sure that the docstrings of the modified functions and classes are up-to-date; changes here will propagate through to the documentation the next time it is built. Be sure to follow the [Numpy documentation standards \(numpydoc\)](#) when writing docstrings. All docstrings will be parsed as reStructuredText, and will form the API documentation section of the documentation.

Testing

We use `pytest` as our test runner. The base way to run every test is

```
pytest /path/to/repo/qutip/tests
```

This will take around 10 to 30 minutes, depending on your computer and how many of the optional requirements you have installed. It is normal for some tests to be marked as “skip” or “xfail” in yellow; these are not problems. True failures will appear in red and be called “fail” or “error”.

While prototyping and making changes, you might want to use some of the filtering features of `pytest`. Instead of passing the whole `tests` directory to the `pytest` command, you can also pass a list of files. You can also use the `-k` selector to only run tests whose names include a particular pattern, for example

```
pytest qutip/tests/test_qobj.py -k "expm"
```

to run the tests of `Qobj.expm`.

Changelog Generation

We use `towncrier` for tracking changes and generating a changelog. When making a pull request, we require that you add a `towncrier` entry along with the code changes. You should create a file named `<PR number>.<change type>` in the `doc/changes` directory, where the PR number should be substituted for `<PR number>`, and `<change type>` is either `feature`, `bugfix`, `doc`, `removal`, `misc`, or `deprecation`, depending on the type of change included in the PR.

You can also create this file by installing `towncrier` and running

```
towncrier create <PR number>.<change type>
```

Running this will create a file in the `doc/changes` directory with a filename corresponding to the argument you passed to `towncrier create`. In this file, you should add a short description of the changes that the PR introduces.

8.1.3 Documentation: qutip/qutip (doc directory)

The core library is in the [qutip/qutip repository on GitHub](#), inside the `doc` directory.

Building

The documentation is built using `sphinx`, `matplotlib` and `numpydoc`, with several additional extensions including `sphinx-gallery` and `sphinx-rtd-theme`. The most up-to-date instructions and dependencies will be in the `README.md` file of the documentation directory. You can see the rendered version of this file simply by going to the [documentation GitHub page](#) and scrolling down.

Building the documentation can be a little finnick on occasion. You likely will want to keep a separate Python environment to build the documentation in, because some of the dependencies can have tight requirements that may conflict with your favourite tools for Python development. We recommend creating an empty `conda` environment containing only Python with

```
conda create -n qutip-doc python=3.8
```

and install all further dependencies with `pip`. There is a `requirements.txt` file in the repository root that fixes all package versions exactly into a known-good configuration for a completely empty environment, using

```
pip install -r requirements.txt
```

This known-good configuration was intended for Python 3.8, though in principle it is possible that other Python versions will work.

Note: We recommend you use `pip` to install dependencies for the documentation rather than `conda` because several necessary packages can be slower to update their `conda` recipes, so suitable versions may not be available.

The documentation build includes running many components of the main QuTiP library to generate figures and to test the output, and to generate all the API documentation. You therefore need to have a version of QuTiP available in the same Python environment. If you are only interested in updating the users' guide, you can use a release version of QuTiP, for example by running `pip install qutip`. If you are also modifying the main library, you need to make your development version accessible in this environment. See the [above section on building QuTiP](#) for more details, though the `requirements.txt` file will have already installed all the build requirements, so you should be able to simply run

```
python setup.py develop
```

in the main library repository.

The documentation is built by running the `make` command. There are several targets to build, but the most useful will be `html` to build the webpage documentation, `latexpdf` to build the PDF documentation (you will also

need a full `pdflatex` installation), and `clean` to remove all built files. The most important command you will want to run is

```
make html
```

You should re-run this any time you make changes, and it should only update files that have been changed.

Important: The documentation build includes running almost all the optional features of QuTiP. If you get failure messages in red, make sure you have installed all of the optional dependencies for the main library.

The HTML files will be placed in the `_build/html` directory. You can open the file `_build/html/index.html` in your web browser to check the output.

Code Style

All user guide pages and docstrings are parsed by Sphinx using reStructuredText. There is a general [Sphinx usage guide](#), which has a lot of information that can sometimes be a little tricky to follow. It may be easier just to look at other `.rst` files already in the documentation to copy the different styles.

Note: reStructuredText is a very different language to the Markdown that you might be familiar with. It's always worth checking your work in a web browser to make sure it's appeared the way you intended.

Testing

There are unfortunately no automated tests for the documentation. You should ensure that no errors appeared in red when you ran `make html`. Try not to introduce any new warnings during the build process. The main test is to open the HTML pages you have built (open `_build/html/index.html` in your web browser), and click through to the relevant pages to make sure everything has rendered the way you expected it to.

8.2 QuTiP Development Roadmap

8.2.1 Preamble

This document outlines plan and ideas for the current and future development of QuTiP. The document is maintained by the QuTiP Admin team. Contributions from the QuTiP Community are very welcome.

In particular this document outlines plans for the next major release of qutip, which will be version 5. And also plans and dreams beyond the next major version.

There is lots of development going on in QuTiP that is not recorded in here. This is just an attempt at coordinated strategy and ideas for the future.

What is QuTiP?

The name QuTiP refers to a few things. Most famously, qutip is a Python library for simulating quantum dynamics. To support this, the library also contains various software tools (functions and classes) that have more generic applications, such as linear algebra components and visualisation utilities, and also tools that are specifically quantum related, but have applications beyond just solving dynamics (for instance partial trace computation).

QuTiP is also an organisation, in the Github sense, and in the sense of a group of people working collaboratively towards common objectives, and also a web presence qutip.org. The QuTiP Community includes all the people who have supported the project since in conception in 2010, including manager, funders, developers, maintainers and users.

These related, and overlapping, uses of the QuTiP name are of little consequence until one starts to consider how to organise all the software packages that are somehow related to QuTiP, and specifically those that are maintained by the QuTiP Admin Team. Herin QuTiP will refer to the project / organisation and qutip to the library for simulating quantum dynamics.

Should we be starting again from scratch, then we would probably chose another name for the main qutip library, such as qutip-quantdyn. However, qutip is famous, and the name will stay.

8.2.2 Library package structure

With a name as general as Quantum Toolkit in Python, the scope for new code modules to be added to qutip is very wide. The library was becoming increasingly difficult to maintain, and in c. 2020 the QuTiP Admin Team decided to limit the scope of the ‘main’ (for want of a better name) qutip package. This scope is restricted to components for the simulation (solving) of the dynamics of quantum systems. The scope includes utilities to support this, including analysis and visualisation of output.

At the same time, again with the intention of easing maintence, a decision to limit dependences was agreed upon. Main qutip runtime code components should depend only upon Numpy and Scipy. Installation (from source) requires Cython, and some optional components also require Cython at runtime. Unit testing requires Pytest. Visualisation (optional) components require Matplotlib.

Due to the all encompassing nature of the plan to abstract the linear algebra data layer, this enhancement (developed as part of a GSoC project) was allowed the freedom (potential for non-backward compatibility) of requiring a major release. The timing of such allows for a restructuring of the qutip compoments, such that some that could be deemed out of scope could be packaged in a different way – that is, not installed as part of the main qutip package. Hence the proposal for different types of package described next. With reference to the [discussion above](#) on the name QuTiP/qutip, the planned restructuring suffers from confusing naming, which seems unavoidable without remaining either the organisation or the main package (neither of which are desirable).

QuTiP family packages The main qutip package already has sub-packages, which are maintained in the main qutip repo. Any packages maintained by the QuTiP organisation will be called QuTiP ‘family’ packages. Sub-packages within qutip main will be called ‘integrated’ sub-packages. Some packages will be maintained in their own repos and installed separately within the main qutip folder structure to provide backwards compatibility, these are (will be) called qutip optional sub-packages. Others will be installed in their own folders, but (most likely) have qutip as a dependency – these will just be called ‘family’ packages.

QuTiP affiliated packages Other packages have been developed by others outside of the QuTiP organisation that work with, and are complementary to, qutip. The plan is to give some recognition to those that we deem worthy of such [this needs clarification]. These packages will not be maintained by the QuTiP Team.

Family packages

qutip main

- **current package status:** family package *qutip*
- **planned package status:** family package *qutip*

The in-scope components of the main qutip package all currently reside in the base folder. The plan is to move some components into integrated subpackages as follows:

- *core* quantum objects and operations
- *solver* quantum dynamics solvers

What will remain in the base folder will be miscellaneous modules. There may be some opportunity for grouping some into a *visualisation* subpackage. There is also some potential for renaming, as some module names have underscores, which is unconventional.

Qtrl

- **current package status:** integrated sub-package *qutip.control*
- **planned package status:** family package *qtrl*

There are many OSS Python packages for quantum control optimisation. There are also many different algorithms. The current *control* integrated subpackage provides the GRAPE and CRAB algorithms. It is too ambitious for QuTiP to attempt (or want) to provide for all options. Control optimisation has been deemed out of scope and hence these components will be separated out into a family package called Qtrl.

Potentially Qtrl may be replaced by separate packages for GRAPE and CRAB, based on the QuTiP Control Framework.

QIP

- **current package status:** integrated sub-package *qutip.qip*
- **planned package status:** family package *qutip-qip*

The QIP subpackage has been deemed out of scope (feature-wise). It also depends on *qutip.control* and hence would be out of scope for dependency reasons. A separate repository has already been made for *qutip-qip*.

qutip-symbolic

- **current package status:** independent package *sympsi*
- **planned package status:** family package *qutip-symbolic*

Long ago Robert Johansson and Eunjong Kim developed Sympsi. It is a fairly complete library for quantum computer algebra (symbolic computation). It is primarily a quantum wrapper for *Sympy*.

It has fallen into unmaintained status. The latest version on the [sympsi repo](#) does not work with recent versions of Sympy. Alex Pitchford has a [fork](#) that does ‘work’ with recent Sympy versions – unit tests pass, and most examples work. However, some (important) examples fail, due to lack of respect for non-commuting operators in Sympy simplification functions (note this was true as of Nov 2019, may be fixed now).

There is a [not discussed with RJ & EK] plan to move this into the QuTiP family to allow the Admin Team to maintain, develop and promote it. The ‘Sympsi’ name is cute, but a little abstract, and *qutip-symbolic* is proposed as an alternative, as it is plainer and more distinct from Sympy.

Affiliated packages

qucontrol-krotov

- **code repository:** <https://github.com/qucontrol/krotov>

A package for quantum control optimisation using Krotov, developed mainly by Michael Goerz.

Generally accepted by the Admin Team as well developed and maintained. A solid candidate for affiliation.

8.2.3 Development Projects

Solver data layer integration

tag solve-dl
status development ongoing
admin lead [Eric](#)
main dev [Eric](#)

The new data layer gives opportunity for significantly improving performance of the qutip solvers. Eric has been revamping the solvers by deploying *QobjEvo* (the time-dependent quantum object) that he developed. *QobjEvo* will exploit the data layer, and the solvers in turn exploit *QobjEvo*.

Qtrl migration

tag qtrl-mig
status conceptualised
admin lead [Alex](#)
main dev TBA

The components currently packaged as an integrated subpackage of qutip main will be moved to separate package called Qtrl. This is the original codename of the package before it was integrated into qutip. Also changes to exploit the new data layer will be implemented.

QuTiP control framework

tag ctrl-fw
status conceptualised
admin lead [Alex](#)
main dev TBA

Create new package qutip-ctrlfw “QuTiP Control Framework”. The aim is provide a common framework that can be adopted by control optimisation packages, such that different packages (algorithms) can be applied to the same problem.

Classes for defining a controlled system:

- named control parameters. Scalar and n-dim. Continuous and discrete variables
- mapping of control parameters to dynamics generator args
- masking for control parameters to be optimised

Classes for time-dependent variable parameterisation

- piecewise constant
- piecewise linear
- Fourier basis
- more

Classes for defining an optimisation problem:

- single and multiple objectives

QuTiP optimisation

tag qutip-optim

status conceptualised

admin lead Alex

main dev TBA

A wrapper for multi-variable optimisation functions. For instance those in *scipy.optimize* (Nelder-Mead, BFGS), but also others, such as Bayesian optimisation and other machine learning based approaches. Initially just providing a common interface for quantum control optimisation, but applicable more generally.

Sympsi migration

tag sympsi-mig

status conceptualised

admin lead Alex

main dev TBA

Create a new family package qutip-symbolic from ajgpitch fork of Sympy. Must gain permission from Robert Johansson and Eunjong Kim. Extended Sympy simplify to respect non-commuting operators. Produce user documentation.

Status messaging and recording

tag status-msg

status conceptualised

admin lead Alex

main dev TBA

QuTiP has various ways of recording and reporting status and progress.

- *ProgressBar* used by some solvers
- Python logging used in qutip.control
- *Dump* used in qutip.control
- heom records *solver.Stats*

Some consolidation of these would be good.

Some processes (some solvers, correlation, control optimisation) have many stages and many layers. *Dump* was initially developed to help with debugging, but it is also useful for recording data for analysis. qutip.logging_utils has been criticised for the way it uses Python logging. The output goes to stderr and hence the output looks like errors in Jupyter notebooks.

Clearly, storing process stage data is costly in terms of memory and cpu time, so any implementation must be able to be optionally switched on/off, and avoided completely in low-level processes (cythonized components).

Required features:

- optional recording (storing) of process stage data (states, operators etc)
- optionally write subsets to stdout
- maybe other graphical representations
- option to save subsets to file
- should ideally replace use of *ProgressBar*, Python logging, *control.Dump*, *solver.Stats*

qutip Interactive

status conceptualised

tag qutip-gui

admin lead [Alex](#)

main dev TBA

QuTiP is pretty simple to use at an entry level for anyone with basic Python skills. However, *some* Python skills are necessary. A graphical user interface (GUI) for some parts of qutip could help make qutip more accessible. This could be particularly helpful in education, for teachers and learners.

This would make an good GSoC project. It is independent and the scope is flexible.

The scope for this is broad and flexible. Ideas including, but not limited to:

Interactive Bloch sphere

Matplotlib has some interactive features (sliders, radio buttons, cmd buttons) that can be used to control parameters. They are a bit clunky to use, but they are there. Could maybe avoid these and develop our own GUI. An interactive Bloch sphere could have sliders for qubit state angles. Buttons to add states, toggle state evolution path.

Interactive solvers

Options to configure dynamics generators (Lindbladian / Hamiltonian args etc) and expectation operators. Then run solver and view state evolution.

Animated circuits

QIP circuits could be animated. Status lights showing evolution of states during the processing. Animated Bloch spheres for qubits.

8.2.4 Completed Development Projects

data layer abstraction

tag dl-abs

status completed

admin lead [Eric](#)

main dev [Jake Lishman](#)

Development completed as a GSoC project. Fully implemented in the dev.major branch. Currently being used by some research groups.

Abstraction of the linear algebra data from code qutip components, allowing for alternatives, such as sparse, dense etc. Difficult to summarize. Almost every file in qutip affected in some way. A major milestone for qutip. Significant performance improvements throughout qutip.

Some developments tasks remain, including providing full control over how the data-layer dispatchers choose the most appropriate output type.

qutip main reorganization

tag qmain-reorg
status completed
admin lead Eric
main dev Jake Lishman

Reorganise qutip main components to the structure *described above*.

qutip user docs migration

tag qmain-docs
status completed
admin lead Jake Lishman
main dev Jake Lishman

The qutip user documentation build files are to be moved to the qutip/qutip repo. This is more typical for an OSS package.

As part of the move, the plan is to reconstruct the Sphinx structure from scratch. Historically, there have been many issues with building the docs. Sphinx has come a long way since qutip docs first developed. The main source (rst) files will remain [pretty much] as they are, although there is a lot of scope to improve them.

The qutip-doc repo will afterwards just be used for documents, such as this one, pertaining to the QuTiP project.

QIP migration

tag qip-mig
status completed
admin lead Boxi
main dev Sidhant Saraogi

A separate package for qutip-qip was created during Sidhant's GSoC project. There is some fine tuning required, especially after qutip.control is migrated.

HEOM revamp

tag heom-revamp
status completed
admin lead Neill
main dev Simon Cross, Tarun Raheja

An overhaul of the HEOM solver, to incorporate the improvements pioneered in BoFiN.

8.2.5 QuTiP major release roadmap

QuTiP v.5

These Projects need to be completed for the qutip v.5 release.

- *data layer abstraction* (completed)
- *qutip main reorganization* (completed)
- *qutip user docs migration* (completed)
- *Solver data layer integration* (in-progress)
- *QIP migration* (completed)
- *Qtrl migration*
- *HEOM revamp* (completed)

The planned timeline for the release is:

- **alpha version, December 2022.** Core features packaged and available for experienced users to test.
- **beta version, January 2023.** All required features and documentation complete, packaged and ready for community testing.
- **full release, April 2023.** Full tested version released.

Planned supported environment:

- python 3.8 .. 3.11
- numpy 1.20 .. 1.23
- scipy 1.5 .. 1.8

8.3 Ideas for future QuTiP development

Ideas for significant new features are listed here. For the general roadmap, see [QuTiP Development Roadmap](#).

8.3.1 QuTiP Interactive

Contents

- *Interactive Bloch sphere*
- *Interactive solvers*
- *Animated circuits*
 - *Expected outcomes*
 - *Skills*
 - *Difficulty*
 - *Mentors*

QuTiP is pretty simple to use at an entry level for anyone with basic Python skills. However, *some* Python skills are necessary. A graphical user interface (GUI) for some parts of qutip could help make qutip more accessible. This could be particularly helpful in education, for teachers and learners.

Ideally, interactive components could be embedded in web pages. Including, but not limited to, Jupyter notebooks.

The scope for this is broad and flexible. Ideas including, but not limited to:

Interactive Bloch sphere

QuTiP has a Bloch sphere virtualisation for qubit states. This could be made interactive through sliders, radio buttons, cmd buttons etc. An interactive Bloch sphere could have sliders for qubit state angles. Buttons to add states, toggle state evolution path. Potential for recording animations. Matplotlib has some interactive features (sliders, radio buttons, cmd buttons) that can be used to control parameters. that could potentially be used.

Interactive solvers

Options to configure dynamics generators (Lindbladian / Hamiltonian args etc) and expectation operators. Then run solver and view state evolution.

Animated circuits

QIP circuits could be animated. Status lights showing evolution of states during the processing. Animated Bloch spheres for qubits.

Expected outcomes

- Interactive graphical components for demonstrating quantum dynamics
- Web pages for qutip.org or Jupyter notebooks introducing quantum dynamics using the new components

Skills

- Git, Python and familiarity with the Python scientific computing stack
- elementary understanding of quantum dynamics

Difficulty

- Variable

Mentors

- Nathan Shammah (nathan.shammah@gmail.com)
- Alex Pitchford (alex.pitchford@gmail.com)
- Simon Cross (hodgestar@gmail.com)
- Boxi Li (etamin1201@gmail.com) [QuTiP GSoC 2019 graduate]

8.3.2 Pulse level description of quantum circuits

Contents

- *Expected outcomes*
- *Skills*
- *Difficulty*
- *Mentors*

• References

The aim of this proposal is to enhance QuTiP quantum-circuit compilation features with regard to quantum information processing. While QuTiP core modules deal with dynamics simulation, there is also a module for quantum circuits simulation. The two subsequent Google Summer of Code projects, in 2019 and 2020, enhanced them in capabilities and features, allowing the simulation both at the level of gates and at the level of time evolution. To connect them, a compiler is implemented to compile quantum gates into the Hamiltonian model. We would like to further enhance this feature in QuTiP and the connection with other libraries.

Expected outcomes

- APIs to import and export pulses to other libraries. Quantum compiler is a current research topic in quantum engineering. Although QuTiP has a simple compiler, many may want to try their own compiler which is more compatible with their quantum device. Allowing importation and exportation of control pulses will make this much easier. This will include a study of existing libraries, such as *qiskit.pulse* and *OpenPulse*¹, comparing them with *qutip.qip.pulse* module and building a more general and comprehensive description of the pulse.
- More examples of quantum system in the *qutip.qip.device* module. The circuit simulation and compilation depend strongly on the physical system. At the moment, we have two models: spin chain and cavity QED. We would like to include some other commonly used platform such as Superconducting system², Ion trap system³ or silicon system. Each model will need a new set of control Hamiltonian and a compiler that finds the control pulse of a quantum gate. More involved noise models can also be added based on the physical system. This part is going to involve some physics and study of commonly used hardware platforms. The related code can be found in *qutip.qip.device* and *qutip.qip.compiler*.

Skills

- Git, Python and familiarity with the Python scientific computing stack
- quantum information processing and quantum computing (quantum circuit formalism)

Difficulty

- Medium

Mentors

- Boxi Li (etamin1201@gmail.com) [QuTiP GSoC 2019 graduate]
- Nathan Shammah (nathan.shammah@gmail.com)
- Alex Pitchford (alex.pitchford@gmail.com)

¹ McKay D C, Alexander T, Bello L, et al. Qiskit backend specifications for openqasm and openpulse experiments[J]. arXiv preprint arXiv:1809.03452, 2018.

² Häffner H, Roos C F, Blatt R, **Quantum computing with trapped ions**, Physics reports, 2008, 469(4): 155-203.

³ Krantz P, Kjaergaard M, Yan F, et al. **A quantum engineer's guide to superconducting qubits**, Applied Physics Reviews, 2019, 6(2): 021318.

References

8.3.3 Quantum Error Mitigation

Contents

- *Expected outcomes*
- *Skills*
- *Difficulty*
- *Mentors*
- *References*

From the QuTiP 4.5 release, the `qutip.qip` module now contains the noisy quantum circuit simulator (which was a GSoC project) providing enhanced features for a pulse-level description of quantum circuits and noise models. A new class *Processor* and several subclasses are added to represent different platforms for quantum computing. They can transfer a quantum circuit into the corresponding control sequence and simulate the dynamics with QuTiP solvers. Different noise models can be added to *qutip.qip.noise* to simulate noise in a quantum device.

This module is still young and many features can be improved, including new device models, new noise models and integration with the existing general framework for quantum circuits (*qutip.qip.circuit*). There are also possible applications such as error mitigation techniques (^{1,2,3}).

The tutorial notebooks can be found at <https://qutip.org/tutorials.html#nisq>. A recent presentation on the FOSDEM conference may help you get an overview (https://fosdem.org/2020/schedule/event/quantum_qutip/). See also the Github Project page for a collection of related issues and ongoing Pull Requests.

Expected outcomes

- Make an overview of existing libraries and features in error mitigation, similarly to a literature survey for a research article, but for a code project (starting from Refs.^{4,5}). This is done in order to best integrate the features in QuTiP with existing libraries and avoid reinventing the wheel.
- Features to perform error mitigation techniques in QuTiP, such as zero-noise extrapolation by pulse stretching.
- Tutorials implementing basic quantum error mitigation protocols
- Possible integration with Mitiq⁶

¹ Kristan Temme, Sergey Bravyi, Jay M. Gambetta, **Error mitigation for short-depth quantum circuits**, Phys. Rev. Lett. 119, 180509 (2017)

² Abhinav Kandala, Kristan Temme, Antonio D. Corcoles, Antonio Mezzacapo, Jerry M. Chow, Jay M. Gambetta, **Extending the computational reach of a noisy superconducting quantum processor**, Nature 567, 491 (2019)

³ S. Endo, S.C. Benjamin, Y. Li, **Practical quantum error mitigation for near-future applications**, Physical Review X 8, 031027 (2018)

⁴ Boxi Li's blog on the GSoC 2019 project on pulse-level control, <https://gsoc2019-boxili.blogspot.com/>

⁵ Video of a recent talk on the GSoC 2019 project, https://fosdem.org/2020/schedule/event/quantum_qutip/

⁶ Mitiq

Skills

- Background in quantum physics and quantum circuits.
- Git, python and familiarity with the Python scientific computing stack

Difficulty

- Medium

Mentors

- Nathan Shammah (nathan.shammah@gmail.com)
- Alex Pitchford (alex.pitchford@gmail.com)
- Eric Giguère (eric.giguere@usherbrooke.ca)
- Neill Lambert (nwlambert@gmail.com)
- Boxi Li (etamin1201@gmail.com) [QuTiP GSoC 2019 graduate]

References

8.3.4 GPU implementation of the Hierarchical Equations of Motion

Contents

- *Expected outcomes*
- *Skills*
- *Difficulty*
- *Mentors*
- *References*

The Hierarchical Equations of Motion (HEOM) method is a non-perturbative approach to simulate the evolution of the density matrix of dissipative quantum systems. The underlying equations are a system of coupled ODEs which can be run on a GPU. This will allow the study of larger systems as discussed in¹. The goal of this project would be to extend QuTiP's HEOM method² and implement it on a GPU.

Since the method is related to simulating large, coupled ODEs, it can also be quite general and extended to other solvers.

¹ <https://pubs.acs.org/doi/abs/10.1021/ct200126d?src=recsys&journalCode=jctcce>

² <https://arxiv.org/abs/2010.10806>

Expected outcomes

- A version of HEOM which runs on a GPU.
- Performance comparison with the CPU version.
- Implement dynamic scaling.

Skills

- Git, python and familiarity with the Python scientific computing stack
- CUDA and OpenCL knowledge

Difficulty

- Hard

Mentors

- Neill Lambert (nwlambert@gmail.com)
- Alex Pitchford (alex.pitchford@gmail.com)
- Shahnawaz Ahmed (shahnawaz.ahmed95@gmail.com)
- Simon Cross (hodgestar@gmail.com)

References

8.3.5 Google Summer of Code

Many possible extensions and improvements to QuTiP have been documented as part of [Google Summer of Code](#):

- [GSoC 2021](#)
- [GSoC 2022](#)

8.3.6 Completed Projects

These projects have been completed:

TensorFlow Data Backend

Contents

- *Why a TensorFlow backend?*
- *Challenges*
 - *Expected outcomes*
 - *Skills*
 - *Difficulty*
 - *Mentors*
 - *References*

Note: This project was completed as part of GSoC 2021³.

QuTiP's data layer provides the mathematical operations needed to work with quantum states and operators, i.e. `Qobj`, inside QuTiP. As part of Google Summer of Code 2020, the data layer was rewritten to allow new backends to be added more easily and for different backends to interoperate with each other. Backends using in-memory spares and dense matrices already exist, and we would like to add a backend that implements the necessary operations using TensorFlow¹.

Why a TensorFlow backend?

TensorFlow supports distributing matrix operations across multiple GPUs and multiple machines, and abstracts away some of the complexities of doing so efficiently. We hope that by using TensorFlow we might enable QuTiP to scale to bigger quantum systems (e.g. more qubits) and decrease the time taken to simulate them.

There is particular interest in trying the new backend with the BoFiN HEOM (Hierarchical Equations of Motion) solver².

Challenges

TensorFlow is a very different kind of computational framework to the existing dense and sparse matrix backends. It uses flow graphs to describe operations, and to work efficiently. Ideally large graphs of operations need to be executed together in order to efficiently compute results.

The QuTiP data layer might need to be adjusted to accommodate these differences, and it is possible that this will prove challenging or even that we will not find a reasonable way to achieve the desired performance.

Expected outcomes

- Add a `qutip.core.data.tensorflow` data type.
- Implement specialisations for some important operations (e.g. `add`, `mul`, `matmul`, `eigen`, etc).
- Write a small benchmark to show how `Qobj` operations scale on the new backend in comparison to the existing backends. Run the benchmark both with and without using a GPU.
- Implement enough for a solver to run on top of the new TensorFlow data backend and benchmark that (stretch goal).

Skills

- Git, Python and familiarity with the Python scientific computing stack
- Familiarity with TensorFlow (beneficial, but not required)
- Familiarity with Cython (beneficial, but not required)

³ <https://github.com/qutip/qutip-tensorflow/>

¹ <https://www.tensorflow.org/>

² <https://github.com/tehrunn/bofin>

Difficulty

- Medium

Mentors

- Simon Cross (hodgestar@gmail.com)
- Jake Lishman (jake@binhbar.com)
- Alex Pitchford (alex.pitchford@gmail.com)

References

8.4 Working with the QuTiP Documentation

The user guide provides an overview of QuTiP’s functionality. The guide is composed of individual reStructured-Text (`.rst`) files which each get rendered as a webpage. Each page typically tackles one area of functionality. To learn more about how to write `.rst` files, it is useful to follow the [sphinx guide](#).

The documentation build also utilizes a number of [Sphinx Extensions](#) including but not limited to [doctest](#), [autodoc](#), [sphinx gallery](#) and [plot](#). Additional extensions can be configured in the `conf.py` file.

8.4.1 Directives

There are two Sphinx directives that can be used to write code examples in the user guide:

- [Doctest](#)
- [Plot](#)

For a more comprehensive account of the usage of each directive, please refer to their individual pages. Here we outline some general guidelines on how to these directives while making a user guide.

Doctest

The doctest directive enables tests on interactive code examples. The simplest way to do this is by specifying a prompt along with its respective output:

```
.. doctest::

    >>> a = 2
    >>> a
    2
```

This is rendered in the documentation as follows:

```
>>> a = 2
>>> a
2
```

While specifying code examples under the `.. doctest::` directive, either all statements must be specified by the `>>>` prompt or without it. For every prompt, any potential corresponding output must be specified immediately after it. This directive is ideally used when there are a number of examples that need to be checked in quick succession.

A different way to specify code examples (and test them) is using the associated `.. testcode::` directive which is effectively a code block:

```
.. testcode::  
  
    a = 2  
    print(a)
```

followed by its results. The result can be specified with the `.. testoutput::` block:

```
.. testoutput::  
  
    2
```

The advantage of the `testcode` directive is that it is a lot simpler to specify and amenable to copying the code to clipboard. Usually, tests are more easily specified with this directive as the input and output are specified in different blocks. The rendering is neater too.

Note: The `doctest` and `testcode` directives should not be assumed to have the same namespace.

Output:

```
a = 2  
print(a)
```

```
2
```

A few notes on using the `doctest` extension:

- By default, each `testcode` and `doctest` block is run in a fresh namespace. To share a common namespace, we can specify a common group across the blocks (within a single `.rst` file). For example,

```
.. doctest:: [group_name]  
  
    >>> a = 2
```

can be followed by some explanation followed by another code block sharing the same namespace

```
.. doctest:: [group_name]  
  
    >>> print(a)  
    2
```

- To only print the code blocks (or the output), use the option `+SKIP` to specify the block without the code being tested when running `make doctest`.
- To check the result of a `Qobj` output, it is useful to make sure that spacing irregularities between the expected and actual output are ignored. For that, we can use the option `+NORMALIZE_WHITESPACE`.

Plot

Since the `doctest` directive cannot render matplotlib figures, we use Matplotlib's `Plot` directive when rendering to LaTeX or HTML.

The `plot` directive can also be used in the `doctest` format. In this case, when running doctests (which is enabled by specifying all statements with the `>>>` prompts), tests also include those specified under the `plot` directive.

Example:

```
First we specify some data:  
  
.. plot::
```

(continues on next page)

(continued from previous page)

```
>>> import numpy as np
>>> x = np.linspace(0, 2 * np.pi, 1000)
>>> x[:10] # doctest: +NORMALIZE_WHITESPACE
array([ 0.          ,  0.00628947,  0.01257895,  0.01886842,  0.0251579 ,
        0.03144737,  0.03773685,  0.04402632,  0.0503158 ,  0.05660527])


.. plot::
:context:

>>> import matplotlib.pyplot as plt
>>> plt.plot(x, np.sin(x))
[...]
```

Note the use of the `NORMALIZE_WHITESPACE` option to ensure that the multiline output matches.

Render:

```
>>> import numpy as np
>>> x = np.linspace(0, 2 * np.pi, 1000)
>>> x[:10]
array([ 0.          ,  0.00628947,  0.01257895,  0.01886842,  0.0251579 ,
        0.03144737,  0.03773685,  0.04402632,  0.0503158 ,  0.05660527])
>>> import matplotlib.pyplot as plt
>>> plt.plot(x, np.sin(x))
[...]
```



A few notes on using the `plot` directive:

- A useful argument to specify in plot blocks is that of `context` which ensures that the code is being run in the namespace of the previous plot block within the same file.
- By default, each rendered figure in one plot block (when using `:context:`) is carried over to the next block.
- When the `context` argument is specified with the `reset` option as `:context: reset`, the namespace is reset to a new one and all figures are erased.
- When the `context` argument is specified with the `close-figs` option as `:context: reset`, the namespace is reset to a new one and all figures are erased.

The Plot directive cannot be used in conjunction with Doctest because they do not share the same namespace when used in the same file. Since Plot can also be used in doctest mode, in the case where code examples require both testing and rendering figures, it is easier to use the Plot directive. To learn more about each directive, it is useful to refer to their individual pages.

8.5 Release and Distribution

8.5.1 Preamble

This document covers the process for managing updates to the current minor release and making new releases. Within this document, the git remote `upstream` refers to the main QuTiP organisation repository, and `origin` refers to your personal fork.

In short, the steps you need to take are:

1. Prepare the release branch (see [git](#)).
2. Run the “Build wheels, optionally deploy to PyPI” GitHub action to build binary and source packages and upload them to PyPI (see [deploy](#)).
3. Retrieve the built documentation from GitHub (see [docbuild](#)).
4. Create a GitHub release and uploaded the built files to it (see [github](#)).
5. Update [qutip.org](#) with the new links and documentation ([web](#)).
6. Update the conda feedstock, deploying the package to conda ([cforge](#)).

8.5.2 Setting Up The Release Branch

In this step you will prepare a git branch on the main QuTiP repository that has the state of the code that is going to be released. This procedure is quite different if you are releasing a new minor or major version compared to if you are making a bugfix patch release. For a new minor or major version, do [update-changelog](#) and then jump to [release](#). For a bug fix to an existing release, do [update-changelog](#) and then jump to [bugfix](#).

Changes that are not backwards-compatible may only be made in a major release. New features that do not affect backwards-compatibility can be made in a minor release. Bug fix releases should be small, only fix bugs, and not introduce any new features.

There are a few steps that *should* have been kept up-to-date during day-to-day development, but might not be quite accurate. For every change that is going to be part of your release, make sure that:

- The user guide in the documentation is updated with any new features, or changes to existing features.
- Any new API classes or functions have entries in a suitable RST file in `doc/apidoc`.
- Any new or changed docstrings are up-to-date and render correctly in the API documentation.

Please make a normal PR to `master` correcting anything missing from these points and have it merged before you begin the release, if necessary.

Updating the Requirements

Ensure that QuTiP’s tests pass on the oldest version supported in the requirements. On major and minor version, requirements can be adjusted upwards, but patch release must not change minimum requirements. We follow [NEP29](#) for minimum supported versions

```
- All minor versions of Python released 42 months prior to the project, and at
↳minimum the two latest minor versions.
- All minor versions of numpy and scipy released in the 24 months prior to the
↳project, and at minimum the last three minor versions.
```

If dependency versions need to be updated, update them in the master branch. The following files may need to be updated: `.github/workflows/tests.yml`, `setup.cfg` and `roadmap.rst`. Finally, ensure that PyPI wheels and conda builds cover at least these versions.

Updating the Changelog

This needs to be done no matter what type of release is being made.

1. Create a new branch to use to make a pull request.
2. Update the changelog using `towncrier`:

```
towncrier build --version=<version-number>
```

Where `<version-number>` is the expected version number of the release

1. Make a pull request on the main `qutip/qutip` repository with this changelog, and get other members of the admin team to approve it.
2. Merge this into `master`.

Now jump to [release](#) if you are making a major or minor release, or [bugfix](#) if you are only fixing bugs in a previous release.

Create a New Minor or Major Release

This involves making a new branch to hold the release and adding some commits to set the code into “release” mode. This release should be done by branching directly off the `master` branch at its current head.

1. On your machine, make sure your copy of `master` is up-to-date (`git checkout master; git pull upstream master`). This should at least involve fetching the changelog PR that you just made. Now create a new branch off a commit in `master` that has the state of the code you want to release. The command is `git checkout -b qutip-<major>.<minor>.X`, for example `qutip-4.7.X`. This branch name will be public, and must follow this format.
2. Push the new branch (with no commits in it relative to `master`) to the main `qutip/qutip` repository (`git push upstream qutip-4.7.X`). Creating a branch is one of the only situations in which it is ok to push to `qutip/qutip` without making a pull request.
3. Create a second new branch, which will be pushed to your fork and used to make a pull request against the `qutip-<major>.<minor>.X` branch on `qutip/qutip` you just created. You can call this branch whatever you like because it is not going to the main repository, for example `git checkout -b prepare-qutip-4.7.0`.
4.
 - Change the `VERSION` file to contain the new version number exactly, removing the `.dev` suffix. For example, if you are releasing the first release of the minor 4.7 track, set `VERSION` to contain the string `4.7.0`. (*Special circumstances:* if you are making an alpha, beta or release candidate release, append a `.a<n>`, `.b<n>` or `.rc<n>` to the version string, where `<n>` is an integer starting from 0 that counts how many of that pre-release track there have been.)
 - Edit `setup.cfg` by changing the “Development Status” line in the `classifiers` section to

`Development Status :: 5 - Production/Stable`

`Commit both changes (git add VERSION setup.cfg; git commit -m "Set release mode for 4.7.0"), and then push them to your fork (git push -u origin prepare-qutip-4.7.0)`

- Using GitHub, make a pull request to the release branch (e.g. `qutip-4.7.X`) using this branch that you just created. You will need to change the “base branch” in the pull request, because GitHub will always try to make the PR against `master` at first. When the tests have passed, merge this in.
- Finally, back on `master`, make a new pull request that changes the `VERSION` file to be `<next-expected-version>.dev`, for example `4.8.0.dev`. The “Development Status” in `setup.cfg` on `master` should not have changed, and should be

`Development Status :: 2 - Pre-Alpha`

because `master` is never directly released.

You should now have a branch that you can see on the GitHub website that is called `qutip-4.7.X` (or whatever minor version), and the state of the code in it should be exactly what you want to release as the new minor release. If you notice you have made a mistake, you can make additional pull requests to the release branch to fix it. `master` should look pretty similar, except the `VERSION` will be higher and have a `.dev` suffix, and the “Development Status” in `setup.cfg` will be different.

You are now ready to actually perform the release. Go to [deploy](#).

Create a Bug Fix Release

In this you will modify an already-released branch by “cherry-picking” one or more pull requests that have been merged to `master` (including your new changelog), and bump the “patch” part of the version number.

- On your machine, make sure your copy of `master` is up-to-date (`git checkout master; git pull upstream master`). In particular, make sure the changelog you wrote in the first step is visible.
- Find the branch of the release that you will be modifying. This should already exist on the `qutip/qutip` repository, and be called `qutip-<major>.<minor>.X` (e.g. `qutip-4.6.X`). If you cannot see it, run `git fetch upstream` to update all the branch references from the main repository. Checkout a new private branch, starting from the head of the release branch (`git checkout -b prepare-qutip-4.6.1 upstream/qutip-4.6.X`). You can call this branch whatever you like (in the example it is `prepare-qutip-4.6.1`), because it will only be used to make a pull request.
- Cherry-pick all the commits that will be added to this release in order, including your PR that wrote the new changelog entries (this will be the last one you cherry-pick). You will want to use `git log` to find the relevant commits, going from **oldest to newest** (their “age” is when they were merged into `master`, not when the PR was first opened). The command is slightly different depending on which merge strategy was used for a particular PR:
 - “merge”: you only need to find one commit though the log will have included several; there will be an entry in `git log` with a title such as “Merge pull request #1000 from <...>”. Note the first 7 characters of its hash. Cherry-pick this by `git cherry-pick --mainline 1 <hash>`.
 - “squash and merge”: there will only be a single commit for the entire PR. Its name will be “<Name of the pull request> (#1000)”. Note the first 7 characters of its hash. Cherry-pick this by `git cherry-pick <hash>`.
 - “rebase and merge”: this is the most difficult, because there will be many commits that you will have to find manually, and cherry-pick all of them. Go to the GitHub page for this PR, and go to the “Commits” tab. Using your local `git log` (you may find `git log --oneline` useful), find the hash for every single commit that is listed on the GitHub page, in order from **oldest to newest** (top-to-bottom in the GitHub view, which is bottom-to-top in `git log`). You will need to use the commit message to do this; the hashes that GitHub reports will probably not be the same as how they

appear locally. Find the first 7 characters of each of the hashes. Cherry-pick these all in one go by `git cherry-pick <hash1> <hash2> ... <hash10>`, where `<hash1>` is the oldest.

If any of the cherry-picks have merge conflicts, first verify that you are cherry-picking in order from oldest to newest. If you still have merge conflicts, you will either need to manually fix them (if it is a *very* simple fix), or else you will need to find which additional PR this patch depends on, and restart the bug fix process including this additional patch. This generally should not happen if you are sticking to very small bug fixes; if the fixes had far-reaching changes, a new minor release may be more appropriate.

4. Change the `VERSION` file by bumping the last number up by one (double-digit numbers are fine, so `4.6.10` comes after `4.6.9`), and commit the change.
5. Push this branch to your fork, and make a pull request against the release branch. On GitHub in the PR screen, you will need to change the “Base” branch to `qutip-4.6.X` (or whatever version), because GitHub will default to making it against `master`. It should be quite clear if you have forgotten to do this, because there will probably be many merge conflicts. Once the tests have passed and you have another admin’s approval, merge the PR.

You should now see that the `qutip-4.6.X` (or whatever) branch on GitHub has been updated, and now includes all the changes you have just made. If you have made a mistake, feel free to make additional PRs to rectify the situation.


You are now ready to actually perform the release. Go to [deploy](#).

8.5.3 Build Release Distribution and Deploy

This step builds the source (sdist) and binary (wheel) distributions, and uploads them to PyPI (pip). You will also be able to download the built files yourself in order to upload them to the QuTiP website.

Build and Deploy

This is handled entirely by a GitHub Action. Go to the “Actions” tab at the top of the QuTiP code repository. Click on the “Build wheels, optionally deploy to PyPI” action in the left-hand sidebar. Click the “Run workflow” dropdown in the header notification; it should look like the image below.




- Use the drop-down menu to choose the branch or tag you want to release from. This should be called `qutip-4.5.X` or similar, depending on what you made earlier. This must *never* be `master`.

- To make the release to PyPI, type the branch name (e.g. `qutip-4.5.x`) into the “Confirm chosen branch name [...]” field. You *may* leave this field blank to skip the deployment and only build the package.
- (Special circumstances) If for some reason you need to override the version number (for example if the previous deployment to PyPI only partially succeeded), you can type a valid Python version identifier into the “Override version number” field. You probably do not need to do this. The mechanism is designed to make alpha-testing major upgrades with nightly releases easier. For even a bugfix release, you should commit the change to the `VERSION` file.
- Click the lower “Run workflow” to perform the build and deployment.

At this point, the deployment will take care of itself. It should take between 30 minutes and an hour, after which the new version will be available for install by `pip install qutip`. You should see the new version appear on [QuTiP’s PyPI page](#).

Download Built Files

When the build is complete, click into its summary screen. This is the main screen used to both monitor the build and see its output, and should look like the below image on a success.



The built binary wheels and the source distribution are the “build artifacts” at the bottom. You need to download both the wheels and the source distribution. Save them on your computer, and unzip both files; you should have many wheel `qutip-*.whl` files, and two sdist files: `qutip-*.tar.gz` and `qutip-*.zip`. These are the same files that have just been uploaded to PyPI.

Monitoring Progress (optional)

While the build is in progress, you can monitor its progress by clicking on its entry in the list below the “Run workflow” button. You should see several subjobs, like the completed screen, except they might not yet be completed.

The “Verify PyPI deployment confirmation” should get ticked, no matter what. If it fails, you have forgotten to choose the correct branch in the drop-down menu or you made a typo when confirming the correct branch, and you will need to restart this step. You can check that the deployment instruction has been understood by clicking the “Verify PyPI deployment confirmation” job, and opening the “Compare confirmation to current reference” subjob. You will see a message saying “Built wheels will be deployed” if you typed in the confirmation, or “Only

building wheels” if you did not. If you see “Only building wheels” but you meant to deploy the release to PyPI, you can cancel the workflow and re-run it after typing the confirmation.

8.5.4 Getting the Built Documentation

The documentation will have been built automatically for you by a GitHub Action when you merged the final pull request into the release branch before building the wheels. You do not need to re-release the documentation on either GitHub or the website if this is a patch release, unless there were changes within it.

Go to the “Actions” tab at the top of the `qutip/qutip` repository, and click the “Build HTML documentation” heading in the left column. You should see a list of times this action has run; click the most recent one whose name is exactly “Build HTML documentation”, with the release branch name next to it (e.g. `qutip-4.6.X`). Download the `qutip_html_docs` artifact to your local machine and unzip it somewhere safe. These are all the HTML files for the built documentation; you should be able to open `index.html` in your own web browser and check that everything is working.

8.5.5 Making a Release on GitHub

This is all done through the “Releases” section of the `qutip/qutip` repository on GitHub.

- Click the “Draft a new release” button.
- Choose the correct branch for your release (e.g. `qutip-4.5.X`) in the drop-down.
- For the tag name, use `v<your-version>`, where the version matches the contents of the `VERSION` file. In other words, if you are releasing a micro version 4.5.3, use `v4.5.3` as the tag, or if you are releasing major version 5.0.0, use `v5.0.0`.
- The title is “QuTiP <your-version>”, e.g. “QuTiP 4.6.0”.
- For the description, write a short (~two-line for a patch release) summary of the reason for this release, and note down any particular user-facing changes that need special attention. Underneath, put the changelog you wrote when you did the documentation release. Note that there may be some syntax differences between the `.rst` file of the changelog and the Markdown of this description field (for example, GitHub’s markdown typically maintains hard-wrap linebreaks, which is probably not what you wanted).
- Drag-and-drop all the `qutip-*.whl`, `qutip-*.tar.gz` and `qutip-*.zip` files you got after the build step into the assets box. You may need to unzip the files `wheels.zip` and `sdist.zip` to find them if you haven’t already; **don’t** upload those two zip files.

Click on the “Publish release” button to finalise.

8.5.6 Website

This assumes that `qutip.github.io` has already been forked and familiarity with the website updating workflow. The documentation need not be updated for every patch release.

Copying New Files

You only need to copy in new documentation to the website repository. Do not copy the `.whl`, `.tar.gz` or `.zip` files into the git repository, because we can access the public links from the GitHub release stage, and this keeps the website `.git` folder a reasonable size.

For all releases move (no new docs) or copy (for new docs) the `qutip-doc-<MAJOR>.<MINOR>.pdf` into the folder `downloads/<MAJOR>.<MINOR>.<MICRO>`.

The legacy html documentation should be in a subfolder like

```
docs/<MAJOR>.<MINOR>
```

For a major or minor release the previous version documentation should be moved into this folder.

The latest version HTML documentation should be the folder

```
docs/latest
```

For any release which new documentation is included - copy the contents `qutip/doc/_build/html` into this folder. **Note that the underscores at start of the subfolder names will need to be removed, otherwise Jekyll will ignore the folders.** There is a script in the docs folder for this. https://github.com/qutip/qutip.github.io/blob/master/docs/remove_leading_underscores.py

HTML File Updates

- Edit `download.html`
 - The ‘Latest release’ version and date should be updated.
 - The tar.gz and zip links need to have their micro release numbers updated in their filenames, labels and `trackEvent` javascript. These links should point to the “Source code” links that appeared when you made in the GitHub Releases section. They should look something like `https://github.com/qutip/qutip/archive/refs/tags/v4.6.0.tar.gz`.
 - For a minor or major release links to the last micro release of the previous version will need to be moved (copied) to the ‘Previous releases’ section.
- Edit `_includes/sidebar.html`
 - The ‘Latest release’ version should be updated. The `gztar` and `zip` file links will need the micro release number updating in the `trackEvent` and file name.
 - The link to the documentation folder and PDF file (if created) should be updated.
- Edit `documentation.html`
 - The previous release tags should be moved (copied) to the ‘Previous releases’ section.

8.5.7 Conda Forge

If not done previously then fork the [qutip-feedstock](#).

Checkout a new branch on your fork, e.g.

```
$ git checkout -b version-4.0.2
```

Find the sha256 checksum for the tarball that the GitHub web interface generated when you produced the release called “Source code”. This is *not* the sdist that you downloaded earlier, it’s a new file that GitHub labels “Source code”. When you download it, though, it will have a name that *looks* like it’s the sdist

```
$ openssl sha256 qutip-4.0.2.tar.gz
```

Edit the `recipe/meta.yaml` file. Change the version at the top of the file, and update the sha256 checksum. Check that the recipe package version requirements at least match those in `setup.cfg`, and that any changes to the build process are reflected in `meta.yaml`. Also ensure that the build number is reset

```
build:  
  number: 0
```

Push changes to your fork, e.g.

```
$ git push --set-upstream origin version-4.0.2
```

Make a Pull Request. This will trigger tests of the package build process.

If (when) the tests pass, the PR can be merged, which will trigger the upload of the packages to the conda-forge channel. To test the packages, add the conda-forge channel with lowest priority

```
$ conda config --append channels conda-forge
```

This should mean that the prerequisites come from the default channel, but the qutip packages are found in conda-forge.

Chapter 9

Bibliography

Chapter 10

Copyright and Licensing

The text of this documentation is licensed under the [Creative Commons Attribution 3.0 Unported License](https://creativecommons.org/licenses/by/3.0/). Unless specifically indicated otherwise, all code samples, the source code of QuTiP, and its reproductions in this documentation, are licensed under the terms of the 3-clause BSD license, reproduced below.

10.1 License Terms for Documentation Text

The canonical form of this license is available at <https://creativecommons.org/licenses/by/3.0/>, which should be considered the binding version of this license. It is reproduced here for convenience.

THE WORK (AS DEFINED BELOW) IS PROVIDED UNDER THE TERMS OF THIS CREATIVE COMMONS PUBLIC LICENSE (“CCPL” OR “LICENSE”). THE WORK IS PROTECTED BY COPYRIGHT AND/OR OTHER APPLICABLE LAW. ANY USE OF THE WORK OTHER THAN AS AUTHORIZED UNDER THIS LICENSE OR COPYRIGHT LAW IS PROHIBITED.

BY EXERCISING ANY RIGHTS TO THE WORK PROVIDED HERE, YOU ACCEPT AND AGREE TO BE BOUND BY THE TERMS OF THIS LICENSE. TO THE EXTENT THIS LICENSE MAY BE CONSIDERED TO BE A CONTRACT, THE LICENSOR GRANTS YOU THE RIGHTS CONTAINED HERE IN CONSIDERATION OF YOUR ACCEPTANCE OF SUCH TERMS AND CONDITIONS.

1. Definitions

- a. “Adaptation” means a work based upon the Work, or upon the Work and other pre-existing works, such as a translation, adaptation, derivative work, arrangement of music or other alterations of a literary or artistic work, or phonogram or performance and includes cinematographic adaptations or any other form in which the Work may be recast, transformed, or adapted including in any form recognizably derived from the original, except that a work that constitutes a Collection will not be considered an Adaptation for the purpose of this License. For the avoidance of doubt, where the Work is a musical work, performance or phonogram, the synchronization of the Work in timed-relation with a moving image (“synching”) will be considered an Adaptation for the purpose of this License.
- b. “Collection” means a collection of literary or artistic works, such as encyclopedias and anthologies, or performances, phonograms or broadcasts, or other works or subject matter other than works listed in Section 1(f) below, which, by reason of the selection and arrangement of their contents, constitute intellectual creations, in which the Work is included in its entirety in unmodified form along with one or more other contributions, each constituting separate and independent works in themselves, which together are assembled into a collective whole. A work that constitutes a Collection will not be considered an Adaptation (as defined above) for the purposes of this License.
- c. “Distribute” means to make available to the public the original and copies of the Work or Adaptation, as appropriate, through sale or other transfer of ownership.
- d. “Licensor” means the individual, individuals, entity or entities that offer(s) the Work under the terms of this License.

- e. “Original Author” means, in the case of a literary or artistic work, the individual, individuals, entity or entities who created the Work or if no individual or entity can be identified, the publisher; and in addition (i) in the case of a performance the actors, singers, musicians, dancers, and other persons who act, sing, deliver, declaim, play in, interpret or otherwise perform literary or artistic works or expressions of folklore; (ii) in the case of a phonogram the producer being the person or legal entity who first fixes the sounds of a performance or other sounds; and, (iii) in the case of broadcasts, the organization that transmits the broadcast.
 - f. “Work” means the literary and/or artistic work offered under the terms of this License including without limitation any production in the literary, scientific and artistic domain, whatever may be the mode or form of its expression including digital form, such as a book, pamphlet and other writing; a lecture, address, sermon or other work of the same nature; a dramatic or dramatico-musical work; a choreographic work or entertainment in dumb show; a musical composition with or without words; a cinematographic work to which are assimilated works expressed by a process analogous to cinematography; a work of drawing, painting, architecture, sculpture, engraving or lithography; a photographic work to which are assimilated works expressed by a process analogous to photography; a work of applied art; an illustration, map, plan, sketch or three-dimensional work relative to geography, topography, architecture or science; a performance; a broadcast; a phonogram; a compilation of data to the extent it is protected as a copyrightable work; or a work performed by a variety or circus performer to the extent it is not otherwise considered a literary or artistic work.
 - g. “You” means an individual or entity exercising rights under this License who has not previously violated the terms of this License with respect to the Work, or who has received express permission from the Licensor to exercise rights under this License despite a previous violation.
 - h. “Publicly Perform” means to perform public recitations of the Work and to communicate to the public those public recitations, by any means or process, including by wire or wireless means or public digital performances; to make available to the public Works in such a way that members of the public may access these Works from a place and at a place individually chosen by them; to perform the Work to the public by any means or process and the communication to the public of the performances of the Work, including by public digital performance; to broadcast and rebroadcast the Work by any means including signs, sounds or images.
 - i. “Reproduce” means to make copies of the Work by any means including without limitation by sound or visual recordings and the right of fixation and reproducing fixations of the Work, including storage of a protected performance or phonogram in digital form or other electronic medium.
2. Fair Dealing Rights. Nothing in this License is intended to reduce, limit, or restrict any uses free from copyright or rights arising from limitations or exceptions that are provided for in connection with the copyright protection under copyright law or other applicable laws.
3. License Grant. Subject to the terms and conditions of this License, Licensor hereby grants You a worldwide, royalty-free, non-exclusive, perpetual (for the duration of the applicable copyright) license to exercise the rights in the Work as stated below:
- a. to Reproduce the Work, to incorporate the Work into one or more Collections, and to Reproduce the Work as incorporated in the Collections;
 - b. to create and Reproduce Adaptations provided that any such Adaptation, including any translation in any medium, takes reasonable steps to clearly label, demarcate or otherwise identify that changes were made to the original Work. For example, a translation could be marked “The original work was translated from English to Spanish,” or a modification could indicate “The original work has been modified.”;
 - c. to Distribute and Publicly Perform the Work including as incorporated in Collections; and,
 - d. to Distribute and Publicly Perform Adaptations.

For the avoidance of doubt:

- i. Non-waivable Compulsory License Schemes. In those jurisdictions in which the right to collect royalties through any statutory or compulsory licensing scheme cannot be waived, the Licensor reserves the exclusive right to collect such royalties for any exercise by You of the rights granted under this License;

- ii. Waivable Compulsory License Schemes. In those jurisdictions in which the right to collect royalties through any statutory or compulsory licensing scheme can be waived, the Licensor waives the exclusive right to collect such royalties for any exercise by You of the rights granted under this License; and,
- iii. Voluntary License Schemes. The Licensor waives the right to collect royalties, whether individually or, in the event that the Licensor is a member of a collecting society that administers voluntary licensing schemes, via that society, from any exercise by You of the rights granted under this License.

The above rights may be exercised in all media and formats whether now known or hereafter devised. The above rights include the right to make such modifications as are technically necessary to exercise the rights in other media and formats. Subject to Section 8(f), all rights not expressly granted by Licensor are hereby reserved.

4. Restrictions. The license granted in Section 3 above is expressly made subject to and limited by the following restrictions:
 - a. You may Distribute or Publicly Perform the Work only under the terms of this License. You must include a copy of, or the Uniform Resource Identifier (URI) for, this License with every copy of the Work You Distribute or Publicly Perform. You may not offer or impose any terms on the Work that restrict the terms of this License or the ability of the recipient of the Work to exercise the rights granted to that recipient under the terms of the License. You may not sublicense the Work. You must keep intact all notices that refer to this License and to the disclaimer of warranties with every copy of the Work You Distribute or Publicly Perform. When You Distribute or Publicly Perform the Work, You may not impose any effective technological measures on the Work that restrict the ability of a recipient of the Work from You to exercise the rights granted to that recipient under the terms of the License. This Section 4(a) applies to the Work as incorporated in a Collection, but this does not require the Collection apart from the Work itself to be made subject to the terms of this License. If You create a Collection, upon notice from any Licensor You must, to the extent practicable, remove from the Collection any credit as required by Section 4(b), as requested. If You create an Adaptation, upon notice from any Licensor You must, to the extent practicable, remove from the Adaptation any credit as required by Section 4(b), as requested.
 - b. If You Distribute, or Publicly Perform the Work or any Adaptations or Collections, You must, unless a request has been made pursuant to Section 4(a), keep intact all copyright notices for the Work and provide, reasonable to the medium or means You are utilizing: (i) the name of the Original Author (or pseudonym, if applicable) if supplied, and/or if the Original Author and/or Licensor designate another party or parties (e.g., a sponsor institute, publishing entity, journal) for attribution (“Attribution Parties”) in Licensor’s copyright notice, terms of service or by other reasonable means, the name of such party or parties; (ii) the title of the Work if supplied; (iii) to the extent reasonably practicable, the URI, if any, that Licensor specifies to be associated with the Work, unless such URI does not refer to the copyright notice or licensing information for the Work; and (iv) , consistent with Section 3(b), in the case of an Adaptation, a credit identifying the use of the Work in the Adaptation (e.g., “French translation of the Work by Original Author,” or “Screenplay based on original Work by Original Author”). The credit required by this Section 4 (b) may be implemented in any reasonable manner; provided, however, that in the case of a Adaptation or Collection, at a minimum such credit will appear, if a credit for all contributing authors of the Adaptation or Collection appears, then as part of these credits and in a manner at least as prominent as the credits for the other contributing authors. For the avoidance of doubt, You may only use the credit required by this Section for the purpose of attribution in the manner set out above and, by exercising Your rights under this License, You may not implicitly or explicitly assert or imply any connection with, sponsorship or endorsement by the Original Author, Licensor and/or Attribution Parties, as appropriate, of You or Your use of the Work, without the separate, express prior written permission of the Original Author, Licensor and/or Attribution Parties.
 - c. Except as otherwise agreed in writing by the Licensor or as may be otherwise permitted by applicable law, if You Reproduce, Distribute or Publicly Perform the Work either by itself or as part of any Adaptations or Collections, You must not distort, mutilate, modify or take other derogatory action in relation to the Work which would be prejudicial to the Original Author’s honor or reputation. Licensor agrees that in those jurisdictions (e.g. Japan), in which any exercise of the right granted in Section 3(b) of this License (the right to make Adaptations) would be deemed to be a distortion, mutilation,

modification or other derogatory action prejudicial to the Original Author's honor and reputation, the Licensor will waive or not assert, as appropriate, this Section, to the fullest extent permitted by the applicable national law, to enable You to reasonably exercise Your right under Section 3(b) of this License (right to make Adaptations) but not otherwise.

5. Representations, Warranties and Disclaimer

UNLESS OTHERWISE MUTUALLY AGREED TO BY THE PARTIES IN WRITING, LICENSOR OFFERS THE WORK AS-IS AND MAKES NO REPRESENTATIONS OR WARRANTIES OF ANY KIND CONCERNING THE WORK, EXPRESS, IMPLIED, STATUTORY OR OTHERWISE, INCLUDING, WITHOUT LIMITATION, WARRANTIES OF TITLE, MERCHANTIBILITY, FITNESS FOR A PARTICULAR PURPOSE, NONINFRINGEMENT, OR THE ABSENCE OF LATENT OR OTHER DEFECTS, ACCURACY, OR THE PRESENCE OF ABSENCE OF ERRORS, WHETHER OR NOT DISCOVERABLE. SOME JURISDICTIONS DO NOT ALLOW THE EXCLUSION OF IMPLIED WARRANTIES, SO SUCH EXCLUSION MAY NOT APPLY TO YOU.

6. Limitation on Liability. EXCEPT TO THE EXTENT REQUIRED BY APPLICABLE LAW, IN NO EVENT WILL LICENSOR BE LIABLE TO YOU ON ANY LEGAL THEORY FOR ANY SPECIAL, INCIDENTAL, CONSEQUENTIAL, PUNITIVE OR EXEMPLARY DAMAGES ARISING OUT OF THIS LICENSE OR THE USE OF THE WORK, EVEN IF LICENSOR HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

7. Termination

- a. This License and the rights granted hereunder will terminate automatically upon any breach by You of the terms of this License. Individuals or entities who have received Adaptations or Collections from You under this License, however, will not have their licenses terminated provided such individuals or entities remain in full compliance with those licenses. Sections 1, 2, 5, 6, 7, and 8 will survive any termination of this License.
- b. Subject to the above terms and conditions, the license granted here is perpetual (for the duration of the applicable copyright in the Work). Notwithstanding the above, Licensor reserves the right to release the Work under different license terms or to stop distributing the Work at any time; provided, however that any such election will not serve to withdraw this License (or any other license that has been, or is required to be, granted under the terms of this License), and this License will continue in full force and effect unless terminated as stated above.

8. Miscellaneous

- a. Each time You Distribute or Publicly Perform the Work or a Collection, the Licensor offers to the recipient a license to the Work on the same terms and conditions as the license granted to You under this License.
- b. Each time You Distribute or Publicly Perform an Adaptation, Licensor offers to the recipient a license to the original Work on the same terms and conditions as the license granted to You under this License.
- c. If any provision of this License is invalid or unenforceable under applicable law, it shall not affect the validity or enforceability of the remainder of the terms of this License, and without further action by the parties to this agreement, such provision shall be reformed to the minimum extent necessary to make such provision valid and enforceable.
- d. No term or provision of this License shall be deemed waived and no breach consented to unless such waiver or consent shall be in writing and signed by the party to be charged with such waiver or consent.
- e. This License constitutes the entire agreement between the parties with respect to the Work licensed here. There are no understandings, agreements or representations with respect to the Work not specified here. Licensor shall not be bound by any additional provisions that may appear in any communication from You. This License may not be modified without the mutual written agreement of the Licensor and You.
- f. The rights granted under, and the subject matter referenced, in this License were drafted utilizing the terminology of the Berne Convention for the Protection of Literary and Artistic Works (as amended on September 28, 1979), the Rome Convention of 1961, the WIPO Copyright Treaty of 1996, the WIPO Performances and Phonograms Treaty of 1996 and the Universal Copyright Convention (as revised on July 24, 1971). These rights and subject matter take effect in the relevant jurisdiction in

which the License terms are sought to be enforced according to the corresponding provisions of the implementation of those treaty provisions in the applicable national law. If the standard suite of rights granted under applicable copyright law includes additional rights not granted under this License, such additional rights are deemed to be included in the License; this License is not intended to restrict the license of any rights under applicable law.

10.2 License Terms for Source Code of QuTiP and Code Samples

Copyright (c) 2011 to 2022 inclusive, QuTiP developers and contributors. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
3. Neither the name of the copyright holder nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS “AS IS” AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT HOLDER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

Chapter 11

Indices and tables

- `genindex`
- `modindex`
- `search`

Bibliography

- [LACN19] Neill Lambert, Shah Nawaz Ahmed, Mauro Cirio, and Franco Nori. Virtual excitations in the ultra-strongly-coupled spin-boson model: physical results from unphysical modes. *arXiv preprint arXiv:1903.05892*, 2019.
- [Tan20] Yoshitaka Tanimura. Numerically “exact” approach to open quantum dynamics: the hierarchical equations of motion (heom). *The Journal of Chemical Physics*, 153(2):020901, 2020. URL: <https://doi.org/10.1063/5.0011599>, doi:10.1063/5.0011599.
- [TK89] Yoshitaka Tanimura and Ryogo Kubo. Time evolution of a quantum system in contact with a nearly gaussian-markoffian noise bath. *J. Phys. Soc. Jpn.*, 58(1):101–114, 1989. doi:10.1143/jpsj.58.101.
- [1] P. Doria, T. Calarco & S. Montangero. *Phys. Rev. Lett.* 106, 190501 (2011).
- [2] T. Caneva, T. Calarco, & S. Montangero. *Phys. Rev. A* 84, 022326 (2011).
- [1] Shore, B. W., “The Theory of Coherent Atomic Excitation”, Wiley, 1990.
- [1] [https://en.wikipedia.org/wiki/Concurrence_\(quantum_computing\)](https://en.wikipedia.org/wiki/Concurrence_(quantum_computing))
- [1] Peter E. Kloeden and Exkhard Platen, *Numerical Solution of Stochastic Differential Equations*.
- [2] H.-P. Breuer and F. Petruccione, *The Theory of Open Quantum Systems*.
- [3] Pierre Rouchon and Jason F. Ralph, *Efficient Quantum Filtering for Quantum Feedback Control*, [arXiv:1410.5345](https://arxiv.org/abs/1410.5345) [quant-ph], *Phys. Rev. A* 91, 012118, (2015).
- [4] Howard M. Wiseman, Gerard J. Milburn, *Quantum measurement and control*.
- [1] J. Rodriguez-Laguna, P. Migdal, M. Ibanez Berganza, M. Lewenstein and G. Sierra, *Qubism: self-similar visualization of many-body wavefunctions*, *New J. Phys.* 14 053028, [arXiv:1112.3560](https://arxiv.org/abs/1112.3560) (2012), open access.
- [BCSZ08] W. Bruzda, V. Cappellini, H.-J. Sommers, K. Życzkowski, *Random Quantum Operations*, *Phys. Lett. A* **373**, 320-324 (2009). doi:10.1016/j.physleta.2008.11.043.
- [Hav03] Havel, T. *Robust procedures for converting among Lindblad, Kraus and matrix representations of quantum dynamical semigroups*. *Journal of Mathematical Physics* **44** 2, 534 (2003). doi:10.1063/1.1518555.
- [Wat13] Watrous, J. *Theory of Quantum Information*, lecture notes.
- [Mez07] F. Mezzadri, *How to generate random matrices from the classical compact groups*, *Notices of the AMS* **54** 592-604 (2007). [arXiv:math-ph/0609050](https://arxiv.org/abs/math-ph/0609050).
- [Moh08] M. Mohseni, A. T. Rezakhani, D. A. Lidar, *Quantum-process tomography: Resource analysis of different strategies*, *Phys. Rev. A* **77**, 032322 (2008). doi:10.1103/PhysRevA.77.032322.
- [Gri98] M. Grifoni, P. Hänggi, *Driven quantum tunneling*, *Physics Reports* **304**, 299 (1998). doi:10.1016/S0370-1573(98)00022-2.
- [Gar03] Gardineer and Zoller, *Quantum Noise* (Springer, 2004).
- [Bre02] H.-P. Breuer and F. Petruccione, *The Theory of Open Quantum Systems* (Oxford, 2002).
- [Coh92] C. Cohen-Tannoudji, J. Dupont-Roc, G. Grynberg, *Atom-Photon Interactions: Basic Processes and Applications*, (Wiley, 1992).

- [WBC11] C. Wood, J. Biamonte, D. G. Cory, *Tensor networks and graphical calculus for open quantum systems*. [arXiv:1111.6950](#)
- [dAless08] D. d'Alessandro, *Introduction to Quantum Control and Dynamics*, (Chapman & Hall/CRC, 2008).
- [Byrd95] R. H. Byrd, P. Lu, J. Nocedal, and C. Zhu, *A Limited Memory Algorithm for Bound Constrained Optimization*, SIAM J. Sci. Comput. **16**, 1190 (1995). [doi:10.1137/0916069](#)
- [Flo12] F. Floether, P. de Fouquieres, and S. G. Schirmer, *Robust quantum gates for open systems via optimal control: Markovian versus non-Markovian dynamics*, New J. Phys. **14**, 073023 (2012). [doi:10.1088/1367-2630/14/7/073023](#)
- [Lloyd14] S. Lloyd and S. Montangero, *Information theoretical analysis of quantum optimal control*, Phys. Rev. Lett. **113**, 010502 (2014). [doi:10.1103/PhysRevLett.113.010502](#)
- [Doria11] P. Doria, T. Calarco & S. Montangero, *Optimal Control Technique for Many-Body Quantum Dynamics*, Phys. Rev. Lett. **106**, 190501 (2011). [doi:10.1103/PhysRevLett.106.190501](#)
- [Caneva11] T. Caneva, T. Calarco, & S. Montangero, *Chopped random-basis quantum optimization*, Phys. Rev. A **84**, 022326 (2011). [doi:10.1103/PhysRevA.84.022326](#)
- [Rach15] N. Rach, M. M. Müller, T. Calarco, and S. Montangero, *Dressing the chopped-random-basis optimization: A bandwidth-limited access to the trap-free landscape*, Phys. Rev. A. **92**, 062343 (2015). [doi:10.1103/PhysRevA.92.062343](#)
- [DYNAMO] S. Machnes, U. Sander, S. J. Glaser, P. De Fouquieres, A. Gruslys, S. Schirmer, and T. Schulte-Herbrueggen, *Comparing, Optimising and Benchmarking Quantum Control Algorithms in a Unifying Programming Framework*, Phys. Rev. A. **84**, 022305 (2010). [arXiv:1011.4874](#)
- [Wis09] Wiseman, H. M. & Milburn, G. J. *Quantum Measurement and Control*, (Cambridge University Press, 2009).
- [NKanej] N. Khaneja et. al. *Optimal control of coupled spin dynamics: Design of NMR pulse sequences by gradient ascent algorithms*. J. Magn. Reson. **172**, 296–305 (2005). [doi:10.1016/j.jmr.2004.11.004](#)

Python Module Index

q

- qutip, 342
- qutip.continuous_variables, 277
- qutip.control.pulsegen, 338
- qutip.control.pulseoptim, 325
- qutip.core.dimensions, 268
- qutip.core.expect, 270
- qutip.core.metrics, 274
- qutip.core.operators, 250
- qutip.core.qobj, 260
- qutip.core.states, 238
- qutip.core.superop_reps, 266
- qutip.core.superoperator, 264
- qutip.core.tensor, 270
- qutip.entropy, 272
- qutip.fileio, 339
- qutip.ipynbtools, 341
- qutip.matplotlib_utilities, 323
- qutip.measurement, 279
- qutip.orbital, 322
- qutip.partial_transpose, 271
- qutip.random_objects, 260
- qutip.solve.nonmarkov.transfertensor, 324
- qutip.solve.piqs, 308
- qutip.solve.stochastic, 292
- qutip.solver.brmsolve, 287
- qutip.solver.correlation, 299
- qutip.solver.floquet, 288
- qutip.solver.heom, 297
- qutip.solver.krylovsolve, 286
- qutip.solver.mcsolve, 284
- qutip.solver.mesolve, 283
- qutip.solver.parallel, 340
- qutip.solver.propagator, 306
- qutip.solver.scattering, 306
- qutip.solver.sesolve, 282
- qutip.solver.spectrum, 303
- qutip.solver.steadystate, 303
- qutip.three_level_atom, 264
- qutip.tomography, 323
- qutip.utilities, 339
- qutip.visualization, 316
- qutip.wigner, 313

Index

A

`about()` (in module *qutip*), 342
`add()` (*Result method*), 212
`add_annotation()` (*Bloch method*), 189
`add_arc()` (*Bloch method*), 189
`add_evo_comp_summary()` (*DynamicsDump method*), 237
`add_evo_dump()` (*DynamicsDump method*), 237
`add_iter_summary()` (*OptimDump method*), 236
`add_line()` (*Bloch method*), 189
`add_points()` (*Bloch method*), 189
`add_points()` (*Bloch3d method*), 192
`add_states()` (*Bloch method*), 190
`add_states()` (*Bloch3d method*), 192
`add_vectors()` (*Bloch method*), 190
`add_vectors()` (*Bloch3d method*), 192
`am()` (in module *qutip.solve.piqs*), 308
`ap()` (in module *qutip.solve.piqs*), 308
`apply_method_params()` (*Optimizer method*), 218
`apply_params()` (*Dynamics method*), 224
`apply_params()` (*FidelityComputer method*), 228
`apply_params()` (*Optimizer method*), 218
`apply_params()` (*PropagatorComputer method*), 227
`apply_params()` (*PulseGen method*), 231
`apply_params()` (*TimeslotComputer method*), 230
`arguments()` (*QobjEvo method*), 186
`average_gate_fidelity()` (in module *qutip.core.metrics*), 274

B

`basis()` (in module *qutip.core.states*), 238
Bath (class in *qutip.solver.heom*), 199
BathExponent (class in *qutip.solver.heom*), 199
`bell_state()` (in module *qutip.core.states*), 239
Bloch (class in *qutip.bloch*), 188
Bloch3d (class in *qutip.bloch3d*), 191
`block_matrix()` (in module *qutip.solve.piqs*), 308
BosonicBath (class in *qutip.solver.heom*), 200
`bra()` (in module *qutip.core.states*), 239
`brmesolve()` (in module *qutip.solver.brmesolve*), 287
BRSolver (class in *qutip.solver.brmesolve*), 194
`bures_angle()` (in module *qutip.core.metrics*), 274
`bures_dist()` (in module *qutip.core.metrics*), 274

C

`c_ops()` (*Dicke method*), 213

`calculate()` (*Stats method*), 235
`calculate_j_m()` (*Pim method*), 214
`calculate_k()` (*Pim method*), 214
`charge()` (in module *qutip.core.operators*), 250
`check_herm()` (*Qobj method*), 177
`check_unitarity()` (*DynamicsUnitary method*), 226
`clear()` (*Bloch method*), 190
`clear()` (*Bloch3d method*), 192
`clear()` (*FidCompUnitary method*), 229
`clear()` (*FidelityComputer method*), 228
`clebsch()` (in module *qutip.utilities*), 339
`coefficient_matrix()` (*Dicke method*), 213
`coefficient_matrix()` (*Pim method*), 215
`coherence_function_g1()` (in module *qutip.solver.correlation*), 299
`coherence_function_g2()` (in module *qutip.solver.correlation*), 299
`coherent()` (in module *qutip.core.states*), 240
`coherent_dm()` (in module *qutip.core.states*), 241
`collapse_dims_oper()` (in module *qutip.core.dimensions*), 268
`collapse_dims_super()` (in module *qutip.core.dimensions*), 268
`collapse_uncoupled()` (in module *qutip.solve.piqs*), 308
`combine()` (*BosonicBath class method*), 200
`combine_dyn_gen()` (*Dynamics method*), 224
`commutator()` (in module *qutip.core.operators*), 251
`compare_amps()` (*TSlotCompUpdateAll method*), 231
`complex_phase_cmap()` (in module *qutip.matplotlib_utilities*), 323
`composite()` (in module *qutip.core.tensor*), 270
`compress()` (*QobjEvo method*), 186
`compute_evolution()` (*Dynamics method*), 224
`compute_fid_err_grad()` (*FidCompTraceDiff method*), 230
`compute_fid_err_grad()` (*FidCompTraceDiffApprox method*), 230
`compute_fid_grad()` (*FidCompUnitary method*), 229
`concurrence()` (in module *qutip.entropy*), 272
`conj()` (*Qobj method*), 177
`conj()` (*QobjEvo method*), 187
`contract()` (*Qobj method*), 177
`convert_unit()` (in module *qutip.utilities*), 339
`copy()` (*Qobj method*), 178

- `copy()` (*QobjEvo method*), 187
 - `correlation_2op_1t()` (in module *qutip.solver.correlation*), 299
 - `correlation_2op_2t()` (in module *qutip.solver.correlation*), 300
 - `correlation_3op()` (in module *qutip.solver.correlation*), 301
 - `correlation_3op_1t()` (in module *qutip.solver.correlation*), 301
 - `correlation_3op_2t()` (in module *qutip.solver.correlation*), 302
 - `correlation_matrix()` (in module *qutip.continuous_variables*), 277
 - `correlation_matrix_field()` (in module *qutip.continuous_variables*), 277
 - `correlation_matrix_quadrature()` (in module *qutip.continuous_variables*), 277
 - `cosm()` (*Qobj method*), 178
 - `covariance_matrix()` (in module *qutip.continuous_variables*), 278
 - `create()` (in module *qutip.core.operators*), 251
 - `create_dump_dir()` (*Dump method*), 236
 - `create_pulse_gen()` (in module *qutip.control.pulsegen*), 338
 - `create_pulse_optimizer()` (in module *qutip.control.pulseoptim*), 325
 - `css()` (in module *qutip.solve.piqs*), 309
- ## D
- `dag()` (*Qobj method*), 178
 - `dag()` (*QobjEvo method*), 187
 - `deep_remove()` (in module *qutip.core.dimensions*), 268
 - `destroy()` (in module *qutip.core.operators*), 251
 - `diag()` (*Qobj method*), 178
 - `Dicke` (class in *qutip.solve.piqs*), 212
 - `dicke()` (in module *qutip.solve.piqs*), 309
 - `dicke_basis()` (in module *qutip.solve.piqs*), 309
 - `dicke_blocks()` (in module *qutip.solve.piqs*), 309
 - `dicke_blocks_full()` (in module *qutip.solve.piqs*), 310
 - `dicke_function_trace()` (in module *qutip.solve.piqs*), 310
 - `dims_idxes_to_tensor_idxes()` (in module *qutip.core.dimensions*), 268
 - `dims_to_tensor_perm()` (in module *qutip.core.dimensions*), 268
 - `dims_to_tensor_shape()` (in module *qutip.core.dimensions*), 269
 - `displace()` (in module *qutip.core.operators*), 252
 - `Distribution` (class in *qutip.distributions*), 216
 - `dnorm()` (in module *qutip.core.metrics*), 274
 - `dnorm()` (*Qobj method*), 178
 - `DrudeLorentzBath` (class in *qutip.solver.heom*), 200
 - `DrudeLorentzPadeBath` (class in *qutip.solver.heom*), 201
 - `dual_chan()` (*Qobj method*), 178
 - `Dump` (class in *qutip.control.dump*), 235
 - `dump_all()` (*DynamicsDump property*), 237
 - `dump_all()` (*OptimDump property*), 236
 - `dump_any()` (*DynamicsDump property*), 237
 - `dump_any()` (*OptimDump property*), 236
 - `dump_current()` (*TimeslotComputer method*), 231
 - `dumping()` (*Dynamics property*), 224
 - `dumping()` (*Optimizer property*), 218
 - `DumpItem` (class in *qutip.control.dump*), 237
 - `DumpSummaryItem` (class in *qutip.control.dump*), 238
 - `dyn_gen()` (*Dynamics property*), 225
 - `dyn_gen_phase()` (*Dynamics property*), 225
 - `dyn_gen_phase()` (*DynamicsSymplectic property*), 227
 - `Dynamics` (class in *qutip.control.dynamics*), 222
 - `DynamicsDump` (class in *qutip.control.dump*), 237
 - `DynamicsGenMat` (class in *qutip.control.dynamics*), 226
 - `DynamicsSymplectic` (class in *qutip.control.dynamics*), 227
 - `DynamicsUnitary` (class in *qutip.control.dynamics*), 226
- ## E
- `eigenenergies()` (*Qobj method*), 178
 - `eigenstates()` (*Qobj method*), 179
 - `energy_degeneracy()` (in module *qutip.solve.piqs*), 310
 - `enr_destroy()` (in module *qutip.core.operators*), 252
 - `enr_fock()` (in module *qutip.core.states*), 242
 - `enr_identity()` (in module *qutip.core.operators*), 253
 - `enr_state_dictionaries()` (in module *qutip.core.states*), 242
 - `enr_thermal_dm()` (in module *qutip.core.states*), 242
 - `entropy_conditional()` (in module *qutip.entropy*), 272
 - `entropy_linear()` (in module *qutip.entropy*), 272
 - `entropy_mutual()` (in module *qutip.entropy*), 272
 - `entropy_relative()` (in module *qutip.entropy*), 272
 - `entropy_vn()` (in module *qutip.entropy*), 273
 - `entropy_vn_dicke()` (in module *qutip.solve.piqs*), 310
 - `enumerate_flat()` (in module *qutip.core.dimensions*), 269
 - `estimate_num_coeffs()` (*PulseGenCrab method*), 234
 - `EvoCompDumpItem` (class in *qutip.control.dump*), 238
 - `excited()` (in module *qutip.solve.piqs*), 310
 - `expect()` (in module *qutip.core.expect*), 270
 - `expect()` (*QobjEvo method*), 187
 - `expect_data()` (*QobjEvo method*), 187
 - `expm()` (*Qobj method*), 179

`exps()` (*HierarchyADOs method*), 204
`extract()` (*HierarchyADOsState method*), 206

F

`FermionicBath` (*class in qutip.solver.heom*), 202
`fid_err_func_wrapper()` (*Optimizer method*), 219
`fid_err_grad_wrapper()` (*Optimizer method*), 219
`FidCompTraceDiff` (*class in qutip.control.fidcomp*), 229
`FidCompTraceDiffApprox` (*class in qutip.control.fidcomp*), 230
`FidCompUnitary` (*class in qutip.control.fidcomp*), 228
`fidelity()` (*in module qutip.core.metrics*), 275
`FidelityComputer` (*class in qutip.control.fidcomp*), 227
`file_data_read()` (*in module qutip.fileio*), 339
`file_data_store()` (*in module qutip.fileio*), 339
`filter()` (*HierarchyADOs method*), 205
`flag_system_changed()` (*Dynamics method*), 225
`flag_system_changed()` (*FidCompUnitary method*), 229
`flag_system_changed()` (*FidelityComputer method*), 228
`flatten()` (*in module qutip.core.dimensions*), 269
`floquet_tensor()` (*in module qutip.solver.floquet*), 290
`FloquetBasis` (*class in qutip.solver.floquet*), 289
`FMESolver` (*class in qutip.solver.floquet*), 288
`fmmsolve()` (*in module qutip.solver.floquet*), 291
`fock()` (*in module qutip.core.states*), 243
`fock_dm()` (*in module qutip.core.states*), 243
`from_floquet_basis()` (*FloquetBasis method*), 289
`fsesolve()` (*in module qutip.solver.floquet*), 292
`full()` (*Qobj method*), 179
`full_evo()` (*Dynamics property*), 225
`fwd_evo()` (*Dynamics property*), 225

G

`gen_pulse()` (*PulseGen method*), 231
`gen_pulse()` (*PulseGenCrabFourier method*), 234
`gen_pulse()` (*PulseGenGaussian method*), 233
`gen_pulse()` (*PulseGenGaussianEdge method*), 233
`gen_pulse()` (*PulseGenLinear method*), 232
`gen_pulse()` (*PulseGenRandom method*), 232
`gen_pulse()` (*PulseGenSaw method*), 233
`gen_pulse()` (*PulseGenSine method*), 233
`gen_pulse()` (*PulseGenSquare method*), 233
`gen_pulse()` (*PulseGenTriangle method*), 233
`gen_pulse()` (*PulseGenZero method*), 232
`general_stochastic()` (*in module qutip.solve.stochastic*), 292
`get_ctrl_dyn_gen()` (*Dynamics method*), 225

`get_drift_dim()` (*Dynamics method*), 225
`get_dyn_gen()` (*Dynamics method*), 225
`get_fid_err()` (*FidCompTraceDiff method*), 230
`get_fid_err()` (*FidCompUnitary method*), 229
`get_fid_err()` (*FidelityComputer method*), 228
`get_fid_err_gradient()` (*FidCompTraceDiff method*), 230
`get_fid_err_gradient()` (*FidCompUnitary method*), 229
`get_fid_err_gradient()` (*FidelityComputer method*), 228
`get_fidelity()` (*FidCompUnitary method*), 229
`get_fidelity_prenorm()` (*FidCompUnitary method*), 229
`get_num_ctrls()` (*Dynamics method*), 225
`get_optim_var_vals()` (*PulseGenCrab method*), 234
`get_timeslot_for_fidelity_calc()` (*TSlotCompUpdateAll method*), 231
`ghz()` (*in module qutip.solve.pigs*), 310
`ghz_state()` (*in module qutip.core.states*), 244
`ground()` (*in module qutip.solve.pigs*), 311
`groundstate()` (*Qobj method*), 179

H

`HarmonicOscillatorProbabilityFunction` (*class in qutip.distributions*), 217
`HarmonicOscillatorWaveFunction` (*class in qutip.distributions*), 217
`hellinger_dist()` (*in module qutip.core.metrics*), 275
`HEOMResult` (*class in qutip.solver.heom*), 206
`heomsolve()` (*in module qutip.solver.heom*), 297
`HEOMSolver` (*class in qutip.solver.heom*), 196
`HierarchyADOs` (*class in qutip.solver.heom*), 204
`HierarchyADOsState` (*class in qutip.solver.heom*), 206
`hilbert_dist()` (*in module qutip.core.metrics*), 276
`hinton()` (*in module qutip.visualization*), 316
`HSolverDL` (*class in qutip.solver.heom*), 198

I

`identity()` (*in module qutip.core.operators*), 253
`identity_uncoupled()` (*in module qutip.solve.pigs*), 311
`idx()` (*HierarchyADOs method*), 205
`init_coeffs()` (*PulseGenCrab method*), 234
`init_comp()` (*FidCompTraceDiff method*), 230
`init_comp()` (*FidCompUnitary method*), 229
`init_comp()` (*FidelityComputer method*), 228
`init_freqs()` (*PulseGenCrabFourier method*), 234
`init_normalization()` (*FidCompUnitary method*), 229
`init_optim()` (*Optimizer method*), 219
`init_optim()` (*OptimizerCrab method*), 220
`init_optim()` (*OptimizerLBFGSB method*), 220
`init_pulse()` (*PulseGen method*), 232

- [init_pulse\(\)](#) (*PulseGenCrab method*), 234
[init_pulse\(\)](#) (*PulseGenCrabFourier method*), 234
[init_pulse\(\)](#) (*PulseGenLinear method*), 232
[init_pulse\(\)](#) (*PulseGenPeriodic method*), 232
[init_timeslots\(\)](#) (*Dynamics method*), 225
[initialize_controls\(\)](#) (*Dynamics method*), 225
[initialize_controls\(\)](#) (*DynamicsUnitary method*), 226
[IntegratorDiag](#) (class in *qutip.solver.integrator.qutip_integrator*), 208
[IntegratorKrylov](#) (class in *qutip.solver.integrator.krylov*), 209
[IntegratorScipyAdams](#) (class in *qutip.solver.integrator.scipy_integrator*), 206
[IntegratorScipyBDF](#) (class in *qutip.solver.integrator.scipy_integrator*), 206
[IntegratorScipyDop853](#) (class in *qutip.solver.integrator.scipy_integrator*), 207
[IntegratorScipyIlsoda](#) (class in *qutip.solver.integrator.scipy_integrator*), 207
[IntegratorVern7](#) (class in *qutip.solver.integrator.qutip_integrator*), 208
[IntegratorVern9](#) (class in *qutip.solver.integrator.qutip_integrator*), 208
[inv\(\)](#) (*Qobj method*), 180
[is_scalar\(\)](#) (in module *qutip.core.dimensions*), 269
[isconstant](#) (*QobjEvo attribute*), 187
[isdiagonal\(\)](#) (in module *qutip.solve.piqs*), 311
[isdicke\(\)](#) (*Pim method*), 215
[isoper](#) (*QobjEvo attribute*), 187
[issuper](#) (*QobjEvo attribute*), 187
[iter_step_callback_func\(\)](#) (*Optimizer method*), 219
- ## J
- [jmat\(\)](#) (in module *qutip.core.operators*), 253
[jspin\(\)](#) (in module *qutip.solve.piqs*), 311
- ## K
- [ket\(\)](#) (in module *qutip.core.states*), 244
[ket2dm\(\)](#) (in module *qutip.core.states*), 245
[kraus_to_choi\(\)](#) (in module *qutip.core.superop_reps*), 266
[kraus_to_super\(\)](#) (in module *qutip.core.superop_reps*), 266
[krylovsolve\(\)](#) (in module *qutip.solver.krylovsolve*), 286
- ## L
- [level\(\)](#) (*Dump property*), 236
[lindblad_dissipator\(\)](#) (in module *qutip.core.superoperator*), 264
[lindbladnian\(\)](#) (*Dicke method*), 213
[linear_map\(\)](#) (*QobjEvo method*), 187
[liouvillian\(\)](#) (*Dicke method*), 213
[liouvillian\(\)](#) (in module *qutip.core.superoperator*), 265
[logarithmic_negativity\(\)](#) (in module *qutip.continuous_variables*), 278
[logm\(\)](#) (*Qobj method*), 180
[LorentzianBath](#) (class in *qutip.solver.heom*), 203
[LorentzianPadeBath](#) (class in *qutip.solver.heom*), 203
- ## M
- [m_degeneracy\(\)](#) (in module *qutip.solve.piqs*), 311
[make_sphere\(\)](#) (*Bloch method*), 190
[make_sphere\(\)](#) (*Bloch3d method*), 192
[marginal\(\)](#) (*Distribution method*), 216
[matmul\(\)](#) (*QobjEvo method*), 187
[matmul_data\(\)](#) (*QobjEvo method*), 187
[matrix_element\(\)](#) (*Qobj method*), 180
[matrix_histogram\(\)](#) (in module *qutip.visualization*), 316
[matrix_histogram_complex\(\)](#) (in module *qutip.visualization*), 317
[maximally_mixed_dm\(\)](#) (in module *qutip.core.states*), 245
[mcsolve\(\)](#) (in module *qutip.solver.mcsolve*), 284
[measure\(\)](#) (in module *qutip.measurement*), 279
[measure_observable\(\)](#) (in module *qutip.measurement*), 279
[measure_povm\(\)](#) (in module *qutip.measurement*), 280
[measurement_statistics\(\)](#) (in module *qutip.measurement*), 280
[measurement_statistics_observable\(\)](#) (in module *qutip.measurement*), 281
[measurement_statistics_povm\(\)](#) (in module *qutip.measurement*), 281
[MemoryCascade](#) (class in *qutip.solve.nonmarkov.memorycascade*), 209
[mesolve\(\)](#) (in module *qutip.solver.mesolve*), 283
[MESolver](#) (class in *qutip.solver.mesolve*), 194
[mode\(\)](#) (*FloquetBasis method*), 290
[module](#)
 qutip, 342
 qutip.continuous_variables, 277
 qutip.control.pulsegen, 338
 qutip.control.pulseoptim, 325
 qutip.core.dimensions, 268
 qutip.core.expect, 270
 qutip.core.metrics, 274
 qutip.core.operators, 250
 qutip.core.qobj, 260

- qutip.core.states, 238
 - qutip.core.superop_reps, 266
 - qutip.core.superoperator, 264
 - qutip.core.tensor, 270
 - qutip.entropy, 272
 - qutip.fileio, 339
 - qutip.ipynbtools, 341
 - qutip.matplotlib_utilities, 323
 - qutip.measurement, 279
 - qutip.orbital, 322
 - qutip.partial_transpose, 271
 - qutip.random_objects, 260
 - qutip.solve.nonmarkov.transfertensor, 324
 - qutip.solve.piqs, 308
 - qutip.solve.stochastic, 292
 - qutip.solver.brmsolve, 287
 - qutip.solver.correlation, 299
 - qutip.solver.floquet, 288
 - qutip.solver.heom, 297
 - qutip.solver.krylovsolve, 286
 - qutip.solver.mcsolve, 284
 - qutip.solver.mesolve, 283
 - qutip.solver.parallel, 340
 - qutip.solver.propagator, 306
 - qutip.solver.scattering, 306
 - qutip.solver.sesolve, 282
 - qutip.solver.spectrum, 303
 - qutip.solver.steadystate, 303
 - qutip.three_level_atom, 264
 - qutip.tomography, 323
 - qutip.utilities, 339
 - qutip.visualization, 316
 - qutip.wigner, 313
 - momentum() (in module qutip.core.operators), 254
- ## N
- n_thermal() (in module qutip.utilities), 339
 - next() (HierarchyADOs method), 205
 - norm() (Qobj method), 181
 - normalize_gradient_PSU() (FidCompUnitary method), 229
 - normalize_gradient_SU() (FidCompUnitary method), 229
 - num() (in module qutip.core.operators), 254
 - num_ctrls() (Dynamics property), 225
 - num_ctrls() (DynamicsUnitary property), 226
 - num_dicke_ladders() (in module qutip.solve.piqs), 312
 - num_dicke_states() (in module qutip.solve.piqs), 312
 - num_elements (QobjEvo attribute), 187
 - num_tls() (in module qutip.solve.piqs), 312
- ## O
- onto_evo() (Dynamics property), 225
 - onwd_evo() (Dynamics property), 225
 - operator_to_vector() (in module qutip.core.superoperator), 265
 - opt_pulse_crab() (in module qutip.control.pulseoptim), 328
 - opt_pulse_crab_unitary() (in module qutip.control.pulseoptim), 330
 - OptimDump (class in qutip.control.dump), 236
 - OptimIterSummary (class in qutip.control.optimizer), 221
 - optimize_pulse() (in module qutip.control.pulseoptim), 333
 - optimize_pulse_unitary() (in module qutip.control.pulseoptim), 335
 - Optimizer (class in qutip.control.optimizer), 217
 - OptimizerBFGS (class in qutip.control.optimizer), 219
 - OptimizerCrab (class in qutip.control.optimizer), 220
 - OptimizerCrabFmin (class in qutip.control.optimizer), 220
 - OptimizerLBFGSB (class in qutip.control.optimizer), 220
 - OptimResult (class in qutip.control.optimresult), 221
 - options() (BRSolver property), 195
 - options() (HEOMSolver property), 196
 - options() (IntegratorDiag property), 208
 - options() (IntegratorKrylov property), 209
 - options() (IntegratorScipyAdams property), 206
 - options() (IntegratorScipyBDF property), 207
 - options() (IntegratorScipyDop853 property), 207
 - options() (IntegratorScipylsoda property), 207
 - options() (IntegratorVern7 property), 208
 - options() (IntegratorVern9 property), 208
 - options() (SESolver property), 194
 - orbital() (in module qutip.orbital), 322
 - outfieldcorr() (MemoryCascade method), 209
 - outfieldpropagator() (MemoryCascade method), 210
 - overlap() (Qobj method), 181
- ## P
- parallel_map() (in module qutip.ipynbtools), 341
 - parallel_map() (in module qutip.solver.parallel), 340
 - partial_transpose() (in module qutip.partial_transpose), 271
 - permute() (Qobj method), 181
 - phase() (in module qutip.core.operators), 255
 - phase_application() (Dynamics property), 225
 - phase_basis() (in module qutip.core.states), 246
 - photocurrent_mesolve() (in module qutip.solve.stochastic), 293
 - photocurrent_sesolve() (in module qutip.solve.stochastic), 293
 - Pim (class in qutip.solve.piqs), 214
 - pisolve() (Dicke method), 213

<code>plot_energy_levels()</code> (in module <code>qutip.visualization</code>), 318	<code>PulseGenRandom</code> (class in <code>qutip.control.pulsegen</code>), 232
<code>plot_expectation_values()</code> (in module <code>qutip.visualization</code>), 318	<code>PulseGenSaw</code> (class in <code>qutip.control.pulsegen</code>), 233
<code>plot_fock_distribution()</code> (in module <code>qutip.visualization</code>), 319	<code>PulseGenSine</code> (class in <code>qutip.control.pulsegen</code>), 233
<code>plot_points()</code> (<i>Bloch3d method</i>), 192	<code>PulseGenSquare</code> (class in <code>qutip.control.pulsegen</code>), 233
<code>plot_qubism()</code> (in module <code>qutip.visualization</code>), 319	<code>PulseGenTriangle</code> (class in <code>qutip.control.pulsegen</code>), 233
<code>plot_schmidt()</code> (in module <code>qutip.visualization</code>), 320	<code>PulseGenZero</code> (class in <code>qutip.control.pulsegen</code>), 232
<code>plot_spin_distribution_2d()</code> (in module <code>qutip.visualization</code>), 320	<code>purity()</code> (<i>Qobj method</i>), 182
<code>plot_spin_distribution_3d()</code> (in module <code>qutip.visualization</code>), 321	<code>purity_dicke()</code> (in module <code>qutip.solve.piqs</code>), 312
<code>plot_vectors()</code> (<i>Bloch3d method</i>), 193	Q
<code>plot_wigner()</code> (in module <code>qutip.visualization</code>), 321	<code>qdiags()</code> (in module <code>qutip.core.operators</code>), 255
<code>plot_wigner_fock_distribution()</code> (in module <code>qutip.visualization</code>), 321	<code>QDistribution</code> (class in <code>qutip.distributions</code>), 217
<code>plot_wigner_sphere()</code> (in module <code>qutip.visualization</code>), 322	<code>qeye()</code> (in module <code>qutip.core.operators</code>), 256
<code>position()</code> (in module <code>qutip.core.operators</code>), 255	<code>QFunc</code> (class in <code>qutip</code>), 193
<code>prev()</code> (<i>HierarchyADOs method</i>), 205	<code>qfunc()</code> (in module <code>qutip.wigner</code>), 313
<code>process_fidelity()</code> (in module <code>qutip.core.metrics</code>), 276	<code>qload()</code> (in module <code>qutip.fileio</code>), 340
<code>proj()</code> (<i>Qobj method</i>), 181	<code>Qobj</code> (class in <code>qutip.core.qobj</code>), 175
<code>project()</code> (<i>Distribution method</i>), 216	<code>QobjEvo</code> (class in <code>qutip.core.cy.qobjevo</code>), 184
<code>projection()</code> (in module <code>qutip.core.states</code>), 246	<code>qppt()</code> (in module <code>qutip.tomography</code>), 323
<code>prop()</code> (<i>Dynamics property</i>), 226	<code>qppt_plot()</code> (in module <code>qutip.tomography</code>), 324
<code>prop_grad()</code> (<i>Dynamics property</i>), 226	<code>qppt_plot_combined()</code> (in module <code>qutip.tomography</code>), 324
<code>propagator()</code> (in module <code>qutip.solver.propagator</code>), 306	<code>qsave()</code> (in module <code>qutip.fileio</code>), 340
<code>propagator()</code> (<i>MemoryCascade method</i>), 210	<code>qutip</code> module, 342
<code>propagator_steadystate()</code> (in module <code>qutip.solver.propagator</code>), 306	<code>qutip.continuous_variables</code> module, 277
<code>PropagatorComputer</code> (class in <code>qutip.control.propcomp</code>), 227	<code>qutip.control.pulsegen</code> module, 338
<code>PropCompApproxGrad</code> (class in <code>qutip.control.propcomp</code>), 227	<code>qutip.control.pulseoptim</code> module, 325
<code>PropCompDiag</code> (class in <code>qutip.control.propcomp</code>), 227	<code>qutip.core.dimensions</code> module, 268
<code>PropCompFrechet</code> (class in <code>qutip.control.propcomp</code>), 227	<code>qutip.core.expect</code> module, 270
<code>pseudo_inverse()</code> (in module <code>qutip.solver.steadystate</code>), 303	<code>qutip.core.metrics</code> module, 274
<code>ptrace()</code> (in module <code>qutip.core.qobj</code>), 260	<code>qutip.core.operators</code> module, 250
<code>ptrace()</code> (<i>Qobj method</i>), 182	<code>qutip.core.qobj</code> module, 260
<code>PulseGen</code> (class in <code>qutip.control.pulsegen</code>), 231	<code>qutip.core.states</code> module, 238
<code>PulseGenCrab</code> (class in <code>qutip.control.pulsegen</code>), 233	<code>qutip.core.superop_reps</code> module, 266
<code>PulseGenCrabFourier</code> (class in <code>qutip.control.pulsegen</code>), 234	<code>qutip.core.superoperator</code> module, 264
<code>PulseGenGaussian</code> (class in <code>qutip.control.pulsegen</code>), 233	<code>qutip.core.tensor</code> module, 270
<code>PulseGenGaussianEdge</code> (class in <code>qutip.control.pulsegen</code>), 233	<code>qutip.entropy</code> module, 272
<code>PulseGenLinear</code> (class in <code>qutip.control.pulsegen</code>), 232	<code>qutip.fileio</code> module, 339
<code>PulseGenPeriodic</code> (class in <code>qutip.control.pulsegen</code>), 232	<code>qutip.ipynbtools</code> module, 341

qutip.matplotlib_utilities
 module, 323
 qutip.measurement
 module, 279
 qutip.orbital
 module, 322
 qutip.partial_transpose
 module, 271
 qutip.random_objects
 module, 260
 qutip.solve.nonmarkov.transfertensor
 module, 324
 qutip.solve.pigs
 module, 308
 qutip.solve.stochastic
 module, 292
 qutip.solver.brmsolve
 module, 287
 qutip.solver.correlation
 module, 299
 qutip.solver.floquet
 module, 288
 qutip.solver.heom
 module, 297
 qutip.solver.krylovsolve
 module, 286
 qutip.solver.mcsolve
 module, 284
 qutip.solver.mesolve
 module, 283
 qutip.solver.parallel
 module, 340
 qutip.solver.propagator
 module, 306
 qutip.solver.scattering
 module, 306
 qutip.solver.sesolve
 module, 282
 qutip.solver.spectrum
 module, 303
 qutip.solver.steadystate
 module, 303
 qutip.three_level_atom
 module, 264
 qutip.tomography
 module, 323
 qutip.utilities
 module, 339
 qutip.visualization
 module, 316
 qutip.wigner
 module, 313
 qutrit_basis() (in module qutip.core.states), 246
 qutrit_ops() (in module qutip.core.operators),
 256
 qzero() (in module qutip.core.operators), 256

R

rand_dm() (in module qutip.random_objects), 260
 rand_herm() (in module qutip.random_objects),
 261
 rand_ket() (in module qutip.random_objects), 262
 rand_stochastic() (in module
 qutip.random_objects), 262
 rand_super() (in module qutip.random_objects),
 262
 rand_super_bcsz() (in module
 qutip.random_objects), 263
 rand_unitary() (in module
 qutip.random_objects), 263
 recompute_evolution() (TSlotCompUpdateAll
 method), 231
 refresh_drift_attribs() (Dynamics method),
 226
 render() (Bloch method), 190
 report() (Stats method), 235
 reset() (FidCompTraceDiff method), 230
 reset() (FidCompTraceDiffApprox method), 230
 reset() (FidCompUnitary method), 229
 reset() (FidelityComputer method), 228
 reset() (PropagatorComputer method), 227
 reset() (PropCompApproxGrad method), 227
 reset() (PropCompDiag method), 227
 reset() (PropCompFrechet method), 227
 reset() (PulseGen method), 232
 reset() (PulseGenCrab method), 234
 reset() (PulseGenCrabFourier method), 234
 reset() (PulseGenGaussian method), 233
 reset() (PulseGenGaussianEdge method), 233
 reset() (PulseGenLinear method), 232
 reset() (PulseGenPeriodic method), 233
 reset() (PulseGenRandom method), 232
 Result (class in qutip.solver.result), 211
 resultclass (FMESolver attribute), 288
 resultclass (HEOMSolver attribute), 196
 rhot() (MemoryCascade method), 210
 run() (FMESolver method), 288
 run() (HEOMSolver method), 196
 run_optimization() (Optimizer method), 219
 run_optimization() (OptimizerBFGS method),
 219
 run_optimization() (OptimizerCrabFmin
 method), 221
 run_optimization() (OptimizerLBFGSB
 method), 220

S

save() (Bloch method), 190
 save() (Bloch3d method), 193
 save_amps() (Dynamics method), 226
 scattering_probability() (in module
 qutip.solver.scattering), 306
 serial_map() (in module qutip.solver.parallel),
 341
 sesolve() (in module qutip.solver.sesolve), 282

- SESolver (class in *qutip.solver.sesolve*), 194
 set_label_convention() (Bloch method), 190
 set_optim_var_vals() (PulseGenCrab method), 234
 set_phase_option() (FidCompUnitary method), 229
 show() (Bloch method), 191
 show() (Bloch3d method), 193
 sigmam() (in module *qutip.core.operators*), 257
 sigmap() (in module *qutip.core.operators*), 257
 sigmax() (in module *qutip.core.operators*), 257
 sigmay() (in module *qutip.core.operators*), 257
 sigmaz() (in module *qutip.core.operators*), 258
 simdiag() (in module *qutip*), 342
 singlet_state() (in module *qutip.core.states*), 246
 sinm() (Qobj method), 182
 smepdpsolve() (in module *qutip.solve.stochastic*), 293
 smesolve() (in module *qutip.solve.stochastic*), 294
 solve() (Pim method), 215
 spectrum() (in module *qutip.solver.spectrum*), 303
 spectrum_correlation_fft() (in module *qutip.solver.spectrum*), 303
 sphereplot() (in module *qutip.visualization*), 322
 spin_algebra() (in module *qutip.solve.piqs*), 312
 spin_coherent() (in module *qutip.core.states*), 246
 spin_Jm() (in module *qutip.core.operators*), 258
 spin_Jp() (in module *qutip.core.operators*), 258
 spin_Jx() (in module *qutip.core.operators*), 258
 spin_Jy() (in module *qutip.core.operators*), 258
 spin_Jz() (in module *qutip.core.operators*), 259
 spin_q_function() (in module *qutip.wigner*), 314
 spin_state() (in module *qutip.core.states*), 247
 spin_wigner() (in module *qutip.wigner*), 314
 spost() (in module *qutip.core.superoperator*), 265
 spre() (in module *qutip.core.superoperator*), 265
 sprepost() (in module *qutip.core.superoperator*), 265
 sqrtm() (Qobj method), 183
 squeeze() (in module *qutip.core.operators*), 259
 squeezing() (in module *qutip.core.operators*), 259
 ssepdpsolve() (in module *qutip.solve.stochastic*), 294
 ssesolve() (in module *qutip.solve.stochastic*), 295
 start() (FMESolver method), 289
 start() (HEOMSolver method), 197
 state() (FloquetBasis method), 290
 state_degeneracy() (in module *qutip.solve.piqs*), 313
 state_index_number() (in module *qutip.core.states*), 247
 state_number_enumerate() (in module *qutip.core.states*), 247
 state_number_index() (in module *qutip.core.states*), 248
 state_number_qobj() (in module *qutip.core.states*), 248
 Stats (class in *qutip.control.stats*), 234
 steady_state() (HEOMSolver method), 197
 steadystate() (in module *qutip.solver.steadystate*), 304
 steadystate_floquet() (in module *qutip.solver.steadystate*), 305
 step() (FMESolver method), 289
 stochastic_solvers() (in module *qutip.solve.stochastic*), 295
 super_tensor() (in module *qutip.core.tensor*), 270
 superradiant() (in module *qutip.solve.piqs*), 313
 sys_dims() (HEOMSolver property), 198
- ## T
- tau1() (Pim method), 215
 tau2() (Pim method), 215
 tau3() (Pim method), 215
 tau4() (Pim method), 215
 tau5() (Pim method), 215
 tau6() (Pim method), 215
 tau7() (Pim method), 215
 tau8() (Pim method), 215
 tau9() (Pim method), 215
 tau_column() (in module *qutip.solve.piqs*), 313
 tau_valid() (Pim method), 215
 temporal_basis_vector() (in module *qutip.solver.scattering*), 307
 temporal_scattered_state() (in module *qutip.solver.scattering*), 307
 tensor() (in module *qutip.core.tensor*), 271
 tensor_contract() (in module *qutip.core.tensor*), 271
 TerminationConditions (class in *qutip.control.termcond*), 221
 terminator() (DrudeLorentzBath method), 201
 terminator() (DrudeLorentzPadeBath method), 202
 thermal_dm() (in module *qutip.core.states*), 249
 three_level_basis() (in module *qutip.three_level_atom*), 264
 three_level_ops() (in module *qutip.three_level_atom*), 264
 tidyup() (Qobj method), 183
 tidyup() (QobjEvo method), 188
 TimeslotComputer (class in *qutip.control.tslocomp*), 230
 to() (Qobj method), 183
 to() (QobjEvo method), 188
 to_chi() (in module *qutip.core.superop_reps*), 266
 to_choi() (in module *qutip.core.superop_reps*), 266
 to_floquet_basis() (FloquetBasis method), 290
 to_kraus() (in module *qutip.core.superop_reps*), 267
 to_stinespring() (in module *qutip.core.superop_reps*), 267

to_super() (in module *qutip.core.superop_reps*),
267
tr() (*Qobj* method), 183
tracedist() (in module *qutip.core.metrics*), 276
trans() (*Qobj* method), 183
trans() (*QobjEvo* method), 188
transform() (*Qobj* method), 184
triplet_states() (in module *qutip.core.states*),
249
trunc_neg() (*Qobj* method), 184
TSlotCompUpdateAll (class in
qutip.control.tslotcomp), 231
ttmsolve() (in module
qutip.solve.nonmarkov.transfertensor),
324
TTMSolverOptions (class in
qutip.solve.nonmarkov.transfertensor),
211
tunneling() (in module *qutip.core.operators*), 259
TwoModeQuadratureCorrelation (class in
qutip.distributions), 217
types (*BathExponent* attribute), 199

U

UnderDampedBath (class in *qutip.solver.heom*), 202
unflatten() (in module *qutip.core.dimensions*),
269
unit() (*Qobj* method), 184
unitarity() (in module *qutip.core.metrics*), 277
unitarity_check() (*Dynamics* method), 226
update() (*HarmonicOscillatorProbabilityFunction*
method), 217
update() (*HarmonicOscillatorWaveFunction*
method), 217
update() (*TwoModeQuadratureCorrelation*
method), 217
update_ctrl_amps() (*Dynamics* method), 226
update_fid_err_log() (*OptimDump* method),
237
update_grad_log() (*OptimDump* method), 237
update_grad_norm_log() (*OptimDump*
method), 237
update_psi() (*TwoModeQuadratureCorrelation*
method), 217
update_rho() (*TwoModeQuadratureCorrelation*
method), 217

V

variance() (in module *qutip.core.expect*), 270
vector_mutation (*Bloch* attribute), 191
vector_style (*Bloch* attribute), 191
vector_to_operator() (in module
qutip.core.superoperator), 266
vector_width (*Bloch* attribute), 191
version_table() (in module *qutip.ipynbtools*),
342
visualize() (*Distribution* method), 216

W

w_state() (in module *qutip.core.states*), 250
wigner() (in module *qutip.wigner*), 315
wigner_cmap() (in module
qutip.matplotlib_utilities), 323
wigner_covariance_matrix() (in module
qutip.continuous_variables), 278
WignerDistribution (class in
qutip.distributions), 216
writeout() (*DynamicsDump* method), 237
writeout() (*EvoCompDumpItem* method), 238
writeout() (*OptimDump* method), 237

Z

zero_ket() (in module *qutip.core.states*), 250